

Parallel typesetting for critical editions: the `reledpar` package*

Maïeul Rouquette[†]based on the original `ledpar` by Peter Wilson
Herries Press[‡]

Abstract

The `reledmac` package has been used for some time for typesetting critical editions. The `reledpar` package is an extension to `reledmac` which enables texts and their critical apparatus to be typeset in parallel, either in two columns or on pairs of facing pages.

`reledpar` provides many tools and options. Normally, they are all documented in this file. Also provided is a help folder, “examples”. The folder contains additional examples (although not for all cases). Examples starting by “3-” are for basic uses, those starting by “4-” are for advanced uses.

To report bugs, please go to ledmac’s GitHub page and click “New Issue”: <https://github.com/maieul/ledmac/issues/>. You must open an account with github.com to access my page (maieul/ledmac). GitHub accounts are free for open-source users. You can report bug in English or in French (better).

You can subscribe to the `reledmac` email list in:
<http://geekographie.maieul.net/146>

Contents

1 Introduction	5
1.1 Aim of this package	5
1.2 Historical overview	6
2 Options	6
2.1 Synchronization’s options	6
2.2 Other options	6
3 General	7

*This file (`reledpar.dtx`) has version number v2.8.0, last revised 2016/03/23.

[†]maieul at maieul dot net

[‡]herries dot press at earthlink dot net

4 Parallel columns	8
4.1 Basic use	8
4.2 Setting	8
4.2.1 Column's width	8
4.2.2 Column's separator	9
4.2.3 Column's positions	9
4.2.4 Mixing two columns and one column texts	9
5 Facing pages	10
5.1 Basic usage	10
5.2 Setting	10
5.2.1 Text width	10
5.2.2 Way of synchronizing	10
5.2.3 Page number	12
5.2.4 Page breaking	12
5.2.5 Right page before \Pages	12
5.2.6 Notes about \mainmatter	13
5.3 Critical and familiar footnotes	13
5.3.1 Notes height setting	13
5.3.2 About the numbering of familiar footnotes	13
5.3.3 Using perpage package	14
5.3.4 Notes for one side only	14
5.3.5 Familiar notes called in the right side, but to be printed in the left side	14
5.4 Using line flag	15
6 Left and right texts	15
6.1 Environments	15
6.2 Numbering text lines and paragraphs	15
6.3 Lineation system	16
6.4 Chunks	17
6.5 \AtEveryPstart and \AtEveryPstartCall	17
6.6 Language setting	18
7 Verse	18
8 Side notes	19
9 Parallel ledgroups	19
9.1 General	19
9.2 Parallel ledgroups and setspace package	20
10 Sectioning commands	20
11 Notes about page number	20
I Implementation overview	22

II Preliminaries	22
II.1 Package's meta-data	22
II.2 Package's requirement	22
II.3 Package's options	22
II.4 Package's options	23
II.4.1 Synchronization's options	23
II.4.2 Other options	24
II.5 Determining side and category of parallel processing	24
II.6 Text's width	25
II.7 Messages	25
III Sectioning commands	27
IV Line counting	31
IV.1 Setting lineation reset	31
IV.2 Setting line number margin	32
IV.3 Setting lineation start and step	33
IV.4 Setting line flag	34
IV.5 Setting line number style	34
IV.6 Print marginal line number	35
IV.7 Line-number counters and lists	35
IV.7.1 Correspond to those in <code>reledmac</code> for regular or left text	35
IV.7.2 Specific to <code>reledpar</code>	36
IV.8 Reading the line-list file	36
IV.9 Commands within the line-list file	37
IV.10 Writing to the line-list file	43
V Marking text for notes	45
V.1 Specific hooks and commands for notes	45
V.1.1 Notes to be printed on one side only	45
V.2 Tools specific to familiar footnotes	45
V.2.1 Managing correct number	46
V.2.2 Familiar footnotes without marks	46
V.2.3 Get correct footnote number	48
V.3 Create hooks	48
V.4 Init standards series (A,B,C,D,E,Z)	48
V.5 Tools specific to <code>L<small>A</small>T<small>E</small>X</code> 's classical footnotes	49
VI Pstart numbers dumping and restoration	49
VII Parallel environments	50
VIII Paragraph decomposition and reassembly	52
VIII.1 Boxes, counters, <code>\pstart</code> and <code>\pend</code>	52
VIII.2 Processing one line	57
VIII.3 Line and page number computation	62
VIII.4 Line number printing	65

VIII.5 Pstart number printing in side	67
VIII.6 Add insertions to the vertical list	69
VIII.7 Penalties	69
VIII.8 Printing leftover notes	70
IX Footnotes	71
IX.1 Footnotes output specific to \Pages	71
X Cross referencing	75
XI Side notes	76
XII Familiar footnotes	77
XIII Verse	77
XIV Naming macros	79
XV Fixing babel and polyglossia	80
XVI Counts and boxes for parallel texts	82
XVII Checking text to be processed	84
XVIII Parallel columns	85
XIX Parallel pages	93
XIX.1 Specific counters	93
XIX.2 Main macro	94
XIX.3 Ensure all notes be printed at the end of parallel pages	100
XIX.4 Struts	100
XIX.5 Page clearing	101
XIX.6 Lines managing	102
XIX.7 Page break managing	103
XIX.8 Getting boxes content	106
XX Page numbering	111
XX.1 Global options	111
XX.2 mainmatter option of \Pages	113
XXI Sections' titles' commands	113
XXII Page break/no page break, depending on the specific line	114
XXIII Parallel ledgroup	115
XXIV Compatibility with eledmac	118

XXV The End	119
Appendix A Some things to do when changing version	120
Appendix A.1 Migration to <code>eledpar</code> 1.4.3	120
Appendix A.2 Migration from <code>eledpar</code> to <code>reledpar</code>	120
Appendix A.2.1 Deprecated options	120
Appendix A.2.2 \renewcommand replaced with command	120
Appendix A.2.3 Commands the names of which have changed	121
Appendix A.3 Migration to <code>reledpar</code> 2.2.0	121
Appendix A.4 Migration to <code>reledpar</code> 2.3.0	121
Appendix A.5 Migration to <code>reledpar</code> 2.4.0	121
Appendix A.6 Migration to <code>reledpar</code> 2.5.0	121
Appendix A.7 Migration to <code>reledpar</code> 2.6.0	121
Appendix A.8 Migration to <code>reledpar</code> 2.6.1	121
References	122
Index	122
Change History	140

1 Introduction

1.1 Aim of this package

Some critical editions contain texts in more than one form, such as a set of verses in one language and their translations in another. In such cases there is a desire to be able to typeset the two texts, together with any critical apparatus, in parallel. The `reledpar` package is an extension to `reledmac` that enables two texts and their apparatus to be set in parallel, either in two columns or on pairs of facing pages.

The package has to try and coerce \TeX into paths it was not designed for. Use of the package, therefore, may produce some surprising results. In this case, please reports them to the author via github's issues: <https://github.com/maieul/ledmac/issues/>.

This manual contains a general description of how to use `reledpar` starting in section 3; the complete source code for the package, with extensive documentation (in sections I through XXV); and an Index to the source code. As `reledpar` is an adjunct to `reledmac` we assume that you have read the `reledmac` manual. Also `reledpar` requires `reledmac` to be used, in the version distributed with version.

You do not need to read the source code for this package in order to use it but doing so may help to answer any questions you might have. The documentation's sections are numbered in roman numeral.

On a first reading, We suggest that you should skip anything after the general documentation in first sections until I, unless you are particularly interested in the innards of `reledpar`.

1.2 Historical overview

Many of the code of this package is based on the `eledpar` package, which was based on the `ledpar`, created as an extension of the `ledmac` package.

Names of the package related to parallel typesetting have moved in parallel of names of the package related to critical edition.

Please read `reledmac`'s handbook in order to understand this evolution.

2 Options

The package can be loaded with a number of global options which are listed here. Those options are fully described in the paragraphs devoted to their feature.

2.1 Synchronization's options

Please read the paragraph on synchronization's option on 5.2.2 p. 10 to understand better those options.

shiftedpstarts prevents white space between paragraphs on facing pages, the white space necessary to sync pages is collected at the bottom of the page instead.

advancedshiftedpstarts does the same as `shiftedpstarts`, but the pstart shift are not counted to determine when cutting the page. That could help to avoid page with blank lines at the bottom.

nomaxlines allows facing pages to have different numbers of lines.

nosyncpstarts disables syncing on facing pages. In that case the pages are filled as two streams normal.

2.2 Other options

parledgroup allows the use of `ledgroup` environment with `reledpar`.¹

widthliketwocolumns set the width of the text printed in a single column to be the same as the width of the text printed in two parallel columns with `reledpar`. This is useful when alternating between normal and parallel typesetting.²

sameparallelpagENUMBER sets page numbers on facing pages to the same value.

prevpgnotnumbered enables that the page before facing pages (the one automatically inserted to start parallel pages on a left page) is not counted. This applies only if the page is empty.

¹This option can either be used on `reledmac` or `reledpar`.

²This option can either be used on `reledmac` or `reledpar`.

3 General

A file may mix *numbered* and *unnumbered* text. Numbered text is printed with marginal line numbers and can include footnotes and endnotes that are referenced to those line numbers: this is how you will want to print the text that you are editing. Unnumbered text is not printed with line numbers, and you can't use `reledmac`'s note commands with it: this is appropriate for introductions and other material added by the editor around the edited text.

The `reledpar` package lets you typeset two *numbered* texts in parallel³. This can be done either as setting the ‘Leftside’ and ‘Rightside’ texts in two columns or on facing pages. In the paired pages case footnotes are placed at the bottom of the page on which they are called out – that is, footnotes belonging to the left are set at the foot of a left (even numbered) page, and those for right texts are at the bottom of the relevant right (odd numbered) page. However, in the columnar case, all footnotes are set at the bottom left of the page on which they are called out – they are not set below the relevant column. The line numbering schemes need not be the same for the two texts.

`reledmac` essentially puts each chunk of numbered text (the text within a `\pstart ... \pend`) into a box and then following the `\pend` extracts the text line by line from the box to number and print it. More precisely, the text is first put into the box as though it was being typeset as normal onto a page and any notes are stored without being typeset. Then each typeset line is extracted from the box and any notes for that line are recalled. The line, with any notes, is then output for printing, possibly with a line number attached. Effectively, all the text is typeset and then afterwards all the notes are typeset.

`reledpar` similarly puts the left and right chunks into boxes but can't immediately output the text after a `\pend` – it has to wait until after both the left and right texts have been collected before it can start processing. This means that several boxes are required and possibly TeX has to store a lot of text in its memory; both the number of potential boxes and memory are limited. If TeX's memory is overfilled the recourse is to reduce the amount of text stored before printing.

`\maxchunks` It is possible to have multiple chunks in the left and right texts before printing them. The macro `\maxchunks{<num>}` specifies the maximum number of chunks within the left or right texts. This is initially set as:

`\maxchunks{5120}`

meaning that there can be up to 5120 chunks in the left text and up to 5120 chunks in the right text, requiring a total of 10240 boxes. If you need more chunks then you can increase `\maxchunks`. The `\maxchunks` must be called in the preamble.

If you `\maxchunks` is too little you can get a `reledpar` error message along the lines: “Too many `\pstart` without printing. Some text will be lost.” then you will have to either increase `\maxchunks` or use the parallel printing commands (`\Columns` or `\Pages`) more frequently.

When typesetting verse using `\stanza`, each line is treated as a chunk, so be warned that if you are setting parallel verses you might have to increase `\maxchunks` much more than it appears at first sight.

³You can use, anyway, `\numberlinefalse` to disable printing of line numbers.

In general, `reledmac` is a TeX resource hog, and `reledpar` only makes things worse in this respect.

4 Parallel columns

4.1 Basic use

`pairs` Numbered text that is to be set in columns must be within a `pairs` environment. Within the environment the text for the lefthand and righthand columns is placed within the `Leftside` and `Rightside` environments, respectively; these are described in more detail below in section 6.

`\Columns` The command `\Columns` typesets the texts in the previous pair of `Leftside` and `Rightside` environments. The general scheme for parallel columns looks like this:

```
\begin{pairs}
\begin{Leftside} ... \end{Leftside}
\begin{Rightside} ... \end{Rightside}
\end{pairs}
\Columns
\begin{pairs}
\begin{Leftside} ... \end{Leftside}
...
\end{pairs}
\Columns
```

`\AtBeginPairs` Keep in mind that the `\Columns` **must be** outside of the `pairs` environment. You can use the macro `\AtBeginPairs` to insert a code at the beginning of each `pairs` environments. That could be useful to add the `\sloppy` macro to prevent overfull hboxes in two columns.

```
\AtBeginPairs{\sloppy}
```

There is no required pagebreak before or after the columns.

4.2 Setting

4.2.1 Column's width

`\Lcolwidth` `\Rcolwidth` The lengths `\Lcolwidth` and `\Rcolwidth` are the widths of the left and right columns, respectively. By default, these are:

```
\setlength{\Lcolwidth}{0.45\textwidth}
\setlength{\Rcolwidth}{0.45\textwidth}
```

They may be adjusted if one text tends to be ‘bulkier’ than the other.

4.2.2 Column's separator

`\columnrulewidth`
`\columnseparator`

The macro `\columnseparator` is called between each left/right pair of lines. By default it inserts a vertical rule of width `\columnrulewidth`. As this is initially defined to be 0pt the rule is invisible. For a visible rule between the columns you could try:
`\setlength{\columnrulewidth}{0.4pt}`

You can also modify `\columnseparator` if you want more control.

4.2.3 Column's positions

`\columnsposition`

By default, columns are positioned to the right of the page. However, you can use `\columnsposition{L}` to align them to the left, or `\columnsposition{C}` to center them.

When you use `\stanza`, the visible rule may shift when a verse has a hanging indent. To prevent shifting, use `\setstanzaindent`s outside the `Leftside` or `Rightside` environment.

By default, the spaces around column separator are the same as the space:

- On the left of columns, if columns are aligned right.
- On the right of columns, if columns are aligned left.
- On both the left and right columns, if columns are centered.

You can redefine `\beforecolumnseparator` and `\aftercolumnseparator` length to define spaces before or after the column separator, instead of letting `reledpar` calculate them automatically.

```
\setlength{\beforecolumnseparator}{length}
\setlength{\aftercolumnseparator}{length}
```

If you want to revert to the previous behavior, just set with a negative value.

4.2.4 Mixing two columns and one column texts

`\widthliketwocolumns`

If you want to mix two-column with single-column text, you can align horizontally single-column text to two-column text with `\widthliketwocolumnstrue`. To reset this feature, use `\widthliketwocolumnsfalse`. You can also use `widthliketwocolumns` as a global option when loading `reledmac` or `reledpar`.

In most cases, you should use `\widthliketwocolumns` in combination with `\noteswidthliketwocolumns` and `\notesXwidthliketwocolumns` to align the critical/familiar footnotes with the two columns. See `reledmac`'s handbook for more details.

If you want to have continuous line numbers between multiple columns and single columns, use the `continuousnumberingwithcolumns` option when loading `reledmac` or `reledpar`. You will need to use `\pausenumbering...\\resumenumbering` instead of `\endnumbering...\\endnumbering` (see 4.2.7 p. 18).

5 Facing pages

5.1 Basic usage

`pages` Numbered text that is to be set on facing pages must be within a `pages` environment. Within the environment the text for the lefthand and righthand pages is placed within the `Leftside` and `Rightside` environments, respectively.

`\Pages` The command `\Pages` typesets the texts in the previous pair of `Leftside` and `Rightside` environments. The general scheme for parallel pages looks like this:

```
\begin{pages}
\begin{Leftside} ... \end{Leftside}
\begin{Rightside} ... \end{Rightside}
\begin{Leftside} ... \end{Leftside}
...
\end{pages}
\Pages
```

The `Leftside` text is set on lefthand (even numbered) pages and the `Rightside` text is set on righthand (odd numbered) pages. Each `\Pages` command starts a new even numbered page. After parallel typesetting is finished, a new page is started. Note that the `\Pages` **must be** outside of the `pages` environment.

5.2 Setting

5.2.1 Text width

`\Lcolwidth` `\Rcolwidth` Within the `pages` environment the lengths `\Lcolwidth` and `\Rcolwidth` are the widths of the left and right pages, respectively. By default, these are set to the normal `textwidth` for the document, but can be changed within the environment if necessary.

5.2.2 Way of synchronizing⁴

Synchronization of left and right texts in parallel processing requires some ‘numbered’ auxiliary files to be written (namely `.1`, `.1R`, `.2`, `.2R`, and so forth), the content of which may change as long as synchronization is not complete. This usually requires LaTeX to be run several times. Therefore, it is advised to use in conjunction utilities such as `latexmk` to ensure that synchronization is complete.

Numbered paragraphs which are contained between the `\pstart` and `\pend` macros are thereafter called ‘chunks’.

In short, the default setting is designed in such a way that corresponding chunks of text are always kept in synchronization, even at the cost of page padding, as it may result in leaving blank lines between chunks of text. Conversely, using in conjunction `advancedshiftedpstarts` and `nomaxlines` settings ensures that pages are filled with text to full advantage—at the cost of the chunks not being kept in synchronization—and every chunk starts on the facing page of its corresponding chunk.

⁴There is a French version of this article on <http://geekographie.maieul.net/185>.

To understand better how each of the synchronization settings of `reledpar` works, one must first understand how the default setting of `reledpar` synchronizes the left and right chunks.

The aim of the default setting is twofold:

- To ensure that left pages contain what is to be on left sides and that right pages contain what is to be on right sides.
- To ensure that every chunk starts on the page that is facing its corresponding chunk.

As regards the latter, `reledpar` checks that both of the following rules are respected:

- The numbers of lines of every pair of chunks must be identical. To keep this rule, `reledpar` may insert some blank lines at the bottom of the chunk that is shorter so that it may eventually have the same number of lines as the one that is longer.
- The main content of two facing pages, apart from critical and familiar footnotes, must have the same numbers of lines, including those that may be blank. Consequently, if one left page contains more notes than the corresponding right page, the bottom of the right page must be left blank.

Each of these rules can be modified by a number of optional synchronization settings in `reledpar`:

1. Regarding the number of lines a pair of chunks may have:
 - (a) 'shiftedpstarts' setting merely moves any added blank lines from the bottom of the chunks to the bottom of the page. It does not allow to have more lines on a given page as it just removes the blank lines between the chunks and does nothing more. To understand better how this work, you may compare the total amounts of lines of text on a given page whether you have activated this setting or not: you will see that both amounts are the same.
 - (b) 'advancedshiftedpstarts' prevents any blank lines from being inserted at the bottom of the chunks, also taking them away from the total amount of lines the page may have. This allows to get more lines on the pages. However, please note that:
 - Blank lines are taken into account as `reledpar` moves from one to the following chunk of text, so that every pair of chunks may always start on the same facing pages.
 - Consequently, blank lines continue to be taken into account in the calculation of the amount of lines a given pair of pages may have. This is why when a longer chunk runs from one page to another the shorter corresponding one also runs across pages, even if this may result in some blank vertical space being left on the first page.
2. As regards the number of lines per page, including blank ones, the `nomaxlines` setting disregards the rule that forces two facing pages to have the same numbers

of lines. So it allows to have more text on the pages. Then, by a complex mechanism it is ensured that two corresponding chunks may always start on the same facing pages, provided that `shiftedpstarts` or `advancedshiftedpstarts` settings shall not be activated.

Lastly, one may disregard all of the synchronization rules and content himself with parallel texts typesetting. To achieve this, please use the `nosyncpstarts` setting.

Please note that every change of synchronization setting resets the content of the ‘numbered’ auxiliary files to make sure that `reledpar` does not try to make the synchronization with wrong calculations.

5.2.3 Page number

By default, `\Pages` use the standard L^AT_EX page number scheme. This means that pages are numbered continuously following printed-book conventions: from left-hand to right-hand side, left-hand pages having even numbers, right-hand pages having odd numbers.

However, you can use the package option `sameparallelpagenumber` to have the same page number for both left and right side. In this case, this setting will apply only for pages typeset by `\Pages`, not for “normal” pages.

Please also read advising in 11 p. 20.

5.2.4 Page breaking

`\setgoalfraction`

When doing parallel pages `reledpar` has to guess where T_EX is going to put pagebreaks and hopefully get there first in order to put the pair of texts on their proper pages. When it thinks that the fraction `\@goalfraction` of a page has been filled, it finishes that page and starts on the other side’s text. The standard value is 0.9.

If you think you can get more on a page, increase this. On the other hand, if some left text overflows onto an odd numbered page or some right text onto an even page, try reducing it. You can change it using `\setgoalfraction{<newvalue>}`.

5.2.5 Right page before `\Pages`

When `\Pages` are called, it starts at a new left page, in order to have parallel pages. Consequently, if it is called on a left page, it clears the current page and then lets a right void page.

`reledpar` provides two options to customize this (eventual) right page.

`prevpgstyle=<style>` in order to set the style of this page. A common value of `<style>` is empty. Use `prevpgstyle=empty` will suppress header and footer in this page.
Please also read advising in 11 p. 20.

`prevpgnotnumbered` will make this page won’t be counted in the page counter.

5.2.6 Notes about \mainmatter

If you use `\frontmatter`, do not use `\mainmatter` directly before `\Pages` because it could create spurious empty pages.

Use instead `\pages` with the optional argument `[mainmatter]`. In this case, the content of `\Pages` will start on a left side, without any spurious empty page, and the left pages will be odd (and not even like in normal way), the first one being 1.

5.3 Critical and familiar footnotes

Of course, in “Facing pages”, the `reledmac`’s both critical and familiar footnotes can be used. However, some specific points must be taken into consideration.

5.3.1 Notes height setting

Since `eledpar` v1.13.0, long notes in facing pages can flow from left to right pages, and *vice-versa*.

However, the `reledmac` default setting for the maximum allotted size to notes is greater than `\textheight`. That makes impossible for long notes to flow across pages.⁵ We have not changed this default setting, because we do not want to break compatibility with older version of `reledmac` and we want to be as close as possible to default `LATEX`’s feature.

So, you MUST change the default setting via `\Xmaxhnotes` (for critical notes) and `\maxhnotesX` (for familiar notes). Both commands are explained in `reledmac` handbook (6.11.5 p. 39). As an advisable setting:

```
\AtBeginDocument{%
    \Xmaxhnotes{0.6\textheight}
    \maxhnotesX{0.6\textheight}
}
```

5.3.2 About the numbering of familiar footnotes

If you use the same series of familiar footnotes on both sides, the numbers won’t be correct in the first run. There will be a continuous numbering for left notes, and a continuous numbering for right notes. However, after the second run, the numbering will be continuous, alternating between the left and right side. For example if you have two left pages and two right pages, with one note by page, you will obtain the following numbering at the first run: 1 (left page), 3 (right page), 2 (left page), 4 (right page). But at the next run, you will obtain: 1 (left page), 2 (right page), 3 (left page), 4 (right page).

If you use parallel columns, during the second of run of typesetting the footnote numbering will not run down the columns. Instead, it will read both column lines completely across the page, and number footnotes from left to right.

⁵The same applies to `LATEX` normal notes. Read <http://tex.stackexchange.com/a/228283/7712> for technical informations.

5.3.3 Using `\perpage` package

It follows from what has been said in the preceding paragraph that if you use the `\MakePerPage` command of the `\perpage` package for footnotes called in parallel typesetting, you must append to the counter the suffix `@typeset`.

So do not set:

```
\MakePerPage{footnote}
\MakePerPage{footnoteA}
\MakePerPage{footnoteB}
```

But set:

```
\MakePerPage{footnote@typeset}
\MakePerPage{footnoteA@typeset}
\MakePerPage{footnoteB@typeset}
```

5.3.4 Notes for one side only

`\Xonlyside` `\onlysideX` You may want to typeset notes on one side only (either left or right). Use `\Xonlyside[⟨s⟩]{⟨p⟩}` to set critical notes, and `\onlysideX[⟨s⟩]{⟨p⟩}` to set familiar notes. `⟨p⟩` must be set to L for notes to be confined only on the left side and to R for notes to be confined only on the right side.

5.3.5 Familiar notes called in the right side, but to be printed in the left side

`\footnoteXnomk` `\footnoteXmk` As often happens, the left side has less room for text. We may want to call familiar notes in the right side while using at the same time the available space in the left side to print them.

To achieve this, we call `\footnoteXnomk{⟨notecontent⟩}` in the left side. X is to be replaced by the series letter. We do this call in the left side after the word which matches up to the one in the right side after which we want to insert the actual footnote mark.

In the right side, we call `\footnoteXmk` at the place we want to have the footnote mark. X is to be replaced by the series letter. For example:

```
\begin{Leftside}
\begin{numbering}
\pstart
A little cat\footnoteAnomk{A note.}. And so one ...
\pend
\end{numbering}
\end{Leftside}
\begin{Rightside}
\begin{numbering}
\pstart
Un petit chat\footnoteAmk. And so one ...
\pend
\end{numbering}

```

```
\end{Rightside}
```

5.4 Using line flag

`\Xlineflag` Use `\Xlineflag[⟨s⟩]` to add right line flag (6.3 p. 17) to right critical footnotes and
`\Xendlineflag` `\Xendlineflag[⟨s⟩]` to add it to right critical endnotes.

6 Left and right texts

6.1 Environments

Parallel texts are divided into `Leftside` and `Rightside`. The form of the contents of these two are independent of whether they will be set in columns or pages.

`Leftside` The left text is put within the `Leftside` environment and the right text likewise in
`Rightside` the `Rightside` environment. The number of `Leftside` and `Rightside` environments must be the same.

6.2 Numbering text lines and paragraphs

`\beginnumbering` Each section of numbered text must be preceded by `\beginnumbering` and followed by
`\endnumbering`, like:
`\beginnumbering`
`<text>`
`\endnumbering`

These have to be separately specified within `Leftside` and `Rightside` environments.

The `\beginnumbering` macro resets the line number to zero, reads an auxiliary file called `⟨jobname⟩.nn` (where `⟨jobname⟩` is the name of the main input file for this job, and nn is 1 for the first numbered section, 2 for the second section, and so on), and then creates a new version of this auxiliary file to collect information during this run. Separate auxiliary files are maintained for right hand texts and these are named `⟨jobname⟩.nnR`, using the 'R' to distinguish them from the left hand and serial (non-parallel) texts.

`\memorydump` The command `\memorydump` effectively performs an `\endnumbering` immediately followed by a `\beginnumbering` while not restarting the numbering sequence. This has the effect of clearing TeX's memory of previous texts and any associated notes, allowing longer apparent streams of parallel texts. The command should be applied to both left and right texts, and after making sure that all previous notes have been output. For example, along the lines of:

```
\begin{pages}
\begin{Leftside}
\beginnumbering
...
\end{Leftside}
\begin{Rightside}
\beginnumbering
```

```

...
\end{Rightside}
\end{pages}
\Pages
\begin{pages}
\begin{Leftside}
\memorydump
...
\end{Leftside}
\begin{Rightside}
\memorydump
...
\end{Rightside}
\end{pages}

```

It is possible to insert a number at every \pstart command. You must use the \numberpstarttrue command to have it. You can stop the numbering with \numberpstartfalse. You can redefine the commands \thepstartL and \thepstartR to change style. The numbering restarts on each \beginnumbering.

The command \skipnumbering when inserted in a line of parallel text causes the numbering of that particular line to be skipped. This can be useful if you are putting some kind of marker (even if it is only a blank line) between stanzas. Remember, parallel texts must be numbered and this provides a way to slip in an “unnumbered” line. When inserted into a numbered line the macro \hidenumbers causes the number for that particular line to be hidden; namely, no line number will print. Note that if you use it in \stanza, you must call it at the beginning of the verse.

6.3 Lineation system

```

\firstrlineum
\linenumincrement
\firsbtlinenum
\sublinenumincrement

\firstrlineum*
\linenumincrement*
\firsbtlinenum*
\sublinenumincrement*
\firstrlineumR
\linenumincrementR
\firsbtlinenumR
\sublinenumincrementR
\lineationR
\lineation*
\linenumberstyleR
\sublinenumberstyleR
\linenumberstyle*
\sublinenumberstyle*

```

Following \firstrlineum{<num>} the first line number will be <num>, and following \linenumincrement{<num>} only every <num>th line will have a printed number.

The lineation commands which finish by a R apply for right text. The lineation commands which are starred apply for both left and right texts. The lineation command which does not finish by a R and who are not starred apply for the left side. **However, these commands apply to right side when they are called inside a left environment. However, such features should not be used any more. The recommended practice is to add all setting commands to the preamble.**

The starred versions change both left and right numbering schemes.

The suffixed version change the right side, without regard to the position they are called.

\lineationR macro is the equivalent of reledmac \lineation macro for the right side.

\lineation* macro is the equivalent of reledmac \lineation macro for both sides.

\linenumberstyleR is the equivalent of reledmac \linenumberstyle for right text. \sublinenumberstyleR is the equivalent of reledmac \sublinenumberstyle right text. The starred version are for both side.

`\linenummarginR` `\linenummargin*` `\setRlineflag`

`\linenummarginR{<margin>}` sets the line margin for right side. `\linenummargin*{<margin>}` sets for both side. `<margin>` can be, as for reledmac's `\linenummargin` one of these values: `left`, `right`, `inner`, `outer`. A "R" is appended to the line numbers of the right texts. This may be useful for parallel columns but for parallel pages it might be more appropriate to redefine it using `\setRlineflag{<flag>}`. Use `\setRlineflag{}` to empty it.

`inenumberLevenifblanktrue` `inenumberRevenifblanktrue`

By default, when a blank line is printed on one side, in order to synchronize with the other side, no line number is printed. However, you can decide to print them for blank lines, also. Use `\inenumberLevenifblanktrue` to enable it on the left side, and `\inenumberRevenifblanktrue` to enable it on right side.

6.4 Chunks

`\pstart` `\pend`

In a serial (non-parallel) mode, each numbered paragraph, or chunk, is contained between the `\pstart` and `\pend` macros, and the paragraph is output when the `\pend` macro occurs. The situation is somewhat different with parallel typesetting as the left text (contained within `\pstart` and `\pend` groups within the `Leftside` environment) has to be set in parallel with the right text (contained within its own `\pstart` and `\pend` groups within the corresponding `Rightside` environment) the `\pend` macros cannot immediately initiate any typesetting — this has to be controlled by the `\Columns` or `\Pages` macros. Several chunks may be specified within a `Leftside` or `Rightside` environment. A multi-chunk text then looks like:

```
\begin{...side}
  % \beginnumbering
  \pstart first chunk \pend
  \pstart second chunk \pend
  ...
  \pstart last chunk \pend
  % \endnumbering
\end{...side}
```

Numbering, via `\beginnumbering` and `\endnumbering`, may extend across several `Leftside` or `Rightside` environments. Remember, though, that the left/right sides are effectively independent of each other.

`\autopar`

The `\autopar` macro can be used, instead of manually inserting `\pstart... \pends`. Please read reledmac's handbook (4.2.2 p. 16).

6.5 \AtEveryPstart and \AtEveryPstartCall

In general, remember that the moment where a `\pstart` is called is different from the moment when the `\pstart... \pend` content is printed, which is when `\Pages` or `\Columns` is processed.

Consequently:

- The argument of `\AtEveryPstart` (see 4.2.4 p. 17) is called before every chunk is printed, except if you used an optional argument for the `\pstart`.

- The argument of `\AtEveryPstartCall` is called before every `\pstart`.

6.6 Language setting

If you are using the `babel` package or the `polyglossia` package ,with different languages (via, say, `\selectlanguage`) for the left and right texts it is particularly important to select the appropriate language within the `Leftside` and `Rightside` environments. The initial language selected for the right text is the `babel` package's default. Also, it is the *last* language setting in a side that controls the language used in any notes for that side when they get printed. If you are using multilingual notes then it is probably safest to explicitly specify the language(s) for each note rather than relying on the language selection for the side. The right side language is also applied to the right side line numbers.

7 Verse

If you are typesetting verses with `reledmac` you can use the `\stanza` construct, and you can also use this in right or left parallel texts. In this case each verse line is a chunk which has two implications. (1) you can unexpectedly exceed the `\maxchunks` limit or the overall limit on the number of boxes, and (2) left and right verse lines are matched, which may not be desirable if one side requires more print lines for verse lines than the other does.

`astanza` `reledpar` provides an `astanza` environment which you can use instead of `\stanza`. A `astanza` environment is a chunk. Consequently left and right `verse` are matched, and not, as with standard `\stanza`, left and right `verse lines`.

Within the `astanza` environment each verse line is treated as an individual paragraph, so there must be no blank lines in the environment otherwise there will be some extraneous vertical spacing. To use `astanza`, simply replace `\stanza` by `\begin{astanza}` and add `\end{astanza}` after the ending `\&`.

The difference between `astanza` and `\stanza` is, that the latter syncs verse by verse, while the environment syncs stanza by stanza.

If you get an error message along the lines of ‘Missing number, treated as zero `\sza@0@`’ it is because you have forgotten to use `\setstanzaindent`s to set the stanza indents.

As `astanza` is a specify type `\pstart... \pend` structure, you can:

- Add optional argument (in brackets) after `\begin{astanza}`, as the optional argument of `\pstart`.
- Use optional argument after the last `\&` as optional argument of `\pend`.

`\sethangingsymbol`

Like in `reledmac`, you could use the `\sethangingsymbol` command to insert a character in each hanging line. If you use it, you must run `LATEX` two time. Example for the French typography

`\sethangingsymbol{[\,]}`

You can also use it to force hanging verse to be flush right:

```
\sethangingsymbol{\protect\hfill}
```

When you use `\lednomp` make sure to use it on both sides in the corresponding verses to keep the pages in sync.

`\thestanzaL` When using `\stanzanumtrue` (8.9 p. 44) in parallel typesetting, `stanza` counter is replaced by `stanzaL` counter in left side and by `stanzaR` counter in right side. Consequently, you can redefine `\thestanzaL` and `\thestanzaR` to change their aspect.

8 Side notes

As in `reledmac`, you must use one of the following commands to add side notes: `\ledsidenote`, `\ledleftnote`, `\ledrightnote`, `\ledouterote`, `\ledinnerote`.

The `\sidenotemargin` defines the margin of the sidenote for either left or right side, depending on the current environment. You can use `\sidenotemargin*` to define it for both sides.

9 Parallel ledgroups

9.1 General

You can also make parallel ledgroups (see the documentation of `reledmac` about ledgroups, 9 p. 45). To do it you have:

- To load `reledpar` package with the `parledgroup` option, or to add `\parledgrouptrue`.
- To push each ledgroup between `\pstart...``\pend` command.

See the following example:

```
\begin{pages}
  \begin{Leftside}
    \begin{numbering}
      \pstart
        \begin{ledgroup}
          ledgroup content
        \end{ledgroup}
      \pend
      \pstart
        \begin{ledgroup}
          ledgroup content
        \end{ledgroup}
      \pend
      \end{numbering}
    \end{Leftside}
    \begin{Rightside}
      \begin{numbering}
```

```
\pstart
  \begin{ledgroup}
    ledgroup content
  \end{ledgroup}
\pend
\pstart
  \begin{ledgroup}
    ledgroup content
  \end{ledgroup}
\pend
\endnumbering
\end{Rightside}
\end{pages}
\Pages
```

9.2 Parallel ledgroups and setspace package

If you use the `setspace` package and want your notes in parallel ledgroups to be single-spaced (not half-spaced or double-spaced), just add to your preamble:

```
\setparledgroupnotespacing{\singespacing}
```

In effect, to have correct spacing, do not change the font size of your notes.

10 Sectioning commands

The standard sectioning commands of `reledmac` are available, and provide parallel sectioning, for both two-column and two-page layout.

```
\eleedsectnotoc
\eleedsectmark
```

By default, the section commands of the right side are not added to the table of contents. But you can change it, using `\eleedsectnotoc{<arg>}`, where `<arg>` could be L (for left side) or R (for right side).

By default, the headers are tokens from the left side. You can change them, using `\eleedsectmark{<arg>}`, where `<arg>` could be L (for left side) or R (for right side).

11 Notes about page number

If you use `sameparallelpagenumber` option (5.2.3 p. 12 or `prevpgnotnumbered` option (5.2.5 p. 12), please read the following paragraph if you want to manipulate page numbers manually.

In order to implement these two options, `reledpar` uses its own page counter, called `par@page`. Consequently, if you use at least one of these options:

1. If you modify `\thepage` command, use the value of `par@page` counter inside and not the value of `page` counter.

2. If you want to modify a page number, modify the value of `page` counter AND the value `par@page` counter.

Notes that `reledpar` automatically do it when you use `\frontmatter` and `\mainmatter` commands.

I Implementation overview

\TeX is designed to process a single stream of text, which may include footnotes, tables, and so on. It just keeps converting its input into a stream typeset pages. It was not designed for typesetting two texts in parallel, where it has to alternate from one to the other. Further, \TeX essentially processes its input one paragraph at a time — it is very difficult to get at the ‘internals’ of a paragraph such as the individual lines in case you want to number them or put some mark at the start or end of the lines.

`reledmac` solves the problem of line numbering by putting the paragraph in typeset form into a box, and then extracting the lines one by one from the box for \TeX to put them onto the page with the appropriate page breaks. Most of the `reledmac` code is concerned with handling this box and its contents.

`reledpar`’s solution to the problem of parallel texts is to put the two texts into separate boxes, and then appropriately extract the pairs of lines from the boxes. This involves duplicating much of the original box code for an extra right text box. The other, smaller, part of the code is concerned with coordinating the line extractions from the boxes.

II Preliminaries

II.1 Package’s meta-data

Announce the name and version of the package, which is targeted for \LaTeXe . The package also requires the `reledmac` package, however we do not load it automatically, because we prefer users to know it.

```

1 %<*code>
2 \NeedsTeXFormat{LaTeX2e}
3 \ProvidesPackage{reledpar}[2016/03/23 v2.8.0 reledmac extension for
parallel texts]%
4 %
5 %

```

II.2 Package’s requirement

Few commands use `\xspace` command.

```

6 \RequirePackage{xspace}%
7 %

```

II.3 Package’s options

We use `xkeyval` in order to manage options with arguments.

```

8 \RequirePackage{xkeyval}%
9 %

```

II.4 Package's options

II.4.1 Synchronization's options

\@par@this@sync@option The \par@sync@option stores the options of synchronization. It use to ensure these options do not change between two run.

```
10 \def\@par@this@sync@option{}%
11 %
```

With the option ‘shiftedpstarts’ a long pstart on the left side (or on the right side) does not make a blank on the corresponding pstart, but the blank is put on the bottom of the page. Consequently, the pstarts on the parallel pages are shifted, but the shift stops at every end of pages.

```
\ifshiftedpstarts12 \newif\ifshiftedpstarts
13 \DeclareOptionX{shiftedpstarts}{%
14   \shiftedpstartstrue%
15   \apptocmd{\@par@this@sync@option}{shifted}{}{}%
16 }%
17 %
```

With the option ‘advancedshiftedpstarts’ a long pstart on the left side (or on the right side) does not make a blank on the corresponding pstart, but the blank is put on the bottom of the page. Consequently, the pstarts on the parallel pages are shifted, but the shift stops at every end of pages. Differing to shiftedpstarts, the pstart shift are not counted to determine when cutting the page. That could help to avoid page with blank lines at the bottom.

```
\ifshiftedpstarts18 \newif\ifadvancedshiftedpstarts
19 \DeclareOptionX{advancedshiftedpstarts}{%
20   \advancedshiftedpstartstrue%
21   \shiftedpstartstrue%
22   \apptocmd{\@par@this@sync@option}{advancedshifted}{}{}%
23 }%
24 %
```

With the option nomaxlines, reledpar allows facing pages to have not the same number of lines.

```
\ifnomaxlines25 \newif\ifnomaxlines%
26 \DeclareOptionX{nomaxlines}{%
27   \nomaxlinestrue%
28   \apptocmd{\@par@this@sync@option}{nomax}{}{}%
29 }%
30 %
```

With the option nosyncpstarts, reledpar only alternate between left and right side, and does not try to obtain the same number of line in corresponding page.

```

\ifnosyncpstarts31 \newif\ifnosyncpstarts%
32 \DeclareOptionX{nosyncpstarts}{%
33   \shiftedpstartstrue%
34   \nomaxlinestrue%
35   \nosyncpstartstrue%
36   \apptocmd{\@par@this@sync@option}{nosync}{}{%
37 }%
38 %

```

II.4.2 Other options

The `parledgroup` can be called either on `reledmac` or `reledpar`.

```

39 \DeclareOptionX{parledgroup}{\parledgrouptrue}
40 %

```

`\ifwidthliketwocolumns` The `widthliketwocolumns` and `continuousnumberingwithcolumns` options can be called either on `reledmac` or `reledpar`.

```

41 \DeclareOptionX{widthliketwocolumns}{\widthliketwocolumnstrue}%
42 \DeclareOptionX{continuousnumberingwithcolumns}{\continuousnumberingwithcolumnstrue}%
43 %

```

`\ifsameparallelpagenumber` Options related to page numbering

```

\ifprevpgnotnumbered
44 \newif\ifprevpgnotnumbered
45 \newif\ifprevpgnotnumbered
46 \DeclareOptionX{sameparallelpagenumber}{\sameparallelpagenumbertrue}
47 \DeclareOptionX{prevpgnotnumbered}{\prevpgnotnumberedtrue}
48 %

```

`\prevpgstyle` We store on `\prevpgstyle` the argument of the option `prevpgstyle`.

```

49 \DeclareOptionX{prevpgstyle}{\gdef\prevpgstyle{\#1}}%
50 %

```

```

51 \ProcessOptionsX%
52 %

```

II.5 Determining side and category of parallel processing

As noted above, much of the code is a duplication of the original `reledmac` code to handle the extra box(es) for the right hand side text, and sometimes for the left hand side as well. In order to distinguish we use ‘R’ or ‘L’ in the names of macros for the right and left code. The specifics of ‘L’ and ‘R’ are normally hidden from the user by letting the `Leftside` and `Rightside` environments set things up appropriately.

```
\ifl@dpairing \ifl@dpairing is set TRUE if we are processing parallel texts and \ifl@dpaging is
\ifl@dpaging also set TRUE if we are doing parallel pages. \ifledRcol is set TRUE if we are doing
\ifledRcol the right hand text. They are defined in reledmac.
```

II.6 Text's width

```
\Lcolwidth The widths of the left and right parallel columns (or pages).
\Rcolwidth
53 \newdimen\Lcolwidth
54   \Lcolwidth=0.45\textwidth
55 \newdimen\Rcolwidth
56   \Rcolwidth=0.45\textwidth
57 %
```

II.7 Messages

All the error and warning messages are collected here as macros.

```
\reledpar@error58 \newcommand{\reledpar@error}[2]{\PackageError{reledpar}{#1}{#2}}
59 %
```

```
\reledpar@warning60 \newcommand{\reledpar@warning}[1]{\PackageWarning{reledpar}{#1}}%
61 %
```

```
\led@err@TooManyPstarts62 \newcommand*{\led@err@TooManyPstarts}{%
63   \reledpar@error{Too many \string\pstart\space without printing.
64     Some text will be lost}{\@ehc}}
65 %
```

```
\d@err@BadLeftRightPstarts66 \newcommand*{\d@err@BadLeftRightPstarts}[2]{%
67   \reledpar@error{The numbers of left (#1) and right (#2)
68     \string\pstart s do not match}{\@ehc}}
69 %
```

```
\led@err@LeftOnRightPage70 \providebool{syntax@}
\led@err@RightOnLeftPage71 \newcommand*{\led@err@LeftOnRightPage}{%
72   \notbool{syntax@}%
73   {\reledpar@error{The left page has ended on a right page}{\@ehc}}%
74   {}%
75 }
76 \newcommand*{\led@err@RightOnLeftPage}{%
77   \notbool{syntax@}%
78   {\reledpar@error{The right page has ended on a left page}{\@ehc}}%
79   {}%
80 }
81 %
```

```

\led@err@Leftside@PreviousNotPrinted82 \newcommand{\led@err@Leftside@PreviousNotPrinted}{%
\led@err@Rightside@PreviousNotPrinted83   \reledpar@error{You call a new Leftside environment while the previous
                                                one has not been typeset by \string\Pages\space or \string\Columns{\@ehc}}
84   \newcommand{\led@err@Rightside@PreviousNotPrinted}{%
85     \reledpar@error{You call a new Rightside environment while the previous
                                                one has not been typeset by \string\Pages\space or \string\Columns{\@ehc}}
86   %
}

\led@err@Pages@InsideEnv87 \newcommand{\led@err@Pages@InsideEnv}{%
\led@err@Columns@InsideEnv88   \reledpar@error{\string\Pages\space must be called *outside* of the `%
                                                pages` environment{\@ehc}}
89   \newcommand{\led@err@Columns@InsideEnv}{%
90     \reledpar@error{\string\Columns\space must be called *outside* of the `%
                                                pairs` environment{\@ehc}}
91   %

\led@err@Pages@WithoutEnv92 \newcommand{\led@err@Pages@WithoutEnv}{%
\led@err@Columns@WithoutEnv93   \reledpar@error{\string\Pages\space called without previous `pages`%
                                                environment{\@ehc}}
94   \newcommand{\led@err@Columns@WithoutEnv}{%
95     \reledpar@error{\string\Columns\space called without previous `pairs`%
                                                environment{\@ehc}}
96   %

\led@error@fail@patch@thepage97 \newcommand{\led@error@fail@patch@thepage}{%
98   \reledpar@error{Fail to patch \string@\thepage\space command.}{\@ehc}%
99 }%
100 %

\led@error@fail@patch@pagenumbering101 \newcommand{\led@error@fail@patch@pagenumbering}{%
102   \reledpar@error{Fail to patch \string\pagenumbering\space command.}{\@ehc}%
103 }%
104 %

\led@error@fail@patch@memnum105 \newcommand{\led@error@fail@patch@memnum}{%
106   \reledpar@error{Fail to patch \string@\memnum\space command.}{\@ehc}%
107 }%
108 %

\led@error@fail@patch@outputpage109 \newcommand{\led@error@fail@patch@outputpage}{%
110   \reledpar@error{Fail to patch \string@\outputpage\space command.}{\@ehc}%
111 }%
112 %

```

```

led@warn@ChangeSyncOption13 \newcommand*{\led@warn@ChangeSyncOption}[1]{%
  ^{14}  \reledpar@warning{You have changed synchronization's options since last
    run. We have not read line-list file #1. Please run LaTeX again.}%
  ^{15}  }%
  ^{16} %

```

```

warn@setting@in@rightside17 \newcommand{\led@warn@setting@in@rightside}[1]{%
  ^{18}  \reledpar@warning{You use #1 inside rightside environment. \MessageBreak%
    Such behavior is deprecated. \MessageBreak%
    Use instead #1R or #1* in your preamble.}%
  ^{19}  }%
  ^{20} %

```

III Sectioning commands

`\section@numR` This is the right side equivalent of `\section@num`.

Each section will read and write an associated ‘line-list file’, containing information used to do the numbering. Normally the file will be called `<jobname>.nn`, where nn is the section number. However, for right side texts the file is called `<jobname>.nnR`. The `\extensionchars` applies to the right side files just as it does to the normal files.

```

^{123} \newcount\section@numR
^{124}   \section@numR=\z@
^{125} %

```

`\ifpst@rtdL` `\ifpst@rtdL` is set FALSE at the start of left side numbering, and similarly for `\ifpst@rtdR` `\ifpst@rtdR`. `\ifpst@rtdL` is defined in `reledmac`.

```

^{126} \pst@rtdLfalse
^{127} \newif\ifpst@rtdR
^{128}
^{129} %

```

`\beginnumberingR` This is the right text equivalent of `\beginnumbering`, and begins a section of numbered text.

```

^{130} \newcommand*{\beginnumberingR}{%
  ^{131}   \ifnumberingR
  ^{132}     \led@err@NumberingStarted
  ^{133}     \endnumberingR
  ^{134}   \fi
  ^{135}   \global\l@dnumpstartsR \z@
  ^{136}   \global\pst@rtdRfalse
  ^{137}   \global\numberingRtrue
  ^{138}   \global\advance\section@numR \@ne
  ^{139}   \global\absline@numR \z@

```

```

140 \gdef \normal@page@breakR{}
141 \gdef \l@prev@pbR{}
142 \gdef \l@prev@nopbR{}
143 \global\line@numR \z@
144 \global\@clockR \z@
145 \global\sub@clockR \z@
146 \global\sublines@false
147 \global\let\next@page@numR\relax
148 \global\let\sub@change\relax
149 \set@continuousnumberingforR%
150 \message{Section \the\section@numR R }%
151 \line@list@stuffR{\jobname.\extensionchars\the\section@numR R}%
152 \l@end@stuff
153 \setcounter{pstartR}{1}
154 \begingroup
155 \initnumbering@sectcountR
156 \gdef\eled@sectionsR@@{}%
157 \if@noeled@sec\else%
158   \makeatletter\InputIfFileExists{\jobname.eledsec\the\section@numR R
159   }{}{}\makeatother%
160   \immediate\openout\eled@sectioningR@out=\jobname.eledsec\the\
161   section@numR R\relax%
162 \fi%
163 }
164 %

```

\endnumbering This is the left text version of the regular `\endnumbering` and must follow the last text for a left text numbered section. It sets `\ifpst@rtedL` to FALSE. It is fully defined in `reledmac`.

\endnumberingR This is the right text equivalent of `\endnumbering` and must follow the last text for a right text numbered section.

```

163 \def\endnumberingR{%
164   \ifnumberingR
165     \global\numberingRfalse
166     \normal@pars
167     \ifnum\l@dnumpstartsR=0%
168       \led@err@NumberingWithoutPstart%
169     \fi%
170     \ifl@dpairing
171       \global\pst@rtedRfalse
172     \else
173       \ifx\insertlines@listR\empty\else
174         \global\noteschanged@true
175       \fi
176       \ifx\line@listR\empty\else
177         \global\noteschanged@true
178       \fi
179     \fi

```

```

180     \ifnoteschanged@%
181         \led@mess@NotesChanged
182     \fi
183 \else
184     \led@err@NumberingNotStarted
185 \fi
186 \endgroup
187 \if@noeled@sec\else%
188     \immediate\closeout\eled@sectioningR@out%
189 \fi%
190 }
191 %
192 %

```

\initnumbering@sectcountR We do not want the right side section commands to be numbered after the left side ones,
 \save@section@number instead we want them numbered after which is typeset before the pages or columns
 \set@sectcountR environments. we switch the L^AT_EX counter in \numberingR.

```

193 \newcounter{chapterR}
194 \newcounter{sectionR}
195 \newcounter{subsectionR}
196 \newcounter{subsubsectionR}
197
198 \newcount\old@chapter%
199 \newcount\old@section%
200 \newcount\old@subsection%
201 \newcount\old@subsubsection%
202 \newcommand{\save@section@number}{%
203     \ifdefined\c@chapter%
204         \global\old@chapter\value{chapter}%
205     \fi%
206     \global\old@section\value{section}%
207     \global\old@subsection\value{subsection}%
208     \global\old@subsubsection\value{subsubsection}%
209 }%
210 \newcommand{\initnumbering@sectcountR}{%
211     \ifdefined\c@chapter%
212         \setcounter{chapterR}{\old@chapter}%
213     \fi%
214     \setcounter{sectionR}{\old@section}%
215     \setcounter{subsectionR}{\old@subsection}%
216     \setcounter{subsubsectionR}{\old@subsubsection}%
217     \set@sectcountR%
218 }
219 \newcommand{\set@sectcountR}{%
220     \let\c@chapter\c@chapterR%
221     \let\c@section\c@sectionR%
222     \let\c@subsection\c@subsectionR%
223     \let\c@subsubsection\c@subsubsectionR%
224 }%

```

225 %

\pausenumberingR These are the right text equivalents of \pausenumbering and \resumenumbering.
\resumenumberingR
226 \newcommand*{\pausenumberingR}{%
227 \endnumberingR\global\numberingRtrue}
228 \newcommand*{\resumenumberingR}{%
229 \ifnumberingR
230 \global\pst@rte@true
231 \global\advance\section@numR \cne
232 \led@mess@SectionContinued{\the\section@numR R}%
233 \line@list@stuffR{\jobname.\extensionchars\the\section@numR R}%
234 \l@dend@stuff
235 \begingroup%
236 \initnumbering@sectcountR%
237 \set@continuousnumberingforR%
238 \else
239 \led@err@numberingShouldHaveStarted
240 \endnumberingR
241 \beginnumberingR
242 \fi}
243 %

\memorydumpL \memorydump is a shorthand for \pausenumbering\resumenumbering. This will clear
\memorydumpR the memorised stuff for the previous chunks while keeping the numbering going.

245 \newcommand*{\memorydumpL}{%
246 \endnumbering
247 \numberingtrue
248 \global\pst@rte@true
249 \global\advance\section@num \cne
250 \led@mess@SectionContinued{\the\section@num}%
251 \line@list@stuff{\jobname.\extensionchars\the\section@num}%
252 \l@dend@stuff}
253
254 \newcommand*{\memorydumpR}{%
255 \endnumberingR
256 \numberingRtrue
257 \global\pst@rte@true
258 \global\advance\section@numR \cne
259 \led@mess@SectionContinued{\the\section@numR R}%
260 \line@list@stuffR{\jobname.\extensionchars\the\section@numR R}%
261 \l@dend@stuff}
262 %

IV Line counting

IV.1 Setting lineation reset

Sometimes you want line numbers that start at 1 at the top of each page; sometimes you want line numbers that start at 1 at each `\pstart`; other times you want line numbers that start at 1 at the start of each section and increase regardless of page breaks. `reledpar` lets you choose different schemes for the left and right texts.

`\lineationR` `\lineationR{<word>}` is the macro used to select the lineation system for right texts. Its argument is a string: either `page`, `pstart` or `section`.

```

264 \newcommand*{\lineationR}[1]{%
265   \ifnumbering
266     \led@err@LineationInNumbered
267   \else
268     \def\@tempa{\#1}\def\@tempb{page}%
269     \ifx\@tempa\@tempb
270       \global\bypage@Rtrue
271       \global\bypstart@Rfalse
272       \unless\ifnocritical@%
273         \Xpstart[] [false]%
274       \fi%
275     \else
276       \def\@tempb{pstart}%
277       \ifx\@tempa\@tempb
278         \global\bypage@Rfalse
279         \global\bypstart@Rtrue
280         \unless\ifnocritical@%
281           \Xpstart%
282         \fi%
283       \else
284         \def\@tempb{section}%
285         \ifx\@tempa\@tempb
286           \global\bypage@Rfalse%
287           \global\bypstart@Rfalse%
288           \unless\ifnocritical@%
289             \Xpstart[] [false]%
290           \fi%
291         \else
292           \led@warn@BadLineation
293         \fi%
294       \fi
295     \fi
296   \fi}%
297 %

```

`t@continuousnumberingforR` `\set@continuousnumberingforR` set the right line numbers at a `\beginnumberingR` or a `\resumenumberingR` in order to have continuous numbering with single column text.

```

298 \newcommand{\set@continuousnumberingforR}{%
299   \ifcontinuousnumberingwithcolumns%
300     \ifnum\line@numR<\line@num%
301       \expandafter\setlinenum\expandafter{\the\line@num}%
302     \fi%
303     \ifnum\last@page@num>\last@page@numR%
304       \global\last@page@numR=\last@page@num%
305     \fi%
306   \fi%
307 }
308 %

```

\lineation* \lineation* change the lineation system for both sides.

```

309 \WithSuffix\newcommand\lineation*[1]{%
310   \lineation{#1}%
311   \lineationR{#1}%
312 }%
313 %

```

IV.2 Setting line number margin

\linenummargin \line@marginR You call \linenummargin{<word>} to specify which margin you want your right text's line numbers in; it takes one argument, a string. You can put the line numbers in the same margin on every page using left or right; or you can use inner or outer to get them in the inner or outer margins. You can change this within a numbered section, but the change may not take effect just when you would like; if it is done between paragraphs nothing surprising should happen.

For right texts the selection is recorded in the count \line@marginR, otherwise in the count \line@margin: 0 for left, 1 for right, 2 for outer, and 3 for inner.

It is defined only once time, in `reledmac`.

```

314 \newcount\line@marginR
315 %

```

By default put right text numbers at the right.

```

316 \line@marginR=\@ne
317 %
318 %

```

\linenummarginR \linenummarginR applies directly for right side, while \linenummargin* applies for \linenummargin* both side.

```

319 \newcommand{\linenummarginR}[1]{%
320   \l@dge@margin{#1}%
321   \ifnum\@l@dtmpcntb>\m@ne%
322     \global\line@marginR=\@l@dtmpcntb%
323   \fi%
324 }

```

```

325 \WithSuffix\newcommand\linenummargin*[1]{%
326   \l@dgepline@margin{#1}%
327   \ifnum\@l@dtmpcntb>\m@ne%
328     \global\line@marginR=\@l@dtmpcntb%
329     \global\line@margin=\@l@dtmpcntb%
330   \fi%
331 }
332 %

```

IV.3 Setting lineation start and step

`\c@firstlinenumR` The following counters tell `reledmac` which right text lines should be printed with line numbers. `firstlinenumR` is the number of the first line in each section that gets a number; `linenumincrementR` is the difference between successive numbered lines. The initial values of these counters produce labels on lines 5, 10, 15, etc. `linenumincrementR` must be at least 1.

```

333 \newcounter{firstlinenumR}
334   \setcounter{firstlinenumR}{5}
335 \newcounter{linenumincrementR}
336   \setcounter{linenumincrementR}{5}
337 %

```

`\c@firstsublinenumR` The following parameters are just like `firstlinenumR` and `linenumincrementR`, but for sub-line numbers. `sublinenumincrementR` must be at least 1.

```

338 \newcounter{firstsublinenumR}
339   \setcounter{firstsublinenumR}{5}
340 \newcounter{sublinenumincrementR}
341   \setcounter{sublinenumincrementR}{5}
342 %
343 %

```

`\firstlinenum` These are the user's macros for changing (sub) line numbers. They are defined in `reledmac`. The starred versions are specific to `eledpar`.

`\linenumincrement`

`\firstsublinenum`

`\sublinenumincrement`

`\firstlinenum*`

`\linenumincrement*`

`\firstsublinenum*`

`\sublinenumincrement*`

```

344 \WithSuffix\newcommand\firstlinenum*[1]{%
345   \setcounter{firstlinenumR}{#1}%
346   \setcounter{firstlinenum}{#1}%
347 }
348 \WithSuffix\newcommand\linenumincrement*[1]{%
349   \setcounter{linenumincrementR}{#1}%
350   \setcounter{linenumincrement}{#1}%
351 }
352 \WithSuffix\newcommand\firstsublinenum*[1]{%
353   \setcounter{subfirstlinenumR}{#1}%
354   \setcounter{subfirstlinenum}{#1}%
355 }
356 \WithSuffix\newcommand\sublinenumincrement*[1]{%

```

```

357   \setcounter{sublinenumincrementR}{#1}%
358   \setcounter{sublinenumincrement}{#1}%
359 }
360 %

```

`\firstlinenumR` And the ‘R’ suffixed version.

```

\linenumincrementR[1]{%
  \newcommand{\firstlinenumR}[1]{%
    \setcounter{firstlinenumR}{#1}%
  }
  \newcommand{\linenumincrementR}[1]{%
    \setcounter{linenumincrementR}{#1}%
  }
  \newcommand{\firstsublinenumR}[1]{%
    \setcounter{subfirstlinenumR}{#1}%
  }
  \newcommand{\sublinenumincrementR}[1]{%
    \setcounter{sublinenumincrementR}{#1}%
  }
}

```

IV.4 Setting line flag

`\Rlineflag` This is appended to the line numbers of right text.

```

374 \newcommand{\setRlineflag}[1]{%
375   \gdef\@Rlineflag{#1}%
376 }
377 \setRlineflag{R}
378 %

```

IV.5 Setting line number style

`\linenumrepR` `\linenumrepR{ctr}` typesets the right line number $\langle ctr \rangle$, and similarly `\sublinenumrepR` for subline numbers.

```

379 \newcommand*{\linenumrepR}[1]{\@arabic{#1}}
380 \newcommand*{\sublinenumrepR}[1]{\@arabic{#1}}
381 %
382 %

```

`\linenumberstyleR` The style can be changed by some user level command

```

\sublinenumberstyleR
383 \newcommand*{\linenumberstyleR}[1]{%
384   \def\linenumrepR##1{\@nameuse{@#1}{##1}}%
385 \newcommand*{\sublinenumberstyleR}[1]{%
386   \def\sublinenumrepR##1{\@nameuse{@#1}{##1}}%
387 %

```

\linenumberstyle* And for both side.

```

\sublinenumberstyle*
388  \WithSuffix\newcommand\linenumberstyle*[1]{%
389    \linenumberstyle{#1}%
390    \linenumberstyleR{#1}%
391  }%
392
393 \WithSuffix\newcommand\sublinenumberstyle*[1]{%
394   \sublinenumberstyle{#1}%
395   \sublinenumberstyleR{#1}%
396 }%
397 %
398 %

```

IV.6 Print marginal line number

\iflinenumberLevenifblank \iflinenumberLevenifblank and \iflinenumberRevenifblank can be switched
 \iflinenumberRevenifblank to TRUE if we want to print the line number, even if the line is blank.

```

399 \newif\iflinenumberLevenifblank
400 \newif\iflinenumberRevenifblank
401 %

```

\leftlinenumR \leftlinenumR and \rightlinenumR are the macros that are called to print the right
 \rightlinenumR text's marginal line numbers. Much of the code for these is common and is maintained
 \l@dlinenumR in \l@dlinenumR.

```

402 \newcommand*\{\leftlinenumR}{%
403   \l@dlinenumR
404   \kern\linenumsep}
405 \newcommand*\{\rightlinenumR}{%
406   \kern\linenumsep
407   \l@dlinenumR}
408 \newcommand*\{\l@dlinenumR}{%
409   \numlabfont\linenumrepR{\line@numR}\@Rlineflag%
410   \ifsblines@
411     \ifnum\spline@num>\z@
412       \unskip\fullstop\sublinenumrepR{\spline@numR}%
413     \fi
414   \fi}
415 %
416 %

```

IV.7 Line-number counters and lists

IV.7.1 Correspond to those in reledmac for regular or left text

We need another set of counters and lists for the right text, corresponding to those in
 reledpar for regular or left text.

\line@numR The count \line@numR stores the line number that is used in the right text's marginal line numbering and in notes. The count \subline@numR stores a sub-line number that qualifies \line@numR. The count \absline@numR stores the absolute number of lines since the start of the right text section: that is, the number we have actually printed, no matter what numbers we attached to them.

```
417 \newcount\line@numR
418 \newcount\subline@numR
419 \newcount\absline@numR
420
421 %
```

\line@listR Now we can define the list macros that will be created from the line-list file. They are directly analogous to the left text ones. The full list of action codes and their meanings is given in the reledmac manual.

\actions@listR Here are the commands to create these lists:

```
422 \list@create{\line@listR}
423 \list@create{\insertlines@listR}
424 \list@create{\actionlines@listR}
425 \list@create{\actions@listR}
426
427 %
```

\page@numR The right text page number.

```
428 \newcount\page@numR
429
430 %
```

IV.7.2 Specific to reledpar

\linesinpar@listL In order to synchronise left and right chunks in parallel processing we need to know how many lines are in each left and right text chunk, and the maximum of these for each pair of chunks.

```
431 \list@create{\linesinpar@listL}
432 \list@create{\linesinpar@listR}
433 \list@create{\maxlinesinpar@list}
434
435 %
```

IV.8 Reading the line-list file

\list@clearing@regR \Clear the right lines for \read@linelist

```
436 \newcommand{\list@clearing@regR}{%
437   \list@clear{\line@listR}%
438   \list@clear{\insertlines@listR}%
}
```

```

439      \list@clear{\actionlines@listR}%
440      \list@clear{\actions@listR}%
441      \list@clear{\linesinpar@listR}%
442      \list@clear{\linesonpage@listR}%
443  }
444 %

```

\@par@sync@option When typesetting parallel pages, \@par@sync@option check if we have changed the synchronization's option since the last run. If true, we just not read the numbered file.

```

445 \newcommand{\@par@sync@option}[1]{%
446   \IfStrEq{#1}{\@par@this@sync@option}{%
447     {}%
448     {\ifledRcol{%
449       \led@warn@ChangeSyncOption{\jobname.\extensionchars\the\section@num}%
450     }%
451     \else{%
452       \led@warn@ChangeSyncOption{\jobname.\extensionchars\the\section@num}%
453     }%
454     \fi%
455     \endinput%
456   }%
457   {}%
458 }

```

\read@linelist \read@linelist{<file>} is the control sequence that is called by \beginnumbering (via \line@list@stuff) to open and process a line-list file; its argument is the name of the file. It is defined only once time in reledmac.

IV.9 Commands within the line-list file

This section defines the commands that can appear within a line-list file, except for \@lab which is in a later section among the cross-referencing commands it is associated with.

The macros with **action** in their names contain all the code that modifies the action-code list.

\@nl@regR \@nl@regR is called by \@nl if we are on a right side. It does everything related to the \@nl start of a new line of numbered text on a right side.

```

457 \newcommand{\@nl@regR}{%
458   \ifx\l@dchset@num\relax \else
459     \advance\absline@numR \@ne
460     \set@line@action
461     \let\l@dchset@num\relax
462     \advance\absline@numR \m@ne
463     \advance\line@numR \m@ne% % do we need this?
464   \fi
465   \advance\absline@numR \@ne

```

```

466 \ifx\next@page@numR\relax \else
467   \page@action
468   \let\next@page@numR\relax
469 \fi
470 \ifx\sub@change\relax \else
471   \ifnum\sub@change>\z@
472     \sublines@true
473   \else
474     \sublines@false
475   \fi
476   \sub@action
477   \let\sub@change\relax
478 \fi
479 \ifcase\@clockR
480 \or
481   \@clockR \tw@
482 \or\or
483   \@clockR \z@
484 \fi
485 \ifcase\sub@clockR
486 \or
487   \sub@clockR \tw@
488 \or\or
489   \sub@clockR \z@
490 \fi
491 \ifsublines@
492   \ifnum\sub@clockR<\tw@
493     \advance\subline@numR \@ne
494   \fi
495 \else
496   \ifnum\@clockR<\tw@
497     \advance\line@numR \@ne \subline@numR \z@
498   \fi
499 \fi}
500
501
502 %

```

\last@page@numR \last@page@numR store the page number of the last right page. It is modified by
 \fix@page \fix@page, defined by reledmac.

```

503 \newcount\last@page@numR
504 \last@page@numR=-10000
505
506 %

```

\@adv The \@adv{\langle num\rangle} macro advances the current visible line number by the amount specified as its argument. This is used to implement \advanceline. It is defined in reledmac.

- \@set** The `\@set{\(num)}` macro sets the current visible line number to the value specified as its argument. This is used to implement `\setline`. It is defined in `reledmac`.
- \l@d@set** The `\l@d@set{\(num)}` macro sets the line number for the next `\pstart...` to the value specified as its argument. This is used to implement `\setlinenum`. It is defined in `reledmac`.
- \page@action** `\page@action` adds an entry to the action-code list to change the page number. It is defined in `reledmac`.
- \set@line@action** `\set@line@action` adds an entry to the action-code list to change the visible line number. It is defined in `reledmac`.
- \sub@action** `\sub@action` adds an entry to the action-code list to turn sub-lineation on or off, according to the current value of the `\ifsublines@` flag. It is defined in `reledmac`.
- \do@clockon** `\lock@on` adds an entry to the action-code list to turn line number locking on. The current setting of the sub-lineation flag tells us whether this applies to line numbers or sub-line numbers. It is defined in `reledmac`, however the code specific to right side is defined here, in `\do@clockonR`.

```

507 \newcount\@clockR
508 \newcount\sub@clockR
509
510 \newcommand*\do@clockonR{%
511   \xright@appenditem{\the\absline@numR}\to\actionlines@listR
512   \ifsublines@
513     \xright@appenditem{-1005}\to\actions@listR
514     \ifnum\sub@clockR=\z@
515       \sub@clockR \@ne
516     \else
517       \ifnum\sub@clockR=\thr@@
518         \sub@clockR \@ne
519       \fi
520     \fi
521   \else
522     \xright@appenditem{-1003}\to\actions@listR
523     \ifnum\@clockR=\z@
524       \@clockR \@ne
525     \else
526       \ifnum\@clockR=\thr@@
527         \@clockR \@ne
528       \fi
529     \fi
530   \fi}
531 %
532 %

```

- \lock@off** `\lock@off` adds an entry to the action-code list to turn line number locking off. It is defined in `reledmac`, however the code specific to right side is defined here, in `\do@lockoffR`.
- \skip@clockoff**

```

533
534
535 \newcommand{\do@clockoffR}{%
536   \xright@appenditem{\the\absline@numR}\to\actionlines@listR
537   \ifsublines@
538     \xright@appenditem{-1006}\to\actions@listR
539     \ifnum\sub@clockR=\tw@
540       \sub@clockR \thr@@
541     \else
542       \sub@clockR \z@%
543     \fi
544   \else
545     \xright@appenditem{-1004}\to\actions@listR
546     \ifnum\@clockR=\tw@
547       \@clockR \thr@@
548     \else
549       \@clockR \z@%
550     \fi
551   \fi}
552
553 %
554 %

```

\n@num

\@ref \@ref@regR \insert@countR

- #1, the number of entries to add to \insertlines@list for this reference. This value for right text, here and within \edtext, which computes it and writes it to the line-list file, will be stored in the count \insert@countR.

```

555 \newcount\insert@countR
556 %

```

- #2, a sequence of other line-list-file commands, executed to determine the ending line-number. This may also include other \@ref commands, corresponding to uses of \edtext within the first argument of another instance of \edtext.

\@ref itself is defined in *reledmac*. It calls \ref@reg or \ref@regR, depending whether we are in left or right side. Here, we define only \ref@regR, \ref@reg is already defined in *reledmac*.

The first thing \@ref@regR itself does is to add the specified number of items to the \insertlines@listR list.

```

557 \newcommand*{\@ref@regR}[2]{%
558   \global\advance\@edtext@level by 1%
559   \global\insert@countR=#1\relax
560   \loop\ifnum\insert@countR>\z@
561     \xright@appenditem{\the\absline@numR}\to\insertlines@listR

```

```

562     \global\advance\insert@countR \m@ne
563     \repeat
564 %

```

Next, process the second argument to determine the page and line numbers for the end of this lemma. We temporarily equate `\@ref` to a different macro that just executes its argument, so that nested `\@ref` commands are just skipped this time. Some other macros need to be temporarily redefined to suppress their action.

```

565     \begingroup
566         \let\@ref=\dummy@ref
567         \let\@lopR@gobble
568         \let\page@action=\relax
569         \let\sub@action=\relax
570         \let\set@line@action=\relax
571         \let\@lab=\relax
572         \let\@lemma=\relax
573         \let\@sw\@gobblethree%
574         #2
575         \global\endpage@num=\page@numR
576         \global\endline@num=\line@numR
577         \global\endsubline@num=\subline@numR
578     \endgroup
579 %

```

Now store all the information about the location of the lemma's start and end in `\line@list@R`.

```

580     \xright@appenditem%
581     {\the\page@numR|\the\line@numR|%
582      \ifsublines@ \the\subline@numR \else 0\fi|%
583      \the\endpage@num|\the\endline@num|%
584      \ifsublines@ \the\endsubline@num \else 0\fi}\to\line@listR
585 %

```

Create a list which will store all the second argument of each `\@sw` in this lemma, at this level.

```

586     \expandafter\list@create\expandafter{\csname sw@list@edtext@tmp@\the\
587     \edtext@level\endcsname}%
588 %

```

Declare and init boolean for lemma in this level.

```

588     \providebool{lemmacommand@\the\edtext@level}%
589     \boolfalse{lemmacommand@\the\edtext@level}%
590 %

```

Execute the second argument of `\@ref` again, to perform for real all the commands within it.

```

591     #2
592     % Now, we store the list of \protect\cs{@sw} of this current \protect\cs{
593     edtext} as an element of

```

```

593 % the global list of list of \protect\cs{@sw} for a \protect\cs{edtext}
594 % depth.
595 % \begin{macrocode}
596 % \ifnum\@edtext@level>0%
597 %   \def\create@this@edtext@level{\expandafter\list@create\expandafter{\
598 %     \csname sw@list@edtextR@\the\@edtext@level\endcsname}%
599 %   \ifcsundef{sw@list@edtextR@\the\@edtext@level}{\
600 %     \create@this@edtext@level}{}%
601 %     \letcs{\@tmp}{sw@list@edtextR@\the\@edtext@level}%
602 %     \letcs{\@tmp}{sw@list@edtextR@\the\@edtext@level}%
603 %     \xright@appenditem{\expandonce\@tmp}{to\@tmp}%
604 %     \global\cslet{sw@list@edtextR@\the\@edtext@level}{\@tmp}%
605 %   \fi%
606 %

```

Decrease edtext level counter.

```

604   \global\advance\@edtext@level by -1%
605 }
606 %

```

\@pend \@pend{\langle num\rangle} adds its argument to the \linesinpar@listL list, and analogously **\@pendR** for \@pendR. If needed, it resets line number. Both are defined in `reledmac`, but they are empty. They are really defined only in `reledpar`.

```

607 \renewcommand*\@pend}[1]{%
608   \ifbypstart@\global\line@num=0\fi%
609   \xright@appenditem{#1}\to\linesinpar@listL}
610 \renewcommand*\@pendR}[1]{%
611   \ifbypstart@R\global\line@numR=0\fi%
612   \xright@appenditem{#1}\to\linesinpar@listR}
613 %
614 %

```

\@pstart \@pstart and cs@pstartR allows us to know, when using \nomaxlines option in which page we should start a pstart, and also how many empty lines we should let before starting this pstart at the begining of the page

```

615 \newcommand{\@pstart}[3]{%
616   \ifcsdef{minpage@pstart@#1}%
617   {\ifnumgreater{#2}{\csuse{minpage@pstart@#1}}{%
618     {\csnumgdef{minpage@pstart@#1}{#2}}%
619     {}%}
620   }%
621   {\csnumgdef{minpage@pstart@#1}{#2}}
622   \csnumgdef{afterlines@pstart@#1L}{#3}%
623 }%
624 %
625 \newcommand{\@pstartR}[3]{%
626   \numdef{\@tmp}{#2-1}%Because we have not to know in which page the pstart
   starts, but in which pair of facing page

```

```

627 \ifcsdef{minpage@pstart@#1}%
628   {\ifnumgreater{\@tmp}{\csuse{minpage@pstart@#1}}{%
629     {\csnumgdef{minpage@pstart@#1}{\@tmp}}%
630     {}%}
631   }%
632   {\csnumgdef{minpage@pstart@#1}{\@tmp}}
633   \csnumgdef{afterlines@pstart@#1R}{#3}%
634 }%
635 %

```

`\@lopL` `\@lopL{<num>}` adds its argument to the `\linesonpage@listL` list, and analogously `\@lopR` for `\@lopR`. Both are defined in `reledmac`, but they are empty. They are really defined only in `reledpar`.

```

636 \renewcommand*{\@lopL}[1]{%
637   \xright@appenditem{#1}\to\linesonpage@listL}
638 \renewcommand*{\@lopR}[1]{%
639   \xright@appenditem{#1}\to\linesonpage@listR}
640 %
641 %

```

IV.10 Writing to the line-list file

We have now defined all the counters, lists, and commands involved in reading the line-list file at the start of a section. Now we will cover the commands that `reledmac` uses within the text of a section to write commands out to the line-list.

`\linenum@outR` The file for right texts will be opened on output stream `\linenum@outR`.

```

642 \newwrite\linenum@outR
643 %

```

`\iffirst@linenum@out@R` Once any file is opened on this stream, we keep it open forever, or else switch to another file that we keep open.

```

\first@linenum@out@Rtrue
644 \newif\iffirst@linenum@out@R
645   \first@linenum@out@Rtrue
646 %

```

`\line@list@stuffR` This is the right text version of the `\line@list@stuff{<file>}` macro. It is called by `\beginnumberingR` and performs all the line-list operations needed at the start of a section. Its argument is the name of the line-list file.

```

647 \newcommand*{\line@list@stuffR}[1]{%
648   \read@linelist{#1}%
649   \iffirst@linenum@out@R
650     \immediate\closeout\linenum@outR
651   \global\first@linenum@out@Rfalse
652   \immediate\openout\linenum@outR=#1

```

```

653   \immediate\write\linenum@outR{\string\line@list@version{\
654     this@line@list@version}}%
655     \ifl@dpaging%
656       \immediate\write\linenum@outR{\string\@par@sync@option{\
657         @par@this@sync@option}}%
658       \fi%
659     \else%
660       \if@minipage%
661         \leavevmode%
662       \fi%
663       \closeout\linenum@outR%
664       \openout\linenum@outR=#1%
665     \fi}
666 %

```

- \new@lineL** The `\new@lineL` macro sends the `\@nl` command to the left text line-list file, to mark the start of a new text line.

```

666 \newcommand*{\new@lineL}{%
667   \write\linenum@out{\string\@nl[\the\c@page] [\thepage]}}
668 %

```

- \new@lineR** The `\new@lineR` macro sends the `\@nl` command to the right text line-list file, to mark the start of a new text line.

```

669 \newcommand*{\new@lineR}{%
670   \write\linenum@outR{\string\@nl[\the\c@page] [\thepage]}}
671 %

```

- \flag@start** We enclose a lemma marked by `\edtext` in `\flag@start` and `\flag@end`: these send the `\@ref` command to the line-list file. They are both defined in `reledmac`.

- \startsub** `\startsub` and `\endsub` turn sub-lineation on and off, by writing appropriate instructions to the line-list file. There are both defined in `reledmac`.

- \advanceline** You can use `\advanceline{<num>}` in running text to advance the current visible line-number by a specified value, positive or negative. It is defined in `reledmac`.

- \setline** You can use `\setline{<num>}` in running text (i.e., within `\pstart ... \pend`) to set the current visible line-number to a specified positive value. It is defined in `reledmac`.

- \setlinenum** You can use `\setlinenum{<num>}` before a `\pstart` to set the visible line-number to a specified positive value. It writes a `\l@d@set` command to the line-list file. It is defined in `reledmac`.

- \startlock** `\startlock` or `\endlock` in running text to start or end line number locking at the current line. They decide whether line numbers or sub-line numbers are affected, depending on the current state of the sub-lineation flags. They are defined in `reledmac`.

```
\skipnumbering
```

V Marking text for notes

The `\edtext` macro is used to create all footnotes and endnotes, as well as to print the portion of the main text to which a given note or notes is keyed. The idea is to have that lemma appear only once in the .tex file: all instances of it in the main text and in the notes are copied from that one appearance.

```
\critext
\edtext
\set@line The \set@line macro is called by \edtext to put the line-reference field and font specifier for the current block of text into \l@d@nums. It is defined in reledmac.
```

V.1 Specific hooks and commands for notes

The `reledmac` `\newseries@` initializes commands which are linked to notes series. However, to keep `reledmac` as light as possible, it does not define commands which are specific to `reledpar`. This is what does `\newseries@par`. The specific hooks are also defined here.

```
\newseries@par72 \newcommand{\newseries@par}[1]{%
673 %
```

V.1.1 Notes to be printed on one side only

`reledpar` allows notes to be printed on one side only. We need to declare these options. We also need boolean flags, and to set them to true when a note series is not printed on one side. We check the `nofamiliar` and `nocritical` Eledmac options.

```
674     \unless\ifnofamiliar@%
675         \csgdef{onlysideX@#1}{}%
676         \global\newbool{keepforsideX@#1}%
677     \fi%
678     \unless\ifnocritical@%
679         \global\newbool{keepforXside@#1}%
680         \csgdef{Xonlyside@#1}{}%
681     \fi%
682 %
```

V.2 Tools specific to familiar footnotes

```
683     \unless\ifnofamiliar@%
684     %
```

V.2.1 Managing correct number

One problem with using familiar footnotes in parallel typesetting is the fact that the order of reading notes is not the same as the order they are typeset, because L^AT_EX reads first all the notes on one side, then all the notes on the other side. Then, however, L^AT_EX alternates between typesetting left-side note and right-side notes. Consequently, if we do nothing special, the note numbers are sorted in the reading order, not in the typesetting order. So we could obtain something like 1,3,2,5,4.

To prevent this problem, we use two new counters by series. Every note, in parallel typesetting, has three associated counters.

1. A L^AT_EX counter `footnoteX`. This is the only one manipulated by user, and the only one finally printed.
2. A T_EX counter `footnoteX@reading`. Its value is incremented when reading the `\footnoteX` command in left or right side environments. It is used to get the correct footnote number from the `.aux` file to be typeset in the main text. This counter is already defined in `reledmac`, as it is also used for hyperlink.
3. A L^AT_EX counter `footnoteX@typeset`. Its value is increased when inserting footnotes. files to be used on the next run for the main text.

So here, we only defined the new counter.

```
685 \newcounter{footnote#1@typeset}%
686 %
```

V.2.2 Familiar footnotes without marks

The `\footnoteXnomk` commands are for notes which are printed on the left side, while they are called in the right side. Basically, they set first toggle `\nomark@` to true, then call the `\footnoteX`, and finally add the footnote counter in the footnote counter list.

First, check the `nofamiliar` option of `reledmac`.

So declare the list.

```
687 \expandafter\list@create\csname footnote#1@mk\endcsname%
688 %
```

Then, declare the `\footnoteXnomk` command.

```
689 \expandafter\newcommand\csname footnote#1nomk\endcsname[1]{%
690 %
```

First step: just call the normal `\footnoteX`, saying that we do not want to print the mark.

```
691 \togglettrue{\nomk@}%
692 \csuse{footnote#1}{##1}%
693 \togglefalse{\nomk@}%
694 %
```

Second, and last, step: store the footnote counter in the footnote counters list. We use some `\let`, because `\xright@appenditem` is difficult to use with `\expandafter`.

```

695     \letcs{\@tmp}{footnote#1@mk}%
696     \numdef{\@tmpa}{\csuse{c@footnote#1}}%
697     \global\xright@appenditem{\@tmpa}\to{\@tmp}%
698     \global\cslet{footnote#1@mk}{\@tmp}%
699   }%
700 %

```

Then, declare the command which inserts the footnotemark in the right side.

```

701     \expandafter\newcommand\csname footnote#1mk\endcsname{%
702   %

```

Get the first element of the footnote mark list. As `\gl@p` is difficult to use with dynamic name macro, we use `\let` commands.

```

703     \letcs{\@tmp}{footnote#1@mk}%
704     \gl@p{\@tmp}\to{\@tmpa}%
705     \global\cslet{footnote#1@mk}{\@tmp}%
706 %

```

Set the footnotecounter with it. For the sake of security, we make a backup of the previous value.

```

707     \letcs{\old@footnote}{\csuse{thefnmark#1}}%
708     \setcounter{footnote#1}{\old@footnote}%
709 %

```

Define the footnote mark and print it

```

710     \protected@csxdef{@thefnmark#1}{\csuse{thefootnote#1}}%
711     \csuse{@footnotemark#1}%
712 %

```

Restore previous footnote counter and finally add space.

```

713     \setcounter{footnote#1}{\old@footnote}%
714     \xspace%
715   }%
716 %

```

End of tools specific to familiar notes.

```

717   \fi
718 %

```

End of `\newseries@par`.

```

719 }%
720 %

```

V.2.3 Get correct footnote number

\get@familiarfootnote@number
\save@familiarfootnote@number

As users can insert footnotes between two \Pairs or \Pages commands, we have to set the \+footnoteX@typeset+ counter to the last value of the footnoteX counter at the beginning of these two commands.

```

721 \newcommand{\save@familiarfootnote@number}{%
722   \unless\ifnofamiliar@%
723     \def\do##1{\csxdef{saved@footnote##1}{\the\csname c@footnote##1\endcsname}}%
724     \dolistloop{@series}%
725   \fi%
726   \xdef{saved@footnote}{\the\c@footnote}%
727 }
728 \newcommand{\get@familiarfootnote@number}{%
729   \unless\ifnofamiliar@%
730     \def\do##1{\setcounter{footnote##1@typeset}{\csuse{saved@footnote##1}}}%
731     \dolistloop{@series}%
732   \fi%
733   \setcounter{footnote@typeset}{\saved@footnote}%
734 }
735 %

```

V.3 Create hooks

Read the reledmac code handbook about \newhookcommand@series. Here, we create hooks which are specific to reledpar.

```

736 \unless\ifnocritical@%
737   \newhookcommand@series{Xonlyside}%
738 \fi%
739 \unless\ifnofamiliar@%
740   \newhookcommand@series{onlysideX}%
741 \fi
742
743 %

```

V.4 Init standards series (A,B,C,D,E,Z)

\init@series@par \newseries@par is called by \newseries. However, this last command is called before reledpar is loaded. Thus, we need to initiate a specific series hook for reledpar.

```

745 \newcommand{\init@series@par}{%
746   \def\do##1{\newseries@par{##1}}%
747   \dolistloop{@series}%
748 }%
749 \init@series@par%
750 %

```

V.5 Tools specific to L^AT_EX's classical footnotes

As users can use classical footnotes of L^AT_EX (\footnote) in parallel texts, we must integrate the same tools to get correct number as for reledmac' footnotes (V.2.1 p. 46).

```
\footnote@reading51 \newcount\footnote@reading%
\footnote@typeset52 \newcounter{footnote@typeset}%
753 %
```

VI Pstart numbers dumping and restoration

While in reledmac the footnotes are inserted at the same time as the \pstart... \pend are read, in reledpar they are inserted when the \Columns or \Pages commands are called. Consequently, if we do nothing, the value of the PstartL and PstartR counters are not the same in the main text and in the notes. To solve this problem, we dump the values in two list (one by side) when processing \pstart and restore these at each \pstart when calling \Columns or \Pages. We also dump and restore the value of the boolean \ifnumberpstart.

So, first step, creating the lists. Here, “pc” means “public counters”.

```
\list@pstartL@pc54 \list@create{\list@pstartL@pc}%
\list@pstartR@pc55 \list@create{\list@pstartR@pc}%
756 %
```

Two commands to dump current pstarts. We prefer two commands to one with argument indicating the side, because the commands are short, and so we save one test (or a \csname construction).

```
\dump@pstartL@pc57 \def\dump@pstartL@pc{%
\dump@pstartR@pc58 \xright@appenditem{\the\c@pstartL}\to\list@pstartL@pc%
759 \global\cslet{numberpstart@L}{\the\l@dnumpstartsL}{\ifnumberpstart}%
760 }%
761
762 \def\dump@pstartR@pc{%
763 \xright@appenditem{\the\c@pstartR}\to\list@pstartR@pc%
764 \global\cslet{numberpstart@R}{\the\l@dnumpstartsR}{\ifnumberpstart}%
765 }%
766
767 %
```

\restore@pstartL@pc And so, the commands to restore them.

```
\restore@pstartR@pc
768 \def\restore@pstartL@pc{%
769 \ifx\list@pstartL@pc\empty\else%
770 \gl@p\list@pstartL@pc\to\@temp%
771 \global\c@pstartL=\@temp%
772 \fi%
```

```

773 }%
774 \def\restore@pstartR@pc{%
775   \ifx\list@pstartR@pc\empty\else%
776     \gl@p\list@pstartR@pc\to\@temp%
777     \global\c@pstartR=\@temp%
778   \fi%
779 }%
780 %

```

VII Parallel environments

The initial set up for parallel processing is deceptively simple.

pairs pages

- `chapterinpages` The pairs environment is for parallel columns and the pages environment for parallel pages.

```

781 \newenvironment{pairs}{%
782   \l@dpairingtrue
783   \l@dpagingfalse
784   \initnumbering@quote
785   \save@familiarfootnote@number%
786   \if@ledgroup%
787     \get@familiarfootnote@number%
788   \fi%
789   \save@section@number%
790   \at@begin@pairs%
791 }{%
792   \l@dpairingfalse
793 }
794 %
795 %

```

- `\AtBeginPairs` The `\AtBeginPairs` macro just define a `\at@begin@pairs` macro, called at the beginning of each pairs environments.

```

796 \newcommand{\AtBeginPairs}[1]{\xdef\at@begin@pairs{\#1}}%
797 \def\at@begin@pairs{}%
798 %
799 %

```

The pages environment additionally sets the ‘column’ widths to the `\textwidth` (as known at the time the package is called). In this environment, there are two text in parallel on 2 pages.

```

800 \newenvironment{pages}{%
801   \l@dpairingtrue
802   \l@dpagingtrue
803   \initnumbering@quote

```

```

804   \save@familiarfootnote@number%
805   \if@ledgroup%
806     \get@familiarfootnote@number%
807   \fi%
808   \save@section@number%
809   \setlength{\Lcolwidth}{\textwidth}%
810   \setlength{\Rcolwidth}{\textwidth}%
811 }{%
812   \l@dpairingfalse
813   \l@dpagingfalse
814 }
815 %
816 %

```

iinstanzaL These boolean tests are switched by the `\stanza` command, using either the left or right **iinstanzaR** side.

```

817 \newif\iinstanzaL
818 \newif\iinstanzaR
819 %

```

Leftside Within the pairs and pages environments the left and right hand texts are within **Leftside** and **Rightside** environments, respectively. The **Leftside** environment is simple, indicating that right text is not within its purview and using some particular macros.

```

820 \newenvironment{Leftside} {%
821   \expandafter\ifvoid\csname l@dLcolrawbox1\endcsname\else%
822     \led@err@Leftside@PreviousNotPrinted%
823   \fi%
824   \ledRcolfalse
825   \setcounter{pstartL}{1}
826   \let\pstart\pstartL
827   \let\thePstart\thePstartL
828   \let\pend\pendL
829   \let\memorydump\memorydumpL
830   \Leftsidehook
831   \let\old@startstanza\@startstanza
832   \def\@startstanza[##1]{\global\instanzaLtrue\old@startstanza[##1]}
833 }{
834   \Leftsidehookend
835 %

```

\Leftsidehook Hooks into the start and end of the **Leftside** and **Rightside** environments. These are initially empty.

```

\Rightsidehook
836 \newcommand*{\Leftsidehook} {}
\Rightsidehookend
837 \newcommand*{\Leftsidehookend} {}
838 \newcommand*{\Rightsidehook} {}
839 \newcommand*{\Rightsidehookend} {}

```

```
840 %
841 %
```

Rightside The Rightside environment is only slightly more complicated than the Leftside. Apart from indicating that right text is being provided it ensures that the right right text code will be used.

```
842 \newenvironment{Rightside}{%
843   \expandafter\ifvoid\csname l@dRcolrawbox1\endcsname\else%
844   \led@err@Rightside@PreviousNotPrinted%
845   \fi%
846   \ledRcoltrue
847   \let\beginnumbering\beginnumberingR
848   \let\endnumbering\endnumberingR
849   \let\pausenumbering\pausenumberingR
850   \let\resumenumbering\resumenumberingR
851   \let\memorydump\memorydumpR
852   \let\thepstart\thepstartR
853   \let\pstart\pstartR
854   \let\pend\pendR
855   \let\ledpb\ledpbR
856   \let\lednopp\lednoppR
857   \let\lineation\lineationR
858   \Rightsidehook
859   \let\old@startstanza\@startstanza
860   \def\@startstanza[##1]{\global\instanzaRtrue\old@startstanza[##1]}
861 }{%
862   \ledRcolfalse
863   \Rightsidehookend
864 }
865 %
866 %
```

VIII Paragraph decomposition and reassembly

In order to be able to count the lines of text and affix line numbers, we add an extra stage of processing for each paragraph. We send the paragraph into a box register, rather than straight onto the vertical list, and when the paragraph ends we slice the paragraph into its component lines; to each line we add any notes or line numbers, add a command to write to the line-list, and then at last send the line to the vertical list. This section contains all the code for this processing.

VIII.1 Boxes, counters, \pstart and \pend

\num@linesR Here are numbers and flags that are used internally in the course of the paragraph decomposition.

\par@lineR When we first form the paragraph, it goes into a box register, \l@dLcolrawbox or \l@dRcolrawbox for right text, instead of onto the current vertical list. The

\ifnumberedpar@ flag will be true while a paragraph is being processed in that way. \num@lines(R) will store the number of lines in the paragraph when it is complete. When we chop it up into lines, each line in turn goes into the \one@line or \one@lineR register, and \par@line(R) will be the number of that line within the paragraph.

```
867 \newcount\num@linesR
868 \newbox\one@lineR
869 \newcount\par@lineR
870 %
```

\pstartL \pstart starts the paragraph by clearing the \inserts@list list and other relevant variables, and then arranges for the subsequent text to go into the appropriate box. \pstart needs to appear at the start of every paragraph that is to be numbered.

Beware: everything that occurs between \pstart and \pend is happening within a group; definitions must be global if you want them to survive past the end of the paragraph.

We have to have specific left and right \pstart when parallel processing; among other things because of potential changes in the linewidth.

```
871
872 \newcounter{pstartL}
873 \renewcommand{\thepstartL}{{\bfseries\@arabic\c@pstartL}. }
874 \newcounter{pstartR}
875 \renewcommand{\thepstartR}{{\bfseries\@arabic\c@pstartR}. }

876
877 \newcommandx*[\pstartL][1][1]{%
878   \if@nobreak%
879     \let\oldnobreak\@nobreaktrue%
880   \else%
881     \let\oldnobreak\@nobreakfalse%
882   \fi%
883   \nobreaktrue%
884   \ifluatex%
885     \xdef\l@luatextextdir@L{\the\textdir}%
886     \xdef\l@luatexpardir@L{\the\pardir}%
887     \xdef\l@luatexbodydir@L{\the\bodydir}%
888   \fi%
889   \ifnumbering \else%
890     \led@err@PstartNotNumbered%
891     \beginnumbering%
892   \fi%
893   \ifnumberedpar@%
894     \led@err@PstartInPstart%
895     \pend%
896   \fi%
897 }%
```

If this is the first \pstart in a numbered section, clear any inserts and set \ifpst@rtedL to FALSE.

```

898 \ifpst@rtedL\else%
899   \list@clear{\inserts@list}%
900   \global\let\next@insert=\empty%
901   \global\pst@rtedLtrue%
902 \fi%
903 \begingroup\everypar{}%
904 %

```

When parallel processing we check that we have not exceeded the maximum number of chunks. In any event we grab a box for the forthcoming text.

```

905 \global\advance\l@dnumstartsL \cne%
906 \ifnum\l@dnumstartsL>\l@dc@maxchunks%
907   \led@err@TooManyPstarts%
908   \global\l@dnumstartsL=\l@dc@maxchunks%
909 \fi%
910 \global\setnamebox{\l@dLcolrawbox\the\l@dnumstartsL}=\vbox\bgroup%
911 %

```

We set all the usual interline penalties to zero; this ensures that there will be no large interline penalties to prevent us from slicing the paragraph into pieces. These penalties revert to the values that you set when the group for the \vbox ends.

```

912 \l@dzopenalties%
913 \ifautopar\else%
914   \ifnumberpstart%
915     \ifsidepstartnum%
916       \else%
917         \thepstartL%
918       \fi%
919     \fi%
920   \fi%
921 \hsize=\Lcolwidth%
922 \numberedpar@true%
923 \iflabelpstart\protected@edef\@currentlabel%
924   {\p@pstartL\thepstartL}\fi%
925 %

```

Dump the optional arguments

```

926 \ifstrempty{#1}%
927   {\csgdef{before@pstartL@\the\l@dnumstartsL}{\at@every@pstart}{}%
928   {\csgdef{before@pstartL@\the\l@dnumstartsL}{\noindent#1}{}%
929   \at@every@pstart@call}%
930 %

```

Gobble following space (automatically done if there is no optional argument)

```

931 \ignorespaces%
932 %
933 }
934 %

```

The same for right side.

```

935 \newcommandx*\pstartR}[1][1]{%
936   \if@nobreak%
937     \let\oldnobreak\@nobreaktrue%
938   \else%
939     \let\oldnobreak\@nobreakfalse%
940   \fi%
941   \@nobreaktrue%
942   \ifluatex%
943     \xdef\l@luatextextdir@R{\the\textdir}%
944     \xdef\l@luatexpardir@R{\the\pardir}%
945     \xdef\l@luatexbodydir@R{\the\bodydir}%
946   \fi%
947   \ifnumberingR \else%
948     \led@err@PstartNotNumbered%
949     \beginnumberingR%
950   \fi%
951   \ifnumberedpar@%
952     \led@err@PstartInPstart%
953     \pendR%
954   \fi%
955   \ifpst@rtedR \else%
956     \list@clear{\inserts@listR}%
957     \global\let\next@insertR=\empty%
958     \global\pst@rtedRtrue%
959   \fi%
960   \begingroup\everypar{}%
961   \global\advance\l@dnumpstartsR \one%
962   \ifnum\l@dnumpstartsR>\l@dc@maxchunks%
963     \led@err@TooManyPstarts%
964     \global\l@dnumpstartsR=\l@dc@maxchunks%
965   \fi%
966   \global\setnamebox{\l@Rcolrawbox\the\l@dnumpstartsR}=\vbox\bgroup%
967     \l@zeropenalties%
968     \ifautopar\else%
969       \ifnumberpstart%
970         \ifsidepstartnum\else%
971           \thepstartR%
972         \fi%
973       \fi%
974     \fi%
975     \hsize=\Rcolwidth%
976     \numberedpar@true%
977     \iflabelpstart\protected@edef\@currentlabel{%
978       \p@pstartR\thepstartR}\fi%
979     \ifstrempty{\#1}%
980       {\csgdef{before@pstartR@\the\l@dnumpstartsR}{\at@every@pstart}{}%
981       {\csgdef{before@pstartR@\the\l@dnumpstartsR}{\noindent\#1}{}%
982       \at@every@pstart@call%

```

```

983     \ignorespaces%
984 }
985 %

```

\pendL \pend must be used to end a numbered paragraph. Again we need a version that knows about left parallel texts.

```

986 \newcommandx*{\pendL}[1][1]{%
987   \ifnumbering \else%
988     \led@err@PendNotNumbered%
989   \fi%
990   \ifnumberedpar@ \else%
991     \led@err@PendNoPstart%
992   \fi%
993 %

```

We immediately call \endgraf to end the paragraph; this ensures that there will be no large interline penalties to prevent us from slicing the paragraph into pieces.

```

994 \endgraf\global\num@lines=\prevgraf\egroup%
995 \global\par@line=0%
996 %

```

End the group that was begun in the \pstart.

```

997 \endgroup%
998 \ignorespaces%
999 \oldnobreak%
1000 \dump@pstartL@pc%
1001 \ifnumberpstart%
1002   \addtocounter{pstartL}{1}%
1003 \fi
1004 \parledgroup@beforenotes@save{L}%
1005 %

```

Dump content of the optional argument.

```

1006 \ifstrempty{#1}%
1007   {\csgdef{after@pendL@the\l@dnumpstartsL}{\at@every@pend}{}%
1008   {\csgdef{after@pendL@the\l@dnumpstartsL}{\noindent#1}{}%
1009   }%
1010 %

```

\pendR The version of \pend needed for right texts.

```

1011 \newcommandx*{\pendR}[1][1]{%
1012   \ifnumberingR \else%
1013     \led@err@PendNotNumbered%
1014   \fi%
1015   \ifnumberedpar@ \else%
1016     \led@err@PendNoPstart%
1017   \fi%

```

```

1018 \endgraf\global\num@linesR=\prevgraf\egroup%
1019 \global\par@lineR=0%
1020 \endgroup%
1021 \ignorespaces%
1022 \oldnobreak%
1023 \dump@pstartR@pc%
1024 \ifnumberpstart%
1025   \addtocounter{pstartR}{1}%
1026 \fi%
1027 \parledgroup@beforenotes@save{R}%
1028 \ifstrempty{#1}%
1029   {\csgdef{after@pendR@the\l@dnumpstartsR}{\at@every@pend}{}%
1030   {\csgdef{after@pendR@the\l@dnumpstartsR}{\noindent#1}{}%
1031 }
1032 %
1033 %

```

\AtEveryPstartCall The `\AtEveryPstartCall` argument is called when the `\pstartL` or `\pstartR` is called. That is different of `\AtEveryPstart` the argument of which is called when the `\pstarts` are printed.

```

1034 \newcommand{\AtEveryPstartCall}[1]{\gdef\at@every@pstart@call{#1}{}%
1035 \gdef\at@every@pstart@call{}%
1036 %

```

\ifprint@last@after@pendL Two booleans set to true, when the time is to print the last optional argument of a `\pend`.

```

1037 \newif\ifprint@last@after@pendL%
1038 \newif\ifprint@last@after@pendR%
1039 %

```

VIII.2 Processing one line

For parallel texts we have to be able to process left and right lines independently. For sequential text we happily use the original `\do@line`. Otherwise ...

\l@dleftbox A line of left text will be put in the box `\l@dleftbox`, and analogously for a line of right
\l@drightbox text.

```

1040 \newbox\l@dleftbox
1041 \newbox\l@drightbox
1042 %
1043 %

```

\countLline We need to know the number of lines processed.

```

1044 \newcount\countLline
1045   \countLline \z@
1046 \newcount\countRline

```

```

1047 \countRline \z@%
1048 %
1049 %

```

\@donereallinesL We need to know the number of ‘real’ lines output (i.e., those that have been input by the user), and the total lines output (which includes any blank lines output for synchronisation).

\@donetotallinesR

```

1050 \newcount\@donereallinesL
1051 \newcount\@donetotallinesL
1052 \newcount\@donereallinesR
1053 \newcount\@donetotallinesR
1054 %
1055 %

```

\do@lineL The \do@lineL macro is called to do all the processing for a single line of left text.

```

1056 \newcommand*\do@lineL{%
1057   \letcs{\ifnumberpstart}{numberpstart@L\the\l@dpscL}%
1058   \advance\countRline \z@%
1059   \ifvbox\namebox{\l@dLcolrawbox\the\l@dpscL}%
1060     {\vbadness=10000%
1061      \splittopskip=\z@%
1062      \do@lineLhook%
1063      \l@demptyd@ta%
1064      \global\setbox\one@line=\vsplit\namebox{\l@dLcolrawbox\the\l@dpscL}%
1065        to\baselineskip}%
1066      \IfStrEq{\splitfirstmarks}{parledgroup@}{begin}{%
1067        parledgroup@notes@startL}{}%
1068        \unvbox\one@line \global\setbox\one@line=\lastbox%
1069        \@writepageofparL%
1070        \getline@numL%
1071        \ifnum\@clock>\z@%
1072          \inserthangingsymboltrue%
1073        \else%
1074          \inserthangingsymbolfalse%
1075        \fi%
1076        \setbox\l@leftbox%
1077        \hb@xt@ \Lcolwidth{%
1078          \ifl@dhidenumber%
1079            \global\l@dhidenumberfalse%
1080            \f@x@l@cks%
1081          \else%
1082            \affixline@num%
1083          \fi%
1084          \xifinlist{\the\l@dpscL}{\eled@sections@@}%
1085            {\add@inserts\affixside@note}%
1086            {\print@lineL}%
1087          }%
1088        }%

```

```

1087   \add@penaltiesL%
1088   \global\advance\@donereallinesL\@ne%
1089   \global\advance\@donetotallinesL\@ne%
1090 \else%
1091   \iflinenumberLevenifblank
1092     \new@lineL%
1093     \l@emptyd@ta%
1094     \getline@numL%
1095     \affixline@num%
1096     \setbox\l@leftbox \hb@xt@ \Lcolwidth{%
1097       \l@dld@ta %space kept for backward compatibility
1098       \hspace*\{\Lcolwidth\}%
1099       \ledrlfill\l@drd@ta%
1100     }%
1101   \else%
1102     \setbox\l@leftbox \hb@xt@ \Lcolwidth{\hspace*\{\Lcolwidth\}}%
1103   \fi%
1104   \global\advance\@donetotallinesL\@ne%
1105 \fi%
1106 }%
1107
1108
1109 %

```

\print@lineL \print@lineL is for lines without a sectioning command. See `reledmac` definition of \print@line for handbook.

```

1110 \def\print@lineL{%
1111   \affixpstart@numL%
1112   \l@dld@ta %space kept for backward compatibility
1113   \add@inserts\affixside@note%
1114   \l@dlsn@te %space kept for backward compatibility
1115   \hb@xt@ \Lcolwidth{\ledllfill\hb@xt@ \wd\one@line{%
1116     \do@insidelineLhook%
1117     \ifluatex%
1118       \textdir\l@luatextextdir@L%
1119     \fi%
1120     \new@lineL%
1121     \inserthangingsymbolL%
1122     \l@unhbox@line{\one@line}\ledrlfill\l@drd@ta%
1123     \l@drsn@te}%
1124   }%
1125 %

```

\print@eledsectionL \print@eledsectionL is for line with macro code.

```

1126 \def\print@eledsectionL{%
1127   \addtocounter{pstartL}{-1}%
1128   \ifdefstring{\@eledsectnotoc}{L}{\ledsectnotoc}{}%
1129   \ifdefstring{\@eledsectmark}{L}{}{\ledsectnomark}

```

```

1130   \numdef{\temp@}{\l@dpscL-1}%
1131   \xifinlist{\temp@}{\eled@sections@@}{\nobreaktrue}{\nobreakfalse}%
1132   \@eled@sectioningtrue%
1133   \bgroup%
1134     \ifluatex%
1135       \textdir\l@luatextextdir@L%
1136       \pardir\l@luatexpardir@L%
1137       \bodydir\l@luatexbodydir@L%
1138       \ifdefstring{\l@luatextextdir@L}{TRT}{\@RTLtrue}{}
1139     \fi%
1140     \csuse{\eled@sectioning@\the\l@dpscL}%
1141   \egroup%
1142   \@eled@sectioningfalse%
1143   \global\csundef{\eled@sectioning@\the\l@dpscL}%
1144   \if@RTL%
1145     \hspace{-3\paperwidth}%
1146     {\hbox{\l@unhbox@line{\one@line}} \new@line}%
1147   \else%
1148     \hspace{3\paperwidth}%
1149     {\new@line \hbox{\l@unhbox@line{\one@line}}}%
1150   \fi%
1151   \vskip\eledsection@correcting@skip%
1152 }
1153 %
1154 %

```

\dolineLhook These high-level commands just redefine the low-level commands. They have to be used by user, without \makeatletter.

```

\doin sidelineLhook 1155 \newcommand*{\dolineLhook}[1]{\gdef\do@lineLhook{#1}}%
\doin sidelineRhook 1156 \newcommand*{\dolineRhook}[1]{\gdef\do@lineRhook{#1}}%
1157 \newcommand*{\doin sidelineLhook}[1]{\gdef\do@insidelineLhook{#1}}%
1158 \newcommand*{\doin sidelineRhook}[1]{\gdef\do@insidelineRhook{#1}}%
1159 %
1160 %

```

\do@lineLhook Hooks, initially empty, into the respective \do@line(L/R) macros.

```

\do@lineRhook 1161 \newcommand*{\do@lineLhook}{}%
\do@insidelineLhook 1162 \newcommand*{\do@lineRhook}{}%
\do@insidelineRhook 1163 \newcommand*{\do@insidelineLhook}{}%
1164 \newcommand*{\do@insidelineRhook}{}%
1165 %
1166 %

```

\do@lineR The \do@lineR macro is called to do all the processing for a single line of right text.

```

1167 \newcommand*{\do@lineR}{%
1168   \let\linenumrepL\linenumrep%

```

```

1169 \let\sublinenumrepL\sublinenumrep%
1170 \let\linenumrep\linenumrepR%
1171 \let\sublinenumrep\sublinenumrepR%
1172 \let\cs{\ifnum\pstart}{\number\pstart\the\l@dpst}%
1173 \ledRcol@true%
1174 \advance\countRline \cne%
1175 \ifvbox\namebox{\l@dpst\rawbox\the\l@dpst}%
1176 {\vbadness=10000%
1177 \splittopskip=\z@%
1178 \do@lineRhook%
1179 \l@emptyd@ta%
1180 \global\setbox\one@lineR=\vsplit\namebox{\l@dpst\rawbox\the\l@dpst}%
1181 to\baselineskip}%
1182 \IfStrEq{\splitfirstmarks\parledgroup@}{begin}{%
1183   \parledgroup@notes@startR}{}%
1184   \unvbox\one@lineR \global\setbox\one@lineR=\lastbox%
1185   \writepageofparR%
1186   \getline@numR%
1187   \ifnum\clockR>\cne%
1188     \inserthangingsymbolRtrue%
1189   \else%
1190     \inserthangingsymbolRfalse%
1191   \fi%
1192   \setbox\l@driftbox%
1193   \hb@xt@ \Rcolwidth{%
1194     \ifl@dhidenumber%
1195       \global\l@dhidenumberfalse%
1196       \f@x@l@cksR%
1197     \else%
1198       \affixline@numR%
1199     \fi%
1200   \xifinlist{\the\l@dpst}{\eled@sectionsR@@}%
1201   {\add@insertsR\affixside@noteR}%
1202   {\print@lineR}%
1203 }%
1204 \add@penaltiesR%
1205 \global\advance\donereallinesR\cne%
1206 \global\advance\donetotallinesR\cne%
1207 \else%
1208   \iflinenumberRevenifblank%
1209     \new@lineR
1210     \l@emptyd@ta%
1211     \getline@numR%
1212     \setbox\l@driftbox \hb@xt@ \Rcolwidth{%
1213       \affixline@numR%
1214       \l@ldd@ta %space kept for backward compatibility
1215       \hspace*\{\Rcolwidth\}%
1216       \ledrlfill\l@drd@ta%
1217     }%
1218   \else%

```

```

1218     \setbox\l@rightbox \hb@xt@ \Rcolwidth{\hspace*\{\Rcolwidth\}}%
1219     \fi%
1220     \global\advance\donetotallinesR\@ne%
1221 \fi%
1222 \ledRcol@false%
1223 \let\linenumrep\linenumrepL%
1224 \let\sublinenumrep\sublinenumrepL%
1225 }
1226
1227
1228 %

```

```
\print@lineR
\print@eledsectionR
```

VIII.3 Line and page number computation

`\getline@numR` The `\getline@numR` macro determines the page and line numbers for the right text line we are about to send to the vertical list. The `\getline@numL` is the same for left text.

```

1229 \newcommand*{\getline@numR}{%
1230   \global\advance\absline@numR \@ne
1231   \do@actionsR
1232   \do@ballastR
1233   \ifledgroupnotesR@\else
1234     \ifnumberline
1235       \ifsingles@
1236         \ifnum\sub@lockR<\tw@
1237           \global\advance\subline@numR \@ne
1238         \fi
1239       \else
1240         \ifnum\@clockR<\tw@
1241           \global\advance\line@numR \@ne
1242           \global\subline@numR \z@
1243         \fi
1244       \fi
1245     \fi
1246   \fi
1247 }
1248 \newcommand*{\getline@numL}{%
1249   \global\advance\absline@num \@ne
1250   \do@actions
1251   \do@ballast
1252   \ifledgroupnotesL@\else
1253     \ifnumberline
1254       \ifsingles@
1255         \ifnum\sub@lock<\tw@
1256           \global\advance\subline@num \@ne
1257         \fi
1258       \else
1259         \ifnum\@clock<\tw@

```

```

1260           \global\advance\line@num \cne
1261           \global\subline@num \z@
1262       \fi
1263   \fi
1264 \fi
1265 }
1267
1268
1269 %

```

\do@ballastR The real work in the line macros above is done in \do@actions, but before we plunge into that, let us get \do@ballastR out of the way.

```

1270 \newcommand*{\do@ballastR}{\global\ballast@count=\z@
1271 \begingroup
1272   \advance\absline@numR \cne
1273   \ifnum\next@actionlineR=\absline@numR
1274     \ifnum\next@actionR>-1001
1275       \global\advance\ballast@count by -\c@ballast
1276     \fi
1277   \fi
1278 \endgroup}
1279 %

```

\l@dskipversenumberR The \do@actionsR macro looks at the list of actions to take at particular right text absolute line numbers, and does everything that is specified for the current line.

\do@actions@fixedcodeR It may call itself recursively and we use tail recursion, via \do@actions@nextR for \do@actions@nextR this.

```

1280
1281 \newif\ifl@dskipversenumberR
1282 \newcommand*{\do@actions@fixedcodeR}{%
1283   \ifcase\@l@dtmcnta%
1284     \or% % 1001
1285       \global\sublines@true
1286     \or% % 1002
1287       \global\sublines@false
1288     \or% % 1003
1289       \global\@clockR=\cne
1290     \or% % 1004%
1291       \ifnum\@clockR=\tw@
1292         \global\@clockR=\thr@@
1293       \else
1294         \global\@clockR=\z@
1295       \fi
1296     \or% % 1005
1297       \global\sub@clockR=\cne
1298     \or% % 1006
1299       \ifnum\sub@clockR=\tw@

```

```

1300      \global\sub@lockR=\thr@@
1301      \else
1302          \global\sub@lockR=\z@
1303      \fi
1304      \or%                                % 1007
1305          \l@dskipnumbertrue
1306      \or%                                % 1008
1307          \l@dskipversenumberRtrue%
1308      \or%                                % 1009
1309          \l@dhidenumbertrue%
1310      \else%
1311          \led@warn@BadAction
1312      \fi%
1313  }

1314

1315 \newcommand*{\do@actionsR}{%
1316     \global\let\do@actions@nextR=\relax
1317     \l@dtmpcntb=\absline@numR
1318     \ifnum\l@dtmpcntb<\next@actionlineR\else
1319         \ifnum\next@actionR>-1001\relax
1320             \global\page@numR=\next@actionR
1321             \ifbypage@R
1322                 \global\line@numR \z@ \global\subline@numR \z@
1323             \fi
1324         \fi
1325     \else
1326         \ifnum\next@actionR<-4999\relax    % 9/05 added relax here
1327             \l@dtmpcnta=-\next@actionR
1328             \advance\l@dtmpcnta by -5001\relax
1329             \ifsublines@%
1330                 \global\subline@numR=\l@dtmpcnta
1331             \else
1332                 \global\line@numR=\l@dtmpcnta
1333             \fi
1334     \else
1335         \l@dtmpcnta=-\next@actionR
1336         \advance\l@dtmpcnta by -1000\relax
1337         \do@actions@fixedcodeR
1338     \fi
1339 \fi
1340 \ifx\actionlines@listR\empty
1341     \gdef\next@actionlineR{1000000}%
1342 \else
1343     \gl@p\actionlines@listR\to\next@actionlineR
1344     \gl@p\actions@listR\to\next@actionR
1345     \global\let\do@actions@nextR=\do@actionsR
1346 \fi
1347 \fi
1348 \do@actions@nextR}
1349

```

1350 %

VIII.4 Line number printing

```

1350 \affixline@numR is the right text version of the \affixline@num macro.
1351
1352 \ch@cksub@l@ckR
1353   \ch@ck@l@ckR
1354     \newcommand*{\l@dcalcnum}[3]{%
1355       \ifnum #1 > #2\relax
1356         \o@l@dtempcpta = #1\relax
1357         \advance\o@l@dtempcpta by -#2\relax
1358         \divide\o@l@dtempcpta by #3\relax
1359         \multiply\o@l@dtempcpta by #3\relax
1360         \advance\o@l@dtempcpta by #2\relax
1361       \else
1362         \o@l@dtempcpta=#2\relax
1363       \fi}
1364
1365 \newcommand*{\ch@cksub@l@ckR}{%
1366   \ifcase\sub@clockR
1367     \or
1368       \ifnum\sublock@disp=\@ne
1369         \o@l@dtempcntb \z@ \o@l@dtempcpta \@ne
1370       \fi
1371     \or
1372       \ifnum\sublock@disp=\tw@
1373       \else
1374         \o@l@dtempcntb \z@ \o@l@dtempcpta \@ne
1375       \fi
1376     \or
1377       \ifnum\sublock@disp=\z@
1378         \o@l@dtempcntb \z@ \o@l@dtempcpta \@ne
1379       \fi
1380     \fi}
1381
1382 \newcommand*{\ch@ck@l@ckR}{%
1383   \ifcase\@clockR
1384     \or
1385       \ifnum\lock@disp=\@ne
1386         \o@l@dtempcntb \z@ \o@l@dtempcpta \@ne
1387       \fi
1388     \or
1389       \ifnum\lock@disp=\tw@
1390       \else
1391         \o@l@dtempcntb \z@ \o@l@dtempcpta \@ne
1392       \fi
1393     \or
1394       \ifnum\lock@disp=\z@
1395         \o@l@dtempcntb \z@ \o@l@dtempcpta \@ne

```

```

1394     \fi
1395   \fi}
1396
1397 \newcommand*{\f@x@l@cksR}{%
1398   \ifcase\@clockR
1399   \or
1400     \global\@clockR \tw@
1401   \or \or
1402     \global\@clockR \z@
1403   \fi
1404 \ifcase\sub@lockR
1405   \or
1406     \global\sub@lockR \tw@
1407   \or \or
1408     \global\sub@lockR \z@
1409   \fi}
1410
1411 \newcommand*{\affixline@numR}{%
1412   \ifledgroupnotesR@ \else \ifnumberline
1413   \ifl@dskipnumber
1414     \global\l@dskipnumberfalse
1415   \else
1416     \ifsublines@
1417       \o1@dtempcntb=\subline@numR
1418       \l@dcalcn{\subline@numR}{\c@firstsublinenumR}{\c@sublinenumincrementR}
1419   }%
1420   \ch@cksub@lockR
1421 \else
1422   \o1@dtempcntb=\line@numR
1423   \ifx\linenumberlist\empty
1424     \l@dcalcn{\line@numR}{\c@firstlinenumR}{\c@linenumincrementR}%
1425   \else
1426     \o1@dtempcnta=\line@numR
1427     \edef\rem@nder{,\linenumberlist,\number\line@numR,}%
1428     \edef\sc@n@list{\def\noexpand\sc@n@list
1429     #####1,\number\o1@dtempcnta,#####2|{\def\noexpand\rem@nder{####2}}}}%
1430     \sc@n@list\expandafter\sc@n@list\rem@nder|%
1431     \ifx\rem@nder\empty\advance\o1@dtempcnta\@ne\fi
1432   \fi
1433   \ch@ck@l@ckR
1434 \fi
1435 \ifnum\o1@dtempcnta=\o1@dtempcntb
1436   \ifl@dskipversenumberR\else
1437     \if@twocolumn
1438       \if@firstcolumn
1439         \gdef\l@ldd@ta{\llap{{\leftlinenumR}}}%
1440       \else
1441         \gdef\l@rd@ta{\rlap{{\rightlinenumR}}}%
1442     \fi

```

```

1443 \else
1444   \if@dtmpcntb=\line@marginR
1445   \ifnum\if@dtmpcntb>\@ne
1446     \advance\if@dtmpcntb by\page@numR
1447   \fi
1448   \ifodd\if@dtmpcntb
1449     \gdef\l@drd@ta{\rlap{{\rightlinenumR}}\%}
1450   \else
1451     \gdef\l@drd@ta{\llap{{\leftlinenumR}}\%}
1452   \fi
1453   \fi
1454 \fi
1455 \fi
1456 \f@x@l@cksR
1457 \fi
1458 \fi
1459 \fi}
1460 %

```

VIII.5 Pstart number printing in side

The printing of the pstart number is like in `reledmac`, with two differences :

- Some commands have versions suffixed by R or L.
- The `\affixpstart@num` and `\affixpstart@numR` commands are called in the `\Pages` command. Consequently, the `pstartL` and `pstartR` counters must be reset at the beginning of this command.

```

\affixpstart@numL61
\affixpstart@numR62 \newcommand*\affixpstart@numL{%
\leftpstartnumR63 \ifsidepstartnum
\rightpstartnumR64 \if@twocolumn
\leftpstartnumL65   \if@firstcolumn
\rightpstartnumL66   \gdef\l@drd@ta{\llap{{\leftpstartnumL}}\%}
\rightpstartnumL67 \else
\rightpstartnumR68   \gdef\l@drd@ta{\rlap{{\rightpstartnumL}}\%}
\rightpstartnumR69 \fi
\rightpstartnumR70 \else
\rightpstartnumR71   \if@dtmpcntb=\line@margin
\rightpstartnumR72   \ifnum\if@dtmpcntb>\@ne
\rightpstartnumR73     \advance\if@dtmpcntb \page@num
\rightpstartnumR74   \fi
\rightpstartnumR75   \ifodd\if@dtmpcntb
\rightpstartnumR76     \gdef\l@drd@ta{\rlap{{\rightpstartnumL}}\%}
\rightpstartnumR77   \else
\rightpstartnumR78     \gdef\l@drd@ta{\llap{{\leftpstartnumL}}\%}
\rightpstartnumR79   \fi
\rightpstartnumR80 \fi

```

```

1481 \fi
1482 }
1483 \newcommand*{\affixpstart@numR}{%
1484 \ifsidepstartnum
1485 \if@twocolumn
1486   \if@firstcolumn
1487     \gdef\l@ldld@ta{\llap{{\leftpstartnumR}}}
1488   \else
1489     \gdef\l@drd@ta{\rlap{{\rightpstartnumR}}}
1490   \fi
1491 \else
1492   \l@dtmpcntb=\line@marginR
1493   \ifnum\l@dtmpcntb>\@ne
1494     \advance\l@dtmpcntb \page@numR
1495   \fi
1496   \ifodd\l@dtmpcntb
1497     \gdef\l@drd@ta{\rlap{{\rightpstartnumR}}}
1498   \else
1499     \gdef\l@ldld@ta{\llap{{\leftpstartnumR}}}
1500   \fi
1501 \fi
1502 \fi
1503 }
1504 \newcommand*{\leftpstartnumL}{%
1505 \ifpstartnum
1506 \theplstartL
1507 \kern\linenumsep\global\pstartnumfalse\fi
1508 }
1509 \newcommand*{\rightpstartnumL}{%
1510 \ifpstartnum\kern\linenumsep
1511 \theplstartL
1512 \global\pstartnumfalse\fi
1513 }
1514 \newif\ifpstartnumR
1515 \pstartnumRtrue
1516 \newcommand*{\leftpstartnumR}{%
1517 \ifpstartnumR
1518 \theplstartR
1519 \kern\linenumsep\global\pstartnumRfalse\fi
1520 }
1521 \newcommand*{\rightpstartnumR}{%
1522 \ifpstartnumR\kern\linenumsep
1523 \theplstartR
1524 \global\pstartnumRfalse\fi
1525 }
1526 %
1527 %

```

VIII.6 Add insertions to the vertical list

\inserts@listR \inserts@listR is the list macro that contains the inserts that we save up for one right text paragraph.

```
1528 \list@create{\inserts@listR}
1529 %
```

\add@insertsR The right text version.

```
\add@inserts@nextR
1530 \newcommand*{\add@insertsR}{%
1531   \global\let\add@inserts@nextR=\relax
1532   \ifx\inserts@listR\empty \else
1533     \ifx\next@insertR\empty
1534       \ifx\insertlines@listR\empty
1535         \global\noteschanged@true
1536         \gdef\next@insertR{100000}%
1537       \else
1538         \gl@p\insertlines@listR\to\next@insertR
1539       \fi
1540     \fi
1541     \ifnum\next@insertR=\absline@numR
1542       \gl@p\inserts@listR\to@\insertR
1543       @insertR
1544       \global\let@\insertR=\undefined
1545       \global\let\next@insertR=\empty
1546       \global\let\add@inserts@nextR=\add@insertsR
1547     \fi
1548   \fi
1549   \add@inserts@nextR}
1550 %
1551 %
```

VIII.7 Penalties

\add@penaltiesL \add@penaltiesL is the last macro used by \do@lineL. It adds up the club, widow, and interline penalties, and puts a single penalty of the appropriate size back into the paragraph; these penalties get removed by the \vsplit operation. \displaywidowpenalty and \brokenpenalty are not restored, since we have no easy way to find out where we should insert them.

In the code below, which is a virtual copy of the original \add@penalties, \num@lines is the number of lines in the whole paragraph, and \par@line is the line we are working on at the moment. The count \cl@dtmpcnta is used to calculate and accumulate the penalty; it is initially set to the value of \ballast@count, which has been worked out in \do@ballast. Finally, the penalty is checked to see that it does not go below -10000.

```
\newcommand*{\add@penaltiesR}{\cl@dtmpcnta=\ballast@count
\ifnum\num@linesR>\@ne
```

```
\global\advance\par@lineR \cne
\ifnum\par@lineR=\cne
    \advance\@l@dtmpcnta by \clubpenalty
\fi
\@l@dtmpcntb=\par@lineR \advance\@l@dtmpcntb \cne
\ifnum\@l@dtmpcntb=\num@linesR
    \advance\@l@dtmpcnta by \widowpenalty
\fi
\ifnum\par@lineR<\num@linesR
    \advance\@l@dtmpcnta by \interlinepenalty
\fi
\fi
\ifnum\@l@dtmpcnta=\z@
    \relax
\else
    \ifnum\@l@dtmpcnta>-10000
        \penalty\@l@dtmpcnta
    \else
        \penalty -10000
    \fi
\fi}
```

This is for a single chunk. However, as we are probably dealing with several chunks at a time, the above is nor really relevant. Peter Wilson thinks that it is likely with parallel text that there is no real need to add back any penalties; even if there was, they would have to match across the left and right lines. So, Peter Wilson ends up with the following.

```
1552 \newcommand*{\add@penaltiesL}{}
1553 \newcommand*{\add@penaltiesR}{}
1554 %
1555 %
```

VIII.8 Printing leftover notes

`\flush@notesR` The `\flush@notesR` macro is called after the entire right text has been sliced up and sent on to the vertical list.

```
1556 \newcommand*{\flush@notesR}{%
1557     \xloop
1558         \ifx\inserts@listR\empty \else
1559             \gl@p\inserts@listR\to\@insertR
1560             \@insertR
1561             \global\let\@insertR=\undefined
1562         \repeat}
1563 %
1564 %
```

IX Footnotes

IX.1 Footnotes output specific to \Pages

```
\print@Xnotes@forpages
\correct@Xfootins@box
\print@notesX@forpages
\correct@footinsX@box
```

The `\Xonlyside` and `\onlysideX` hooks for `\Pages` allow notes to be printed either in left or right pages only. The implementation of such features is delegated to `\print@Xnotes@forpages`, which replaces `\print@Xnotes` inside `\Pages`. Here is how we proceed⁶:

- If notes are to be printed in both sides, we just proceed the usual way: print the foot starts for the series, then the foot group.
- If notes are to be printed in the left side, we do these prints only for even pages ; if notes are to be printed in the right side, we do these prints only for odd pages.
- However, that is not enough. Because the problem does not only consists in printing notes in any particular page. It is also not to put aside room for notes in the pages where we do not want to print them. To take an example: if some note in the left side is too long by 160pt to be printed in full in the left page, we do not want to put aside 160pt a space for it in the following right page.
- To solve this problem, we change the magnification factor associated with notes before going to the next page. If we start a page where no notes are supposed to be printed, the magnification counter is set to 0. We also set the note skip to 0pt. Before starting a new page where these notes are supposed to be printed, we reset these counter and skip to their default values. (About these counter and skip, read *The TeXbook* p. 122-125).
- There still remains a last problem. This problem is quite complex to understand, so an example will speak for itself. Suppose we allow 10 lines of notes by page. Suppose a long note, be it 25 lines, which needs three pages to be printed. Suppose it must be printed only on left pages, namely odd pages.

On p. 2, the first 10 lines of the notes are printed. On p. 3, the box associated to the notes contains 10 lines. However, as we are in a right page, we do not void this box. So `TEX` will keep its content for the pages to come. However, on p. 4 it will also add one line in the footnote box, because in any case, `TEX` adds some content in the box when preparing the output routines, even if there is some content left in this box from the previous pages. So the lines in the note box at p. 4 will be $10 + 1 = 11$. There is one line which should not be there. Furthermore, as the box size is for 10 lines and not for 11 lines, this last line will be glued to the previous one.

To fix this double issue:

- For the pages where notes must be NOT printed, we allow to every note box one line less than it ought to be. In our example, that means that we allow `TEX` to add only $10 - 1 = 9$ line in the note box on p. 3. Before shifting to

⁶See <http://tex.stackexchange.com/a/230332/7712>.

the pages where notes must be printed, we allow to every notes the expected number of lines. In our example, that means that we allow TeX to add 10 lines in the note box on p. 4. As on p. 3 only 9 lines were allowed, that means note box of p. 4 will contain $9 + 1 = 10$ lines. So the “one line too many” problem is solved.

- Still remains the “glue” problem. We solve it by recreating a clean note box. We split the one which is created by TeX to get the next line printed. Then, we create the new box, by bringing together the first part and the last part of the split box, adding some skip between them. That is achieved by \correct@Xfootins@box (or \correct@footinsX@box for familiar notes).

The code to print critical notes, when processing \Pages.

```
1565 \newcommand\print@Xnotes@forpages[1]{%
1566 %
```

First case: notes are for both sides. Just print the note start and the note group

```
1567 \ifcsempty{Xonlyside@#1}{%
1568   \csuse{#1footstart}{#1}%
1569   \csuse{#1footgroup}{#1}%
1570 }%
1571 %
```

Second case: notes are for one side only. First test if we are in a page where they must be printed.

```
1572 {%
1573   \ifboolexpr{%
1574     ((test {\ifcsstring{Xonlyside@#1}{L}} and not test{\ifnumodd{\c@page}%
1575 }})%
1576   or%
1577   (test {\ifcsstring{Xonlyside@#1}{R}} and test{\ifnumodd{\c@page}}))%
1578 }%
```

If we are in a page where notes must be printed, print the notes, after having made the corrections which are needed for boxes.

```
1579 {%
1580   \correct@Xfootins@box{#1}%
1581   \csuse{#1footstart}{#1}%
1582   \csuse{#1footgroup}{#1}%
1583 }%
```

Then, say not to keep room for notes in the next page.

```
1584 \global\count\csuse{#1footins}=0%
1585 \global\skip\csuse{#1footins}=0pt%
1586 %
```

And also, allow one line less for notes in the next page.

```

1587   \csuse{Xnotefontsize@#1}%
1588   \global\advance\dimen\csuse{#1footins} by -\baselineskip%
1589 %

```

Now we have printed the notes. So we put aside this fact.

```

1590   \global\boolfalse{keepforXside@#1}%
1591   }%
1592 %

```

In case we are on a page where notes must NOT be printed. First, memorize that we have not printed the notes, despite having some to print.

```

1593   {%
1594     \global\booltrue{keepforXside@#1}%
1595   %

```

Then restore expected rooms for notes on the next page.

```

1596   \global\count\csuse{#1footins}=\csuse{default@#1footins}%
1597   \global\skip\csuse{#1footins}=\csuse{Xbeforenotes@#1}%
1598 %

```

Last but not least, restore the normal line number allowed to notes for the following page.

```

1599   \bgroup%
1600     \csuse{Xnotefontsize@#1}%
1601     \global\advance\dimen\csuse{#1footins} by \baselineskip%
1602   \egroup%
1603 %

1604 % End of \protect\cs{print@Xnotes@forpages}.
1605 }%
1606 }%
1607 }%
1608 %

```

Now, \correct@Xfootins@box, to fix problem of last line being glued to the previous one.

```

1609 \newcommand{\correct@Xfootins@box}[1]{%
1610 %

```

We need to make correction only in case we have not printed any note in the previous page, although there was to be “normally” printed.

```

1611   \ifbool{keepforXside@#1}{%
1612   %

```

Some setting needed to do the right splitting.

```

1613   \csuse{Xnotefontsize@#1}%
1614   \splittopskip=0pt%
1615 %

```

And now, split the last line, and push in the right place.

```

1616     \global\setbox\csuse{\#1footins}=\vbox{%
1617         \vsplit\csuse{\#1footins} to \dimexpr\ht\csuse{\#1footins}-1pt\relax%
1618         \vskip \dimexpr-0.5\baselineskip-0.5\lineskip-0.5pt\relax%
1619         \unvbox\csuse{\#1footins}%
1620     }%
1621 %

```

End of the macro.

```

1622     }{}%
1623 }%
1624 %

```

And now, the same for familiar footnotes.

```

1625 \newcommand{\print@notesX@forpages}[1]{%
1626     \ifcsempty{onlysideX@\#1}{%
1627         \csuse{footstart\#1}{\#1}%
1628         \csuse{footgroup\#1}{\#1}%
1629     }%
1630     {%
1631         \ifboolexpr{%
1632             ((test {\ifcsstring{onlysideX@\#1}{L}} and not test{\ifnumodd{\c@page
1633             }})%
1634             or%
1635             (test {\ifcsstring{onlysideX@\#1}{R}} and test{\ifnumodd{\c@page}}))%
1636         }%
1637         \correct@footinsX@box{\#1}%
1638         \csuse{footstart\#1}{\#1}%
1639         \csuse{footgroup\#1}{\#1}%
1640         \global\count\csuse{footins\#1}=0%
1641         \global\skip\csuse{footins\#1}=0pt%
1642         \csuse{notefontsizeX@\#1}%
1643         \global\advance\dimen\csuse{footins\#1} by -\baselineskip%
1644         \global\boolfalse{keepforsideX@\#1}%
1645     }%
1646     {%
1647         \global\booltrue{keepforsideX@\#1}%
1648         \global\count\csuse{footins\#1}=\csuse{default@footins\#1}%
1649         \global\skip\csuse{footins\#1}=\csuse{beforenotesX@\#1}%
1650         \bgroup%
1651             \csuse{notefontsizeX@\#1}%
1652             \global\advance\dimen\csuse{footins\#1} by \baselineskip%
1653             \egroup%
1654     }%
1655 }%
1656 }%
1657 \newcommand{\correct@footinsX@box}[1]{%
1658     \ifbool{keepforsideX@\#1}{%

```

```

1659 \csuse{notefontsizeX@#1}%
1660 \splittopskip=0pt%
1661 \global\setbox\csuse{footins#1}=\vbox{%
1662   \vsplit\csuse{footins#1} to \dimexpr\ht\csuse{footins#1}-1pt\relax%
1663   \vskip \dimexpr-0.5\baselineskip-0.5\lineskip-0.5pt\relax%
1664   \unvbox\csuse{footins#1}%
1665 }%
1666 }%
1667 }%
1668 %

```

X Cross referencing

`\labelref@listR` Set up a new list, `\labelref@listR`, to hold the page, line and sub-line numbers for each label in right text.

```

1669 \list@create{\labelref@listR}
1670 %
1671 %

```

`\edlabel` This command is defined only one time in `reledmac`, including features for `reledpar`.

`\l@dmake@labelsR` This is the right text version of `\l@dmake@labels`, taking account of `\@Rlineflag`.

```

1672 \def\l@dmake@labelsR#1|#2|#3|#4|#5{%
1673   \expandafter\ifx\csname the@label\csuse{XR@prefix}#5\endcsname \relax%
1674   \else
1675     \led@warn@DuplicateLabel{\csuse{XR@prefix}#5}%
1676     \fi
1677   \expandafter\gdef\csname the@label\csuse{XR@prefix}#5\endcsname
1678   {#1|#2|#3|#4|\@Rlineflag}%
1679   \ignorespaces}
1680 \AtBeginDocument{%
1681   \def\l@dmake@labelsR#1|#2|#3|#4|#5{}%
1682 }
1683 %

```

`\@lab` The `\@lab` command, which appears in the `\linenum@out` file, appends the current values of page, line and sub-line to the `\labelref@list`. These values are defined by the earlier `\@page`, `\@nl`, and the `\sub@on` and `\sub@off` commands appearing in the `\linenum@out` file.

It is defined on `reledmac`.

XI Side notes

Regular \marginpars do not work inside numbered text — they do not produce any note but do put an extra unnumbered blank line into the text.

\sidenote@marginR Specifies which margin sidenotes can be in.

```

1683 \sidenotemargin*{%
1684   \l@dgtsidenote@margin{#1}%
1685   \global\sidenote@marginR=\@l@dttempcntb
1686   \global\sidenote@margin=\@l@dttempcntb
1687 }
1688 \newcount\sidenote@marginR
1689 \global\sidenote@margin=\@ne
1690 %
1691 %

```

\affixside@noteR The right text version of \affixside@note.

```

1692 \newcommand*{\affixside@noteR}{%
1693   \def\sidenotecontent@{}%
1694   \numgdef{\itemcount@}{0}%
1695   \def\do##1{%
1696     \ifnumequal{\itemcount@}{0}%
1697       {%
1698         \appto\sidenotecontent@{\#\#1}}% Not print not separator before
the 1st note
1699         {\appto\sidenotecontent@{\sidenotesep \#\#1}}%
1700       }%
1701     \numgdef{\itemcount@}{\itemcount@+1}%
1702   }%
1703   \dolistloop{\l@dcsnotetext}%
1704   \ifnumgreater{\itemcount@}{1}{\led@err@ManySidenotes}{}%
1705   \gdef@templ@d{}%
1706   \gdef@templ@n{\l@dcsnotetext\l@dcsnotetext\l\dcsnotetext@r}%
1707   \lfix@\templ@d\@templ@n \else%
1708     \if@twocolumn%
1709       \if@firstcolumn%
1710         \setl@dlp@rbox{\#\#1}{\sidenotecontent@}%
1711       \else%
1712         \setl@drp@rbox{\sidenotecontent@}%
1713       \fi%
1714     \else%
1715       \l@dttempcntb=\sidenote@marginR%
1716       \ifnum\l@dttempcntb>\@ne%
1717         \advance\l@dttempcntb by\page@numR%
1718       \fi%
1719       \ifodd\l@dttempcntb%
1720         \setl@drp@rbox{\sidenotecontent@}%
1721       \gdef\sidenotecontent@{}%

```

```

1722     \numdef{\itemcount}{0}%
1723     \dolistloop{\l@dcsnotetext@l}%
1724     \ifnumgreater{\itemcount}{1}{\led@err@ManyLeftnotes}{}%
1725     \setl@dlp@rbox{\ sidenotecontent@}%
1726   \else%
1727     \setl@dlp@rbox{\ sidenotecontent@}%
1728     \gdef\sidenotecontent@{}%
1729     \numdef{\itemcount}{0}%
1730     \dolistloop{\l@dcsnotetext@r}%
1731     \ifnumgreater{\itemcount}{1}{\led@err@ManyRightnotes}{}%
1732     \setl@drp@rbox{\ sidenotecontent@}%
1733   \fi%
1734   \fi%
1735   \fi%
1736 }
1737 %
1738 %

```

XII Familiar footnotes

`\l@dbfnote` `\l@dbfnote` adds the footnote to the insert list, and `\vl@dbfnote` calls the original `@footnotetext`. There are both defined in `reledmac`.

`\normalbfnoteX`

XIII Verse

Like in `reledmac`, the insertion of `hangingsymbol` is base on `\ifinserthangingsymbol`, and, for the right side, on `\ifinserthangingsymbolR`. Both commands also include the hanging space, to be sure the `\one@line` of hanging lines has the same width that the `\one@line` of normal lines and to prevent the column separator from shifting.

```

\inserthangingsymbolL39 \newif\ifinserthangingsymbolR
\inserthangingsymbolR40 \newcommand{\inserthangingsymbolL}{%
  \ifinserthangingsymbol%
    \ifinstanzaL%
      \hskip \c@ifundefined{sza@0@}{0}{\expandafter%
        \noexpand\csname sza@0@\endcsname\stanzaindentbase%
        \changingsymbol%
      }%
    \fi%
  \fi%
}
\inserthangingsymbolR{%
  \ifinserthangingsymbolR%
    \ifinstanzaR%
      \hskip \c@ifundefined{sza@0@}{0}{\expandafter%
        \noexpand\csname sza@0@\endcsname\stanzaindentbase%
      }%
    \fi%
}

```

```

1754     \@hangingsymbol%
1755     \fi%
1756     \fi%
1757 }%
1758 %

```

Before we can define the main stanza macros we need to be able to save and reset the category code for &. To save the current value we use \next from the \loop macro.

```

1759 \chardef\next=\catcode`\
1760 \catcode`&=\active
1761 %
1762 %

```

astanza This is roughly an environmental form of \stanza, which treats its stanza-like contents as a single chunk.

```

1763 \newenvironment{astanza}[1] [] {%
1764     \catcode`\&=\active
1765     \global\stanzacount\one\stanzamodulo\one
1766     \ifnum\useunamecount{sza00@}=\z@%
1767         \let\stanzahang\relax
1768         \let\endlock\relax
1769     \else
1770         \rightskip\z@ plus 1fil\relax
1771     \fi
1772     \ifnum\useunamecount{szp00@}=\z@%
1773         \let\sza@penalty\relax
1774     \fi
1775     \def&{%
1776         \endlock\mbox{}%
1777         \sza@penalty
1778         \global\advance\stanzacount\one
1779         \c@astanza@line}%
1780     \def\&{\c@stopastanza}%
1781     \pstart[#1]%
1782     \c@astanza@line
1783     \let\par\relax\ignorespaces%No paragraph in verses
1784 }{%
1785 %
1786 %

```

\c@stopastanza This command is called by \& in astanza environment. It allows optional arguments.

```

1787 \newcommandx{\c@stopastanza}[1][1,usedefault]{%
1788     \endlock\mbox{}%
1789     \pend[#1]%
1790 }%
1791 %

```

\@stanza@line This gets put at the start of each line in the environment. It sets up the paragraph style – each line is treated as a paragraph.

```

1792 \newcommand*{\@stanza@line}{%
1793   \ifnum\value{stanzaindentsrepetition}=0
1794     \parindent=\csname sza@\number\stanza@count
1795       @\endcsname\stanzaindentbase
1796   \else
1797     \parindent=\csname sza@\number\stanza@modulo
1798       @\endcsname\stanzaindentbase
1799     \managestanza@modulo
1800   \fi
1801   \endgraf
1802   \stanza@hang%
1803   \ignorespaces}
1804 %
1805 %

```

Lastly reset the modified category codes.

```

1806 \catcode`\&=\next
1807
1808 %

```

\thestanzaL And now, the left and right stanza counter.

```

\thestanzaR
1809 \newcounter{stanzaL}
1810 \newcounter{stanzaR}
1811 \renewcommand{\thestanzaL}{%
1812   \textbf{\arabic{stanzaL}}%
1813 }
1814 \renewcommand{\thestanzaR}{%
1815   \textbf{\arabic{stanzaR}}%
1816 }
1817 %
1818 %

```

XIV Naming macros

The L^AT_EX kernel provides \@namedef and \@namuse for defining and using macros that may have non-letters in their names. We need something similar here as we are going to need and use some numbered boxes and counters.

\newnamebox A set of macros for creating and using ‘named’ boxes; the macros are called after the regular box macros, but including the string ‘name’.

```

\setnamebox
\unhnamebox
1819 \providecommand*{\newnamebox}[1]{%
1820   \expandafter\newbox\csname #1\endcsname}
\unvnamebox
1821 \providecommand*{\setnamebox}[1]{%

```

```

1822 \expandafter\setbox\csname #1\endcsname}
1823 \providecommand*\{ \unhnamebox}[1]{%
1824 \expandafter\unhbox\csname #1\endcsname}
1825 \providecommand*\{ \unvnamebox}[1]{%
1826 \expandafter\unvbox\csname #1\endcsname}
1827 \providecommand*\{ \namebox}[1]{%
1828 \csname #1\endcsname}
1829 %
1830 %

```

`\newnamecount` Macros for creating and using ‘named’ counts.

`\usenamecount`

```

1831 \providecommand*\{ \newnamecount}[1]{%
1832 \expandafter\newcount\csname #1\endcsname}
1833 \providecommand*\{ \usenamecount}[1]{%
1834 \csname #1\endcsname}
1835 %
1836 %

```

XV Fixing babel and polyglossia

With parallel texts there is the possibility that the two sides might use different languages via `babel`. On the other hand, nor `babel` nor `polyglossia` might not be called at all (even though it might be already built into the format).

With the normal sequential text each line is initially typeset in the current language environment, and then it is output at which time its attachments are typeset (in the same language environment). In the parallel case lines are typeset in their current language but an attachment might be typeset outside the language environment of its line if the left and right side languages are different. To counter this, we have to make sure that the correct language is used at the proper times.

`\ifl@dusedbabel` A flag for checking if `babel` has been used as a package.

```

\l@dusedbabelfalse
\l@dusedbabeltrue
1837 \newif\ifl@dusedbabel
1838 %

```

`\l@dchecklang`

`\bbl@set@language` In `babel` the macro `\bbl@set@language{\<lang\>}` does the work when the language `\<lang\>` is changed via `\selectlanguage`. Unfortunately for us, if it is given an argument in the form of a control sequence it strips off the `\` character rather than expanding the command. We need a version that accepts an argument in the form `\lang` without it stripping the `\`.

```

1839 \patchcmd{\bbl@set@language}{%
1840   {\selectlanguage{\languagename}}}{%
1841   {\edef\languagename{\#1}\selectlanguage{\languagename}}}{%

```

```

1842   {}%
1843   {}%
1844 %
1845 %

```

The rest of the setup has to be postponed until the end of the preamble when we know if `babel` or `polyglossia` have been used or not. However, for now assume that it has not been used.

```

\selectlanguage \selectlanguage is a babel command. \theledlanguageL and \theledlanguageR
\l@duselanguage are the names of the languages of the left and right texts. \l@duselanguage is similar
\theledlanguageL to \selectlanguage.
\theledlanguageR
1846 \newcommand*\l@duselanguage{[1]{}
1847 \gdef\theledlanguageL{}
1848 \gdef\theledlanguageR{}
1849 %
1850 %

```

Now do the `babel` or `polyglossia` fix or, if necessary.

```

1851 \AtBeginDocument{%
1852   \@ifundefined{xp@main@language}{%
1853     \ifundefined{bb@main@language}{%
1854   %

```

Either `babel` has not been used or it has been used with no specified language.

```

1855 \l@dusedbabelfalse
1856 }%
1857 %

```

Here we deal with the case where `babel` has been used. `\selectlanguage` has to be redefined to use our version of `\bb@set@language` and to store the left or right language.

```

1858 \l@dusedbabeltrue
1859 \let\l@doldselectlanguage\selectlanguage
1860 \let\l@doldbb@set@language\bb@set@language
1861 \renewcommand{\selectlanguage}[1]{%
1862   \l@doldselectlanguage{#1}%
1863   \ifledRcol \gdef\theledlanguageR{#1}%
1864   \else     \gdef\theledlanguageL{#1}%
1865   \fi}
1866 %

```

`\l@duselanguage` simply calls the original `\selectlanguage` so that `\theledlanguageL` and `\theledlanguageR` are unaltered.

```

1867 \renewcommand*\l@duselanguage{[1]{%
1868   \expandafter\l@doldselectlanguage\expandafter{#1}}
1869 %

```

Lastly, initialise the left and right languages to the current babel one.

```

1870   \gdef\theledlanguageL{\bb@main@language}%
1871   \gdef\theledlanguageR{\bb@main@language}%
1872   }%
1873   }
1874 %

```

If use polyglossia

```

1875 { \let\old@otherlanguage\otherlanguage%
1876   \renewcommand{\otherlanguage}[2][]{%
1877     \selectlanguage[#1]{#2}%
1878     \ifledRcol \gdef\theledlanguageR{#2}%
1879     \else      \gdef\theledlanguageL{#2}%
1880     \fi}%
1881   \renewcommand{\l@duelanguage}[1]{%
1882     \csuse{no\language@name @numbers}\select@language{#1}%
1883   }%
1884   \gdef\theledlanguageL{\xpg@main@language}%
1885   \gdef\theledlanguageR{\xpg@main@language}%
1886 %

```

That is it.

```

1887 }%
1888 %

```

XVI Counts and boxes for parallel texts

In sequential text, each chunk (that enclosed by `\pstart ... \pend`) is put into a box called `\raw@text` and then immediately printed, resulting in the box being emptied and ready for the next chunk. For parallel processing multiple boxes are needed as printing is delayed. We also need extra counters for various things.

`\maxchunks` The maximum number of chunk pairs before printing has to be called for. The default is `\l@dc@maxchunks` 5120 chunk pairs.

```

1889 \newcount\l@dc@maxchunks
1890 \newcommand{\maxchunks}[1]{\l@dc@maxchunks=#1}
1891 \maxchunks{5120}
1892
1893 %

```

`\l@dnumpstartsL` The numbers of left and right chunks. `\l@dnumpstartsL` is defined in `eledmac`.

`\l@dnumpstartsR`

```

1894 \newcount\l@dnumpstartsR
1895
1896 %

```

\l@pscL A couple of scratch counts for use in left and right texts, respectively.

```

1897 \newcount\l@dpscL
1898 \newcount\l@dpscR
1899 %
1900 %

```

\l@dsetuprawboxes This macro creates \maxchunks pairs of boxes for left and right chunks. The boxes are called \l@dLcolrawbox1, \l@dLcolrawbox2, etc.

```

1901 \newcommand*\l@dsetuprawboxes{%
1902   \l@dtmpcntb=\l@dc@maxchunks
1903   \loop\ifnum\l@dtmpcntb>\z@
1904     \newnamebox{l@dLcolrawbox}{\the\l@dtmpcntb}
1905     \newnamebox{l@dRcolrawbox}{\the\l@dtmpcntb}
1906     \advance\l@dtmpcntb \m@ne
1907     \repeat}
1908 %
1909 %

```

\l@dsetupmaxlinecounts To be able to synchronise left and right texts we need to know the maximum number of text lines there are in each pair of chunks. \l@dsetupmaxlinecounts creates \maxchunks new counts called \l@dmaxlinesinpar1, etc., and \l@dzeromaxlinecounts zeroes all of them.

```

1910 \newcommand*\l@dsetupmaxlinecounts{%
1911   \l@dtmpcntb=\l@dc@maxchunks
1912   \loop\ifnum\l@dtmpcntb>\z@
1913     \newnamecount{l@dmaxlinesinpar}{\the\l@dtmpcntb}
1914     \advance\l@dtmpcntb \m@ne
1915     \repeat}
1916 \newcommand*\l@dzeromaxlinecounts{%
1917   \begingroup
1918   \l@dtmpcntb=\l@dc@maxchunks
1919   \loop\ifnum\l@dtmpcntb>\z@
1920     \global\usenamecount{l@dmaxlinesinpar}{\the\l@dtmpcntb}=\z@
1921     \advance\l@dtmpcntb \m@ne
1922     \repeat
1923   \endgroup}
1924 %
1925 %

```

Make sure that all these are set up. This has to be done after the user has had an opportunity to change \maxchunks.

```

1926 \AtBeginDocument{%
1927   \l@dsetuprawboxes
1928   \l@dsetupmaxlinecounts
1929   \l@dzeromaxlinecounts
1930   \l@dnumpstartsL=\z@

```

```

1931   \l@dnumpstartsR=\z@
1932   \l@dpscL=\z@
1933   \l@dpscR=\z@}
1934
1935 %

```

XVII Checking text to be processed

```

\if@pstarts \check@pstarts returns \pstartstrue if there are any unprocessed chunks.
\pstartstrue
\@pstartsfalse
\@pstartsfalse
\check@pstarts
\@pstartsfalse
\ifnum\l@dnumpstartsL>\l@dpscL
\pstartstrue
\else
\ifnum\l@dnumpstartsR>\l@dpscR
\pstartstrue
\fi
\fi
}

\%

```

\ifaraw@text \checkraw@text checks whether the current Left or Right box is void or not. If one or other is not void it sets \araw@texttrue, otherwise both are void and it sets \araw@textfalse.

```

\checkraw@text
\newif\ifaraw@text
\newcommand*\{\checkraw@text}{%
\araw@textfalse
\ifvbox\namebox{\l@dLcolrawbox\the\l@dpscL}
\araw@texttrue
\else
\ifvbox\namebox{\l@dRcolrawbox\the\l@dpscR}
\araw@texttrue
\fi
\fi
}

\%

```

\@writelnlinesinparL These write the number of text lines in a chunk to the section files, and then afterwards zero the counter.

```

\newcommand*\{\@writelnlinesinparL}{%
\edef\next{%
\write\linenum@out{\string\pend[\the\@donereallinesL]}}%
\next

```

```

1966     \global\@donereallinesL \z@%
1967 \newcommand*{\@writelnlinesinparR}{%
1968     \edef\next{%
1969         \write\linenum@outR{\string\@pendR[\the\@donereallinesR]}%
1970     \next
1971     \global\@donereallinesR \z@%
1972 %
1973 %

```

\@writepageofparL These write the pages where start the first line of a chunk.

\@writepageofparR

```

1974 \newcommand*{\@writepageofparL}[0]{%
1975     \ifnum\@donereallinesL=\z@%
1976         \edef\next{%
1977             \write\linenum@out{\string\@pstart{\the\l@dpscL}{\the\c@page}{\the\
1978             numpagelinesL}}%
1979         }%
1980         \next%
1981     \fi%
1982 }%
1983 \newcommand*{\@writepageofparR}[0]{%
1984     \ifnum\@donereallinesR=\z@%
1985         \edef\next{%
1986             \write\linenum@outR{\string\@pstartR{\the\l@dpscR}{\the\c@page}{\the\
1987             numpagelinesR}}%
1988         }%
1989     \fi%
1990 }%

```

XVIII Parallel columns

\@eledsectionL The parbox \@eledsectionL and \@eledsectionR will keep the sections' title.

\@eledsectionR

```

1991 \newsavebox{\@eledsectionL}%
1992 \newsavebox{\@eledsectionR}%
1993 %

```

\Columns The \Columns command results in the previous Left and Right texts being typeset in matching columns. There should be equal numbers of chunks in the left and right texts.

```

1994 \newcommand*{\Columns}{%
1995     \ifl@dpairing%
1996         \led@err@Columns@InsideEnv%
1997     \fi%
1998     \expandafter\ifvoid\csname l@dRcolrawbox1\endcsname%
1999         \led@err@Columns@WithoutEnv%
2000     \else%

```

```

2001 \global\l@dprintingcolumnstrue%
2002 \eledsection@correcting@skip=-\baselineskip% Correction for sections' titles
2003 \ifnum\l@dnumpstartsL=\l@dnumpstartsR\else
2004     \led@err@BadLeftRightPstarts{\the\l@dnumpstartsL}{\the\l@dnumpstartsR}%
2005 \fi
2006 %

```

Start a group and zero counters, etc.

```

2007 \begin{group}
2008     \l@dzeropenalties
2009     \endgraf\global\num@lines=\prevgraf
2010         \global\num@linesR=\prevgraf
2011     \global\par@line=\z@
2012     \global\par@lineR=\z@
2013     \global\l@dpscL=\z@
2014     \global\l@dpscR=\z@
2015     \get@familiarfootnote@number%
2016 %

```

Check if there are chunks to be processed, and process them two by two (left and right pairs).

```

2017 \check@pstarts
2018 \loop\if@pstarts
2019     \global\pstartnumtrue
2020     \global\pstartnumRtrue
2021 %

```

Increment `\l@dpscL` and `\l@dpscR` which here count the numbers of left and right chunks. Also restore the value of the public pstart counters.

```

2022 \global\advance\l@dpscL \one
2023 \global\advance\l@dpscR \one
2024 \restore@pstartL@pc%
2025 \restore@pstartR@pc%
2026 %

```

We print the optional argument of `\pstart` or the argument of `\AtEveryPstart`.

```

2027 \Columns@print@before@pstart%
2028 %

```

Check if there is text yet to be processed in at least one of the two current chunks, and also whether the left and right languages are the same

```

2029 \checkraw@text
2030 {
2031     \loop\ifaraw@text

```

Grab the next pair of left and right text lines and output them, swapping languages if they differ, adding section title if needed.

```

2032 \l@duselanguage{\theledlanguageL}%
2033 \do@lineL
2034 \xifinlist{\the\l@dpscL}{\eled@sections@@}
2035 {%
2036   \ifdefstring{\@eledsectmark}{L}%
2037     {\csuse{eled@sectmark@\the\l@dpscL}%
2038      }{}%
2039   \global\csundef{eled@sectmark@\the\l@dpscL}%
2040   \savebox{@eledsectionL}{\parbox[t][][t]{\Lcolwidth}{\vbox
2041     {}{\print@eledsectionL}}}\vbox{}-> prevent alignment troubles with RTL
2042   language
2043   }%
2044   {}%
2045 \l@duselanguage{\theledlanguageR}%
2046 \do@lineR
2047 \xifinlist{\the\l@dpscR}{\eled@sectionsR@@}
2048 {%
2049   \ifdefstring{\@eledsectmark}{R}%
2050     {\csuse{eled@sectmark@\the\l@dpscR R}%
2051      }{}%
2052   \global\csundef{eled@sectmark@\the\l@dpscR R}%
2053   \savebox{@eledsectionR}{\parbox[t][][t]{\Rcolwidth}{\vbox
2054     {}{\print@eledsectionR}}}\vbox{}-> prevent alignment troubles with RTL
2055   language
2056   }%
2057 \hb@xt@ \hsize{%
2058   \ifdefstring{\columns@position}{L}{}{\hfill }%
2059   \unhbox\l@leftbox%
2060   \ifhbox{@eledsectionL}%
2061     \usebox{@eledsectionL}%
2062   \fi%
2063   \print@columnseparator%
2064   \unhbox\l@rightbox%
2065   \ifhbox{@eledsectionR}%
2066     \usebox{@eledsectionR}%
2067   \fi%
2068   \ifdefstring{\columns@position}{R}{}{\hfill}%
2069   }%
2070 \checkraw@text
2071 \checkverseL
2072 \checkverseR
2073 \checkpb@columns
2074 \repeat%
2075 %

```

Having completed a pair of chunks, write the number of lines in each chunk to the respective section files. Increment pstart counters and reset line numbering if it is by pstart.

```

2072   \writelinesinparL
2073   \writelinesinparR

```

```

2074   \check@pstarts
2075     \ifbypstart@%
2076       \write\linenum@out{\string\@set[1]}
2077       \resetprevline@
2078     \fi
2079   \ifbypstart@R
2080     \write\linenum@outR{\string\@set[1]}
2081     \resetprevline@
2082   \fi
2083   \Columns@print@after@pend%
2084   \repeat
2085 %

```

Having output all chunks, make sure all notes have been output, then zero counts ready for the next set of texts. The boolean tests for stanza are switched to false.

```

2086   \flush@notes
2087   \flush@notesR
2088 \endgroup
2089 %

2090 \global\l@dpstL=\z@
2091 \global\l@dpstR=\z@
2092 \global\l@dnumpstartsL=\z@
2093 \global\l@dnumpstartsR=\z@
2094 \global\l@dprintingcolumnsfalse%
2095 \ignorespaces
2096   \global\instanzaFfalse%
2097   \global\instanzaRfalse%
2098 \fi}
2099
2100 %

```

`\print@columnseparator` `\print@columnseparator` prints the column separator, with surrounding spaces (as the user has set them). We use the `\ifdim` instead of `etoolbox` to avoid having `\hfill` in a {}, which deletes some space (but not much).

```

2101 \def\print@columnseparator{%
2102   \ifdim\beforecolumnseparator<0pt%
2103     \hfill%
2104   \else%
2105     \hspace{\beforecolumnseparator}%
2106   \fi%
2107   \columnseparator%
2108   \ifdim\aftercolumnseparator<0pt%
2109     \hfill%
2110   \else%
2111     \hspace{\beforecolumnseparator}%
2112   \fi%
2113 }%
2114 %

```

\checkpb@columns \checkpb@columns prevent or make pagebreaking in columns, depending of the use of \ledpb or \lednspb.

```

2115 \newcommand{\checkpb@columns}{%
2116   \newif\if@pb
2117   \newif\if@nopb
2118   \IfStrEq{\led@pb@setting}{before}{%
2119     \numdef{\next@absline}{\the\absline@num+1}%
2120     \numdef{\next@abslineR}{\the\absline@numR+1}%
2121     \xifinlistcs{\next@absline}{l@prev@pb}{\@pbtrue}{}
2122     \xifinlistcs{\next@abslineR}{l@prev@pbR}{\@pbtrue}{}
2123     \xifinlistcs{\next@absline}{l@prev@nopb}{\@nopbtrue}{}
2124     \xifinlistcs{\next@abslineR}{l@prev@nopbR}{\@nopbtrue}{}
2125   }{%
2126   }
2127   \IfStrEq{\led@pb@setting}{after}{%
2128     \xifinlistcs{\the\absline@num}{l@prev@pb}{\@pbtrue}{}
2129     \xifinlistcs{\the\absline@numR}{l@prev@pbR}{\@pbtrue}{}
2130     \xifinlistcs{\the\absline@num}{l@prev@nopb}{\@nopbtrue}{}
2131     \xifinlistcs{\the\absline@numR}{l@prev@nopbR}{\@nopbtrue}{}
2132   }{%
2133   }
2134 \if@nopb\nopagebreak[4]\enlargethispage{\baselineskip}\fi
2135 \if@pb\pagebreak[4]\fi
2136 }
2137 %

```

\columnseparator The separator between line pairs in parallel columns is in the form of a vertical rule extending a little below the baseline and with a height slightly greater than the \baselineskip. The width of the rule is \columnrulewidth (initially 0pt so the rule is invisible).

```

2137 \newcommand*\columnseparator{%
2138   \smash{\rule[-0.2\baselineskip]{\columnrulewidth}{1.05\baselineskip}}%
2139   \newdimen\columnrulewidth
2140   \columnrulewidth=\z@
2141
2142 %

```

\columnsposition The position of the \Columns in a page. Default value is R. Stored in \columns@position.

```

2143 \newcommand*\columnsposition[1]{%
2144   \xdef\columns@position{\#1}%
2145   }%
2146 \xdef\columns@position{R}%
2147 %

```

\beforecolumnseparator \beforecolumnseparator and \aftercolumnseparator lengths are defined to -1pt.
\aftercolumnseparator If user changes them to a positive length, the lengths are used to define blank spaces before / after the column separator, instead of \hfill.

```

2148 \newlength{\beforecolumnseparator}%
2149 \setlength{\beforecolumnseparator}{-2pt}%
2150
2151 \newlength{\aftercolumnseparator}%
2152 \setlength{\aftercolumnseparator}{-2pt}%
2153
2154 %

```

`setwidthliketwocolumns@L` The `\setwidth...` macros are called in `\begin{numbering}` in a **non-parallel** typesetting context, to fix the width of the lines to be vertically aligned with parallel columns. They are also called at the beginning of a note's group, if some options are enabled. The `\setposition...` macros are called in `\begin{numbering}` in a **non-parallel** typesetting context to fix the position of the lines. The `\setnoteposition...` macros are called in `\xxxfootstart` in a **non-parallel** typesetting context to fix the position of notes block.

`setwidthliketwocolumns@C`

`setpositionliketwocolumns@C`

`setnotepositionliketwocolumns@C`

`setwidthliketwocolumns@R`

`setpositionliketwocolumns@R`

`setnotepositionliketwocolumns@R`

`setwidthliketwocolumns@R`

`setpositionliketwocolumns@R`

`setnotepositionliketwocolumns@R`

```

2155 \newcommand{\setwidthliketwocolumns@L}{%
2156 % Temporary dimension, initially equal to the standard hsize, i.e. text
2157 % width
2158 % \begin{macrocode}
2159 % \newdimen\temp%
2160 % \temp=\hsize%

```

Hsize : Left + Right width

```

2161 \hsize=\Lcolwidth%
2162 \advance\hsize\Rcolwidth%
2163 %

```

Now, calculating the remaining space

```

2164 \advance\temp-\hsize%
2165 %

```

And multiply the hsize by 2/3 of this space

```

2166 \multiply\temp by 2%
2167 \divide\temp by 3%
2168 \advance\hsize\temp%
2169 }%
2170
2171 \newcommand{\setpositionliketwocolumns@L}{%
2172 % \renewcommand{\ledrlfill}{\hfill}%
2173 }%
2174
2175 \newcommand{\setnotespositionliketwocolumns@L}{%
2176 }%
2177
2178
2179 %

```

```

2180 \newcommand{\setwidthliketwocolumns@C}{%
2181 % Temporary dimension, initially equal to the standard hsize, i.e. text
2182 % width
2183 \newdimen\temp%
2184 \temp=\hsize%
2185 % Hsize : Left + Right width
2186 %

2187 \hsize=\Lcolwidth%
2188 \advance\hsize\Rcolwidth%
2189 % Now, calculating the remaining space
2190 %

2191 \advance\temp-\hsize%
2192 %

```

And multiply the hsize by 1/2 of this space

```

2193 \divide\temp by 2%
2194 \advance\hsize\temp%
2195 }%

2196
2197 \newcommand{\setpositionliketwocolumns@C}{%
2198 \doinsidelinehook{\hfill}%
2199 \renewcommand{\ledrlfill}{\hfill}%
2200 }%

2201
2202 \newcommand{\setnotespositionliketwocolumns@C}{%
2203 \newdimen\temp%
2204 \newdimen\tempa%
2205 \temp=\hsize%
2206 \tempa=\Lcolwidth%
2207 \advance\tempa\Rcolwidth%
2208 \advance\temp-\tempa%
2209 \divide\temp by 2%
2210 \leftskip=\temp%
2211 \rightskip=-\temp%
2212 }%

2213
2214 \newcommand{\setwidthliketwocolumns@R}{%
2215 %

```

Temporary dimension, initially equal to the standard hsize, i.e. text width

```

2216 \newdimen\temp%
2217 \temp=\hsize%
2218 %

```

Hsize : Left + Right width

```

2219   \hsize=\Lcolwidth%
2220   \advance\hsize\Rcolwidth%
2221 %

```

Now, calculating the remaining space

```

2222   \advance\temp-\hsize%
2223 %

```

And multiply the hsize by 2/3 of this space

```

2224   \multiply\temp by 2%
2225   \divide\temp by 3%
2226   \advance\hsize\temp%
2227 }%
2228
2229 \newcommand{\setpositionliketwocolumns@R}{%
2230   \doinsidelinehook{\hfill}%
2231 }%
2232
2233 \newcommand{\setnotespositionliketwocolumns@R}{%
2234   \newdimen\temp%
2235   \newdimen\tempa%
2236   \temp=\hsize%
2237   \tempa=\Lcolwidth%
2238   \advance\tempa\Rcolwidth%
2239   \advance\temp-\tempa%
2240   \divide\temp by 2%
2241   \leftskip=\temp%
2242   \rightskip=-\temp%
2243 }%
2244
2245 %

```

\Columns@print@before@pstart
 \Columns@print@after@pend

The \Columns@print@before@pstart and \Columns@print@after@pend print the content of the optional argument of \pstart / \pend. If this content is not empty, it also print the separator.

```

2246 \newcommand{\Columns@print@before@pstart}{%
2247   \ifboolexpr{%
2248     test{\ifcsstring{before@pstartL@\the\l@dpscL}{\at@every@pstart}}%
2249     and test {\ifcsstring{before@pstartR@\the\l@dpscR}{\at@every@pstart}}%
2250     and test {\ifdefempty{\at@every@pstart}}}}%
2251   {}%
2252   {}%
2253   \hb@xt@ \hsize{%
2254     \ifdefstring{\columns@position}{L}{}{\hfill }%
2255     \par\parbox[t][][t]{\Lcolwidth}{%
2256       \csuse{before@pstartL@\the\l@dpscL}%
2257     }%
2258     \print@columnseparator%
2259     \parbox[t][][t]{\Rcolwidth}{%

```

```

2260           \set@sectcountR%
2261           \csuse{before@pstartR@\the\l@dpscR}%
2262       }%
2263       \ifdefstring{\columns@position}{R}{}{\hfill}%
2264   }%
2265 }%
2266 \global\csundef{before@pstartL@\the\l@dpscL}%
2267 \global\csundef{before@pstartR@\the\l@dpscR}%
2268 }%
2269 \newcommand{\Columns@print@after@pend}%
2270   \ifboolexpr{%
2271     test{\ifcsstring{after@pendL@\the\l@dpscL}{\at@every@pend}}%
2272     and test {\ifcsstring{after@pendR@\the\l@dpscR}{\at@every@pend}}%
2273     and test {\ifdefempty{\at@every@pend}}}%
2274   }%
2275 }%
2276   \hb@xt@ \hsize{%
2277     \ifdefstring{\columns@position}{L}{}{\hfill }%
2278     \parbox[t][][t]{\Lcolwidth}{%
2279       \csuse{after@pendL@\the\l@dpscL}%
2280     }%
2281     \print@columnseparator%
2282     \parbox[t][][t]{\Rcolwidth}{%
2283       \set@sectcountR%
2284       \csuse{after@pendR@\the\l@dpscR}%
2285     }%
2286     \ifdefstring{\columns@position}{R}{}{\hfill}%
2287   }%
2288 }%
2289 \global\csundef{after@pendL@\the\l@dpscL}%
2290 \global\csundef{after@pendR@\the\l@dpscR}%
2291 }%
2292 %

```

XIX Parallel pages

This is considerably more complicated than parallel columns.

XIX.1 Specific counters

`\numpagelinesL` Counts for the number of lines on a left or right page, and the smaller of the number of
`\numpagelinesR` lines on a pair of facing pages.

```

2293 \newcount\numpagelinesL
2294 \newcount\numpagelinesR
2295 \newcount\l@dminpagelines
2296
2297 %

```

XIX.2 Main macro

- \Pages The \Pages command results in the previous Left and Right texts being typeset on matching facing pages. There should be equal numbers of chunks in the left and right texts.

```

2298 \newcommandx*\{\Pages\}[1][1,usedefault]{%
2299   \ifl@dpairing%
2300     \led@err@Pages@InsideEnv%
2301   \fi%
2302   \expandafter\ifvoid\csname l@dRcolrawbox1\endcsname%
2303     \led@err@Pages@WithoutEnv%
2304   \else%
2305   \ifstrequal{#1}{mainmatter}{\Pages@mainmattertrue}{\Pages@mainmatterfalse}%
2306   }%
2307   \eledsection@correcting@skip=-2\baselineskip% line correcting for section
2308   titles.
2309   \parledgroup@notespacing@set@correction%
2310   \typeout{}%
2311   \typeout{***** PAGES *****}%
2312   \ifnum\l@dnumpstartsL=\l@dnumpstartsR\else%
2313     \led@err@BadLeftRightPstarts{\the\l@dnumpstartsL}{\the\l@dnumpstartsR}%
2314   \fi%
2315 %

```

Get onto an empty even (left) page, then initialise counters, etc.

```

2314 \cleartol@devenpage%
2315 \global\l@dpriintingpagestrue%
2316 \begingroup%
2317 %

```

As \Pages must be called outside of the pages environment, we have to redefine the \Lcolwidth and \Rcolwidth lengths, to prevent false overfull hboxes.

```

2318 \setlength{\Lcolwidth}{\textwidth}%
2319 \setlength{\Rcolwidth}{\textwidth}%
2320 %

2321 \l@dzopenalties%
2322 \endgraf\global\num@lines=\prevgraf%
2323 \global\num@linesR=\prevgraf%
2324 \global\par@line=\z@%
2325 \global\par@lineR=\z@%
2326 \global\l@dpscL=\z@%
2327 \global\l@dpscR=\z@%
2328 \writtenlinesLfalse%
2329 \writtenlinesRfalse%
2330 \get@familiarfootnote@number%
2331 %

```

The footnotes are printed in a different way from expected in `reledmac`, as we may want to print the notes on one side only.

```

2332   \let\print@Xnotes\print@Xnotes@forpages%
2333   \let\print@notesX\print@notesX@forpages%
2334 %

```

Check if there are chunks to be processed.

```

2335   \check@pstarts%
2336   \loop\if@pstarts%
2337 %

```

Loop over the number of chunks, incrementing the chunk counts ($\l@dpscL$ and $\l@dpscR$ are chunk (box) counts.)

```

2338   \global\advance\l@dpscL \@ne%
2339   \global\advance\l@dpscR \@ne%
2340 %

```

Calculate the maximum number of real text lines in the chunk pair, storing the result in the relevant $\l@dmaxlinesinpar$.

```

2341   \getlinesfromparlistL%
2342   \getlinesfromparlistR%
2343   \l@dcalc@maxoftwo{\@cs@linesinparL}{\@cs@linesinparR}%
2344   {\usenamecount{\l@dmaxlinesinpar}{\the\l@dpscL}}%
2345   \check@pstarts%
2346   \repeat%
2347 %

```

Zero the counts again, ready for the next bit.

```

2348   \global\l@dpscL=\z@%
2349   \global\l@dpscR=\z@%
2350 %

```

Get the number of lines on the first pair of pages and store the minimum in $\l@dminpagelines$.

```

2351   \getlinesfrompagelistL%
2352   \getlinesfrompagelistR%
2353   \l@dcalc@minoftwo{\@cs@linesonpageL}{\@cs@linesonpageR}%
2354   {\l@dminpagelines}%
2355 %

```

Now we start processing the left and right chunks ($\l@dpscL$ and $\l@dpscR$ count the left and right chunks), starting with the first pair.

```

2356   \check@pstarts%
2357   \if@pstarts%
2358 %

```

Increment the chunk counts to get the first pair. Restore also the value of public pstart counters.

```

2359   \global\advance\l@dpscL \@ne%
2360   \global\advance\l@dpscR \@ne%
2361   \restore@pstartL@pc%
2362   \restore@pstartR@pc%
2363 %

```

We have not processed any lines from these chunks yet, so zero the respective line counts.

```

2364     \global\@donereallinesL=\z@%
2365     \global\@donetotallinesL=\z@%
2366     \global\@donereallinesR=\z@%
2367     \global\@donetotallinesR=\z@%
2368 %

```

Start a loop over the boxes (chunks).

```

2369     \checkraw@text%
2370 %

2371 %     \begingroup
2372 {      \loop\ifaraw@text%
2373 %

```

See if there is more that can be done for the left page and set up the left language.

```

2374     \checkpageL%
2375     \l@duselanguage{\theledlanguageL}%
2376 {
2377 %

```

Process the next (left) text line, adding it to the page. Eventually, adds the optional argument of pstart.

```

2378     \ifdefstring{\@eledsectnotoc}{L}{\ledsectnotoc}{}%
2379     \csuse{before@pstartL@\the\l@dpscL}%
2380     \global\csundef{before@pstartL@\the\l@dpscL}%
2381     \do@lineL%
2382     \xifinlist{\the\l@dpscL}{\eled@sections@@}%
2383     {\print@eledsectionL}%
2384     {}%
2385     \advance\numpagelinesL \cne%
2386 %

```

When using shiftedpstarts option, a \l@dleftbox with a null height is not printed. That means we do not insert blank lines at the end of a left chunk lower than the corresponding right chunk. However, a \l@dleftbox with a null height will advance the \pagetotal in any case. Because if we do not do this, the \checkpageL could let \ifl@pagefull to false, and consequently a \clopL equal to 1000 could be written in the numbered file, even if all the lines actually needed for the current page have been printed. \l@dleftbox

```

2387     \ifshiftedpstarts%
2388     \ifdim\ht\l@dleftbox>0pt%
2389     \parledgroup@correction@notespacing{L}%
2390     \hb@xt@ \hsize{\ledstrutL\unhbox\l@dleftbox}%
2391     \else%
2392     \unless\ifadvancedshiftedpstarts%
2393     \dimen0=\pagetotal%

```

```

2394           \advance\dimen0 by \baselineskip%
2395           \global\pagetotal=\dimen0%
2396 \else%
2397   \ifnomaxlines%
2398     \numdef{\@tmp}{\the\l@dpscL+1}%
2399     \ifcsdef{minpage@pstart@{\@tmp}}{%
2400       \ifnumless{\the\c@page}{\csuse{%
2401         minpage@pstart@{\@tmp}}}%
2402       {\dimen0=\pagetotal}%
2403       \advance\dimen0 by \baselineskip%
2404       \global\pagetotal=\dimen0%
2405     }%
2406     {}%
2407   }{}%
2408   \fi%
2409   \fi%
2410 \else%
2411   \parledgroup@correction@notespacing{L}%
2412   \hb@xt@ \hsize{\ledstrutL\unhbox\l@leftbox}%
2413 \fi%
2414 %

```

Perhaps we have to move to the next (left) box. Check if we have got all we can onto the page. If not, repeat for the next line. Check if we have to print the optional argument of the last pend. Check if the page is full. Check if the verse is split in two subsequent pages. Check there is any forced page breaks. Reset the verse skipnumber boolean

```

2415   \get@nextboxL%
2416   \global\l@dskipversenumberfalse%
2417   \ifprint@last@after@pendL%
2418     \csuse{after@pendL@\the\l@dpscL}%
2419     \global\csundef{after@pendL@\the\l@dpscL}%
2420   \fi%
2421   \checkpageL%
2422   \checkverseL%
2423   \checkpbL%
2424   \repeat%
2425 %

```

That (left) page has been filled. Output the number of real lines on the page — if the page break is because the page has been filled with lines, use the actual number, otherwise the page has been ended early in order to synchronise with the facing page so use an impossibly large number.

```

2426   \ifl@dpagefull%
2427     \@writelnesongpageL{\the\numpagelinesL}%
2428   \else%
2429     \@writelnesongpageL{1000}%
2430   \fi%
2431 %

```

Reset to zero the left-page line count, clear the page to get onto the facing (odd, right) page, and reinitialize the accumulated dimension of interline correction for notes in parallel ledgroup.

```

2432      \numpagelinesL \z@%
2433      \parledgroup@correction@notespacing@init%
2434      \clearl@leftpage }%
2435 %

```

Now do the same for the right text.

```

2436      \checkpageR%
2437      \l@duselanguage{\theledlanguageR}%
2438  {
2439      \loop\ifl@dsamepage%
2440      \set@sectcountR%
2441      \ifdefstring{@eledsectnotoc}{R}{\ledsectnotoc}{}
2442      \csuse{before@pstartR@\the\l@dpscR}%
2443      \global\csundef{before@pstartR@\the\l@dpscR}%
2444      \do@lineR%
2445      \xifinlist{\the\l@dpscR}{\eled@sectionsR@@}%
2446      {\print@eledsectionR}%
2447      {}%
2448      \advance\numpagelinesR \one%
2449      \ifshiftedpstarts%
2450      \ifdim\ht\l@rightbox>0pt%
2451      \parledgroup@correction@notespacing{R}%
2452      \hb@xt@ \hsize{\ledstrutR\unhbox\l@rightbox}%
2453      \else%
2454      \unless\ifadvancedshiftedpstarts%
2455      \dimen0=\pagetotal%
2456      \advance\dimen0 by \baselineskip%
2457      \global\pagetotal=\dimen0%
2458      \else%
2459      \ifnomaxlines%
2460      \numdef{@tmp}{\the\l@dpscR+1}%
2461      \ifcsdef{minpage@pstart@{\@tmp}}{%
2462      \ifnumless{\the\c@page}{\csuse{%
2463      minpage@pstart@{\@tmp}}}{%
2464      \dimen0=\pagetotal%
2465      \advance\dimen0 by \baselineskip%
2466      \global\pagetotal=\dimen0%
2467      }{}%
2468      \fi%
2469      \fi%
2470      \else%
2471      \parledgroup@correction@notespacing{R}%
2472      \hb@xt@ \hsize{\ledstrutR\unhbox\l@rightbox}%
2473      \fi%

```

```

2475      \get@nextboxR%
2476      \global\l@dskipversenumberRfalse%
2477      \ifprint@last@after@pendR%
2478          \csuse{after@pendR@\the\l@dpscR}%
2479          \global\csundef{after@pendR@\the\l@dpscR}%
2480      \fi%
2481      \checkpageR%
2482      \checkverseR%
2483      \checkpbR%
2484      \repeat%
2485      \ifl@dpagefull%
2486          \@writelinesonpageR{\the\numpagelinesR}%
2487      \else%
2488          \@writelinesonpageR{1000}%
2489      \fi%
2490      \numpagelinesR=\z@%
2491      \parledgroup@correction@notespacing@init%
2492 %

```

The page is full, so move onto the next (left, odd) page and repeat left text processing.

```

2493      \clearl@drighthpage}%
2494 %

```

More to do? If there is we have to get the number of lines for the next pair of pages before starting to output them.

```

2495      \checkraw@text%
2496      \ifaraw@text%
2497          \getlinesfrompagelistL%
2498          \getlinesfrompagelistR%
2499          \l@dcalc@minoftwo{\@cs@linesonpageL}{\@cs@linesonpageR}%
2500          {\l@dminpagelines}%
2501      \fi%
2502      \repeat}%
2503 %

```

We have now output the text from all the chunks.

```

2504      \fi%
2505 %

```

Make sure that there are no inserts hanging around.

```

2506      \flush@notes%
2507      \flush@notesR%
2508      \endgroup%
2509 %

```

Zero counts ready for the next set of left/right text chunks. The boolean tests for stanza are switched to false.

```

2510      \global\l@dpscL=\z@%
2511      \global\l@dpscR=\z@%

```

```

2512 \global\l@dnumpstartsL=\z@%
2513 \global\l@dnumpstartsR=\z@%
2514   \global\instanzaLfalse%
2515   \global\instanzaRfalse%
2516 \global\l@dprintingpagesfalse%
2517 \finish@Pages@notes%Needed to prevent final notes overlap line number
2518 \ignorespaces\fi}
2519
2520
2521 %

```

XIX.3 Ensure all notes be printed at the end of parallel pages

\finish@Pages@notes This macro ensures that all long notes are printed at the end of \Pages typesetting, and that there is no more long notes left for the next pages.

```

2522 \newcommand{\finish@Pages@notes}{%
2523   \def\do##1{%
2524 %

```

First, declare footnote box if there was no previous declared. E.g. if familiar or critical notes were disabled by reledmac's options.

```

2525 \ifnocritical@%
2526   \global\newnamebox{##1footins}
2527 \fi
2528 \ifnofamiliar@%
2529   \global\newnamebox{footins##1}
2530 \fi
2531 %

```

And now, add a \newpage if there is no more footnote to print.

```

2532 \ifvoid\csuse{##1footins}%
2533   \ifvoid\csuse{footins##1}\else%
2534     \newpage\null%
2535     \listbreak%
2536   \fi%
2537 \else%
2538   \newpage\null%
2539   \listbreak%
2540 \fi%
2541 }%
2542 \dolistloop{\@series}%
2543 }%
2544 %

```

XIX.4 Struts

\ledstrutL Struts inserted into leftand right text lines.
\ledstrutR

```

2545 \newcommand*{\ledstrutL}{}%
2546 \newcommand*{\ledstrutR}{}%
2547 %
2548 %

```

XIX.5 Page clearing

`\cleartoevenpage` `\cleartoevenpage`, which is defined in the memoir class, is like `\clear(double)page` except that we end up on an even page. `\cleartol@devenpage` is similar except that it first checks to see if it is already on an empty page.

```

2549 \providetcommand{\cleartoevenpage}[1][\@empty]{%
2550   \clearpage
2551   \ifodd\c@page\hbox{}#1\clearpage\fi}
2552 %
2553 \newcommand*{\cleartol@devenpage}{%
2554   \ifdim\pagetotal<\topskip% on an empty page
2555   \else
2556     \clearpage
2557     \Pages@mainmatter%
2558   \fi
2559   \ifodd\c@page%
2560     \ifprevpgnotnumbered%
2561       \addtocounter{par@page}{-1}%
2562       \ifdef{\prevpgstyle}{\thispagestyle{\prevpgstyle}}{}%
2563     \fi%
2564     \hbox{}\clearpage%
2565   \fi%
2566 }%
2567 %

```

`\clearl@leftpage` `\clearl@leftpage` and `\clearl@rightpage` get us onto an odd and even page, respectively, checking that we end up on the subsequent page. Both commands use `\newpage` and not `\clearpage`. Because `\clearpage` prints all footnotes before the next page, even if it has to add new empty pages, while `\newpage` does not. And as we want notes started in the left page continue in the right page and *vice-versa*, we must use `\newpage` and not `\clearpage`

```

2568 \newcommand*{\clearl@leftpage}{%
2569   \ifdim\pagetotal=0pt\hbox{}\fi%
2570   \newpage%
2571   \ifodd\c@page\else
2572     \led@err@LeftOnRightPage
2573     \hbox{}%
2574     \cleardoublepage
2575   \fi}
2576 %
2577 \newcommand*{\clearl@rightpage}{%
2578   \ifdim\pagetotal=0pt\hbox{}\fi%

```

```

2579 \newpage%
2580 \ifodd\c@page
2581   \led@err@RightOnLeftPage
2582   \hbox{}%
2583   \cleartoevenpage
2584 \fi}
2585 %
2586 %

```

XIX.6 Lines managing

\getlinesfromparlistL \getlinesfromparlistL gets the next entry from the \linesinpar@listL and puts it into \cs@linesinparL; if the list is empty, it sets \cs@linesinparL to 0. Similarly for \getlinesfromparlistR.

```

@cs@linesinparR
2587 \newcommand*{\getlinesfromparlistL}{%
2588   \ifx\linesinpar@listL\empty
2589     \gdef\@cs@linesinparL{0}%
2590   \else
2591     \gl@p\linesinpar@listL\to\@cs@linesinparL
2592   \fi}
2593 \newcommand*{\getlinesfromparlistR}{%
2594   \ifx\linesinpar@listR\empty
2595     \gdef\@cs@linesinparR{0}%
2596   \else
2597     \gl@p\linesinpar@listR\to\@cs@linesinparR
2598   \fi}
2599 %
2600 %

```

\getlinesfrompagelistL \getlinesfrompagelistL gets the next entry from the \linesonpage@listL and puts it into \cs@linesonpageL; if the list is empty, it sets \cs@linesonpageL to 1000. Similarly for \getlinesfrompagelistR.

```

@cs@linesonpageR
2601 \newcommand*{\getlinesfrompagelistL}{%
2602   \ifx\linesonpage@listL\empty
2603     \gdef\@cs@linesonpageL{1000}%
2604   \else
2605     \gl@p\linesonpage@listL\to\@cs@linesonpageL
2606   \fi}
2607 \newcommand*{\getlinesfrompagelistR}{%
2608   \ifx\linesonpage@listR\empty
2609     \gdef\@cs@linesonpageR{1000}%
2610   \else
2611     \gl@p\linesonpage@listR\to\@cs@linesonpageR
2612   \fi}
2613 %
2614 %

```

\@writelnsonpageL These macros output the number of lines on a page to the section file in the form of
 \@writelnsonpageR \@lopL or \@lopR macros.

```

2615 \newcommand*{\@writelnsonpageL}[1]{%
2616   \edef\next{\write\linenum@out{\string\@lopL{#1}}}\%
2617   \next}
2618 \newcommand*{\@writelnsonpageR}[1]{%
2619   \edef\next{\write\linenum@outR{\string\@lopR{#1}}}\%
2620   \next}
2621 %
2622 %

```

\l@dcalc@maxoftwo \l@dcalc@maxoftwo{\langle num\rangle}{\langle num\rangle}{\langle count\rangle} sets *count* to the maximum of the
 \l@dcalc@minoftwo two *num*.

Similarly \l@dcalc@minoftwo{\langle num\rangle}{\langle num\rangle}{\langle count\rangle} sets *count* to the minimum of the two *num*.

```

2623 \newcommand*{\l@dcalc@maxoftwo}[3]{%
2624   \ifnum #2>#1\relax
2625     #3=#2\relax
2626   \else
2627     #3=#1\relax
2628   \fi}
2629 \newcommand*{\l@dcalc@minoftwo}[3]{%
2630   \ifnum #2<#1\relax
2631     #3=#2\relax
2632   \else
2633     #3=#1\relax
2634   \fi}
2635 %
2636 %

```

XIX.7 Page break managing

\ifl@dsamepage \checkpageL tests if the space and lines already taken on the page by text and footnotes is less than the constraints. If so, then \ifl@dpagefull is set FALSE and \ifl@dsamepage is set TRUE. If the page is spatially full then \ifl@dpagefull is set TRUE and \ifl@dsamepage is set FALSE. If it is not spatially full but the maximum number of lines have been output then both \ifl@dpagefull and \ifl@dsamepage are set FALSE.
 \l@dsamepagetrue
 \l@dsamepagefalse
 \ifl@dpagefulltrue
 \l@dpagefulltrue
 \l@dpagefullfalse

```

2637 \checkpageL \newif\ifl@dsamepage
2638 \checkpageR \l@dsamepagetrue
2639 \newif\ifl@dpagefull
2640 %
2641 \newcommand*{\checkpageL}{%
2642   \l@dpagefulltrue
2643   \l@dsamepagetrue
2644   \check@goal

```

```

2645 \ifdim\pagetotal<\ledthegoal
2646   \ifnum\numpagelinesL<\l@minpagelines
2647   \else
2648     \ifnomaxlines%
2649     \else%
2650       \l@dsamepagefalse%
2651       \l@dpagewillfalse%
2652     \fi%
2653   \fi
2654 \else
2655   \l@dsamepagefalse
2656   \l@dpagewilltrue
2657 \fi%
2658 \ifprint@last@after@pendL%
2659   \l@dpagewillfalse%
2660   \l@dsamepagefalse%
2661   \print@last@after@pendLfalse%
2662 \fi%
2663 }%
2664
2665 \newcommand*{\checkpageR}{%
2666   \l@dpagewilltrue
2667   \l@dsamepagetrue
2668   \check@goal
2669   \ifdim\pagetotal<\ledthegoal
2670     \ifnum\numpagelinesR<\l@minpagelines
2671     \else
2672       \ifnomaxlines%
2673       \else%
2674         \l@dsamepagefalse%
2675         \l@dpagewillfalse%
2676       \fi%
2677     \fi
2678   \else
2679     \l@dsamepagefalse
2680     \l@dpagewilltrue
2681   \fi%
2682   \ifprint@last@after@pendR%
2683     \l@dpagewillfalse%
2684     \l@dsamepagefalse%
2685     \print@last@after@pendRfalse%
2686   \fi%
2687 }%
2688 %
2689 %

```

\checkpbL \checkpbR are called after each line is printed, and after the page is checked. These commands correct page breaks depending on \ledpb and \lednorp.

```
2690 \newcommand{\checkpbL}{
```

```

2691   \IfStrEq{\led@pb@setting}{after}{
2692     \xifinlistcs{\the\absline@num}{\l@prev@pb}{\l@dpagefulltrue\
2693     \l@dsamepagefalse}{}}
2694     \xifinlistcs{\the\absline@num}{\l@prev@nopb}{\l@dpagefullfalse\
2695     \l@dsamepagetrue}{}}
2696   }{}
2697   \IfStrEq{\led@pb@setting}{before}{
2698     \numdef{\next@absline}{\the\absline@num+1}
2699     \xifinlistcs{\next@absline}{\l@prev@pb}{\l@dpagefulltrue\
2700     \l@dsamepagefalse}{}}
2701     \xifinlistcs{\next@absline}{\l@prev@nopb}{\l@dpagefullfalse\
2702     \l@dsamepagetrue}{}}
2703   }{}
2704 }
2705 \newcommand{\checkpbR}{%
2706   \IfStrEq{\led@pb@setting}{after}{
2707     \xifinlistcs{\the\absline@numR}{\l@prev@pbR}{\l@dpagefulltrue\
2708     \l@dsamepagefalse}{}}
2709     \xifinlistcs{\the\absline@numR}{\l@prev@nopbR}{\l@dpagefullfalse\
2710     \l@dsamepagetrue}{}}
2711   }{}
2712   \IfStrEq{\led@pb@setting}{before}{
2713     \numdef{\next@abslineR}{\the\absline@numR+1}
2714     \xifinlistcs{\next@abslineR}{\l@prev@pbR}{\l@dpagefulltrue\
2715     \l@dsamepagefalse}{}}
2716     \xifinlistcs{\next@abslineR}{\l@prev@nopbR}{\l@dpagefullfalse\
2717     \l@dsamepagetrue}{}}
2718   }{}
2719 }
2720 %

```

\checkverseL \checkverseL and \checkverseR are called after each line is printed. They prevent \checkverseR page break inside line of verse.

```

2714 \newcommand{\checkverseL}{%
2715   \ifinstanzaL
2716     \iflednopbinverse
2717       \ifinserthangingsymbol
2718         \numgdef{\prev@abslineverse}{\the\absline@num-1}
2719         \IfStrEq{\led@pb@setting}{after}{\lednopbnum{\prev@abslineverse}}{%
2720           \IfStrEq{\led@pb@setting}{before}{\ifnum\numpagelinesL<3\ledpbnum{\
2721             \prev@abslineverse}\fi}{%
2722             \fi
2723           \fi
2724         }%
2725       \newcommand{\checkverseR}{%
2726         \ifinstanzaR
2727           \iflednopbinverse

```

```

2728 \ifinserthangingsymbolR
2729   \numgdef{\prev@abslineverse}{\the\absline@numR-1}
2730   \IfStrEq{\led@pb@setting}{after}{\lednopbnumR{\prev@abslineverse}{}}
2731   \IfStrEq{\led@pb@setting}{before}{\ifnum\numpagelinesR<3\ledpbnumR{\prev@abslineverse}\fi}{}%
2732   \fi
2733 \fi
2734 \fi
2735 }
2736 %

```

\setgoalfraction \ledthegoal is the amount of space allowed to taken by text and footnotes on a page before a forced pagebreak. This can be controlled via \goalfraction. \ledthegoal is calculated via \check@goal.

```

\check@goal \newdimen\ledthegoal
2737 \ifshiftedpstarts
2738   \newcommand*\@goalfraction{0.95}
2739 \else
2740   \newcommand*\@goalfraction{0.9}
2741 \fi
2742 %
2743 \newcommand*\check@goal{%
2744   \ledthegoal=\@goalfraction\pagegoal}
2745 \newcommand{\setgoalfraction}[1]{%
2746   \xdef\@goalfraction{#1}}
2747 }
2748 %
2749 %

```

\ifwrittenlinesL Booleans for whether line data has been written to the section file.

```

\ifwrittenlinesL \newif\ifwrittenlinesL
2750 \newif\ifwrittenlinesR
2751 %
2752 %
2753 %

```

XIX.8 Getting boxes content

\if@getnextbox The \if@getnextbox boolean is switched to true if we can get the next chunk in a page after finished previous chunk. That is:

- If we use the nosyncpstarts option, in any case
- If we do not use it, only when the number or real or blank line of the current chunk is equal or greater to the maximum number of line in the current pair of chunks.

```

2754 \newif\if@getnextbox%
2755 %

```

\get@nextboxL If the current box is not empty (i.e., still contains some lines) nothing is done. Otherwise
\get@nextboxR if and only if a synchronisation point is reached the next box is started.

```
2756 \newcommand*\get@nextboxL{%
2757   \ifvbox\namebox{\l@dLcolrawbox\the\l@dpscL}\% box is not empty
2758   %
%
```

The current box is not empty; do nothing.

```
2759   \else%                                box is empty
2760   %
%
```

The box is empty. By default, we can get the next box

```
2761   \getnextboxtrue%Should be local, but be cautious
2762   %
%
```

But not when sufficient lines for this page have been generated (except when we don't do any synchronization whatsoever). output.

```
2763   \ifnum\useunamecount{\l@dmaxlinesinpar\the\l@dpscL}>\donetotallinesL
2764     \parledgroup@notes@endL%
2765     \unless\ifnosyncpstarts%
2766       \getnextboxfalse%
2767     %
%
```

If we use the nomaxlines option, we will start at new page, but we take count of the lines to be typeset for the actual right chunk on the right page, before starting new chunk on the left page.

```
2768   \ifnomaxlines%
2769     \ifdim\pagetotal<\ledthegoal%
2770       \numdef{\@tmp}{\l@dpscL+1}%
2771       \ifcsdef{afterlines@pstart@\@tmp R}%
2772         \ifnumless{\numpagelinesL}{\csuse{afterlines@pstart@\@tmp R}}%
2773           %
2774           \ifcsdef{minpage@pstart@\@tmp}%
2775             \ifnumless{\the\c@page}{\csuse{minpage@pstart@\@tmp}}%
2776               \ifnum\numpagelinesL=\l@dminpagelines%
2777                 \getnextboxtrue%
2778               \fi%
2779             }%
2780             {\getnextboxtrue}%
2781             {\getnextboxtrue}%
2782           }%
2783         }%
2784         \fi%
2785       \fi%
2786     \fi%
2787   \else%
2788     \ifnomaxlines%
```

```

2790   \numdef{\@tmp}{\the\l@dpscL+1}%
2791   \ifcsdef{minpage@pstart@\@tmp}%
2792     \ifnumless{\the\c@page}{\csuse{minpage@pstart@\@tmp}}%
2793       {\ifdimgreater{\pagetotal}{\ledthegoal}%
2794         {\@getnextboxtrue}%
2795         {\@getnextboxfalse}%
2796       }%
2797       {\@getnextboxtrue}%
2798     }{%
2799     \fi%
2800   \fi%
2801 %

```

Sufficient lines have been output.

```

2802   \if@getnextbox%
2803     \ifnum\useunamecount{l@dmaxlinesinpar}\the\l@dpscL=\@donetotallinesL
2804       \parledgroup@notes@endL
2805     \fi
2806     \ifwrittenlinesL\else
2807   %

```

Write out the number of lines done, and set the boolean so this is only done once.

```

2808   \@writelnlinesinparL
2809   \writtenlinesLtrue
2810   \fi
2811   \ifnum\l@dnumpstartsL>\l@dpscL
2812 %

```

There are still unprocessed boxes. Recalculate the maximum number of lines needed, and move onto the next box (by incrementing `\l@dpscL`). If needed, restart the line numbering.

```

2813   \writtenlinesLfalso
2814   \ifbypstart@
2815     \global\line@num=0%
2816     \resetprevline@%
2817   \fi
2818 % Add the content of the optional argument of the previous \protect\cs{pend}
2819 % .
2820 % \begin{macrocode}
2821   \csuse{after@pendL@\the\l@dpscL}%
2822   \global\csundef{after@pendL@\the\l@dpscL}%
2823 %

```

Check the number of lines

```

2823   \l@dcalc@maxoftwo{\the\useunamecount{l@dmaxlinesinpar}\the\l@dpscL}%
2824   {\the\@donetotallinesL}%
2825   {\useunamecount{l@dmaxlinesinpar}\the\l@dpscL}%
2826   \global\@donetotallinesL \z@
2827 %

```

Go to the next pstart

```

2828     \global\advance\l@dpscL \@ne
2829     \global\pstartnumtrue%
2830     \restore@pstartL@pc%
2831 %

```

Add notes of parallel ledgroup.

```

2832     \parledgroup@notes@endL
2833     \parledgroup@correction@notesspacing@final{L}
2834 \else
2835 %

```

```

2836     \print@last@after@pendLtrue%
2837     \fi
2838     \fi
2839     \fi}
2840 %

```

```

2841 \newcommand*{\get@nextboxR}{%
2842   \ifvbox\namebox{\l@dRcolrawbox\the\l@dpscR}%
2843   % box is not empty
2844   \else%
2845   % box is empty
2846   \@getnextboxtrue%
2847   \ifnum\useunamecount{\l@dmaxlinesinpar\the\l@dpscR}>\@donetotallinesR
2848   \parledgroup@notes@endR
2849   \unless\ifnosyncpstarts%
2850   \@getnextboxfalse%
2851   \ifnomaxlines%
2852   \ifdim\pagetotal<\ledthegoal%
2853   \numdef{\@tmp}{\l@dpscR+1}%
2854   \ifcsdef{afterlines@pstart@\@tmp L}{%
2855     \ifnumless{\numpagelinesL}{\csuse{afterlines@pstart@\@tmp L}}%
2856     %
2857     {}%
2858     \ifcsdef{minpage@pstart@\@tmp}%
2859     {\ifnumless{\the\c@page}{\csuse{minpage@pstart@\@tmp}}%
2860       \ifnum\numpagelinesR=\l@dminpagelines%
2861         \@getnextboxtrue%
2862       \fi%
2863     }%
2864     {}%
2865     {}%
2866     \fi%
2867     \fi%
2868     \fi%
2869   \else%
2870   \ifnomaxlines%

```

```

2871   \numdef{\@tmp}{\the\l@dpscR+1}%
2872   \ifcsdef{minpage@pstart@\@tmp}%
2873     \ifnumless{\the\c@page}{\csuse{minpage@pstart@\@tmp}}%
2874       {\ifdimgreater{\pagetotal}{\ledthegoal}%
2875         {\@getnextboxtrue}%
2876         {\@getnextboxfalse}%
2877       }%
2878       {\@getnextboxtrue}%
2879     }{}%
2880   \fi%
2881 \fi%
2882 \if@getnextbox%
2883   \ifnum\usenamecount{l@dmaxlinesinpar}\the\l@dpscR=\@donetotallinesR
2884     \parledgroup@notes@endR
2885   \fi
2886   \ifwrittenlinesR\else
2887     \@writelinesinparR
2888     \writtenlinesRtrue
2889   \fi
2890   \ifnum\l@dnumpstartsR>\l@dpscR
2891     \writtenlinesRfalse
2892     \ifbypstart@R
2893       \global\line@numR=0%
2894       \resetprevline@%
2895     \fi
2896     \csuse{after@pendR@\the\l@dpscR}%
2897     \global\csundef{after@pendR@\the\l@dpscR}%
2898     \l@dcalc@maxoftwo{\the\usenamecount{l@dmaxlinesinpar}\the\l@dpscR}%
2899       {\the\@donetotallinesR}%
2900       {\usenamecount{l@dmaxlinesinpar}\the\l@dpscR}%
2901     \global\@donetotallinesR \z@
2902     \global\advance\l@dpscR \c@ne
2903     \global\pstartnumRtrue%
2904     \restore@pstartR@pc%
2905     \parledgroup@notes@endR
2906     \parledgroup@correction@notespacing@final{R}
2907   \else
2908     \print@last@after@pendRtrue%
2909   \fi
2910 \fi%
2911 \fi%
2912 %
2913 %

```

XX Page numbering

XX.1 Global options

The `sameparallelpagenumber` option allows the same page number on both left and right side. The `prevpgnotnumbered` option allows an empty (not numbered) right-side page before `\Pages`.

We cannot implement these two options by changing the value of the `page` counter, since its value is used by many L^AT_EX features to determine whether a page is left (even-numbered) or right (odd-numbered). Consequently, we have to do it by patching `\thepage`, in order to use the value of the `par@page` counter instead of value of `page` counter.

This counter will be increased in a patched version of the L^AT_EX's `\@outputpage` macro, as is the `page` counter in this macro. However, this increase will take account of the options.

`\par@patch@thepage` `\par@patch@pagenumbering` `\par@patch@thepage` patches `\thepage` in order to use the value of `par@page` counter and not the value of `par@page`. It must be called after any redefinition of `\thepage`. That is why we insert it at the end of the L^AT_EX macro `\pagenumbering`, which is called by some `\xxxmatter` commands. In cases when we are using the `memoir` class, we insert it at the end of `\@memprnum`. When using `\pagenumbering`, we also need to restart `par@page` counter. Consequently, we have wrapped `\par@patch@thepage` and counter restart in `\par@patch@pagenumbering`. We also call `\par@patch@thepage` it at the beginning of the document.

```

2914
2915 \newcommand{\par@patch@thepage}{%
2916   \ifboolexpr{%
2917     bool{sameparallelpagenumber}%
2918     or bool{prevpgnotnumbered}%
2919   }{%
2920     \patchcmd{\thepage}{%
2921       {page}{par@page}%
2922       {}%
2923       {\led@error@fail@patch@thepage}%
2924     }{}%
2925   }{%
2926 }
2927
2928 \newcommand{\par@patch@pagenumbering}{%
2929   \ifboolexpr{%
2930     bool{sameparallelpagenumber}%
2931     or bool{prevpgnotnumbered}%
2932   }{%
2933     \setcounter{par@page}{1}%
2934   }{%
2935   }{%
2936   \par@patch@thepage%
2937 }
```

```

2938 }%
2939
2940 \ifl@dmemoir%
2941   \apptocmd{\@mempnum}{%
2942     {\par@patch@pagenumbering}%
2943     {}%
2944     {\led@error@fail@patch@{mempnum}}%
2945
2946 \else%
2947   \apptocmd{\pagenumbering}{%
2948     {\par@patch@pagenumbering}%
2949     {}%
2950     {\led@error@fail@patch@pagenumbering}}%
2951 \fi%
2952
2953 \AtBeginDocument{\par@patch@thepage}%
2954 %

```

\@outputpage As its name says, `\@outputpage` is a L^AT_EX's macro called in the output routine. It is this macro which increases the page counter.. We patch it in order to increase, conditionally, the `par@page` counter.

```

2955 \AtBeginDocument{%
2956   \apptocmd{\@outputpage}{%
2957     \ifsameparallelpagenumber{%
2958       \ifl@dprintingpages{%
2959         \ifodd\c@page\else{%
2960           \stepcounter{par@page}%
2961         }\fi%
2962       \else{%
2963         \stepcounter{par@page}%
2964       }\fi%
2965     }\else{%
2966       \stepcounter{par@page}%
2967     }\fi%
2968   }%
2969   {}%
2970   {\led@error@fail@patch@{@outputpage}}%
2971 }
2972 %

```

\thepar@page And now, initialize `par@page` counter.

```

2973 \newcounter{par@page}%
2974 \setcounter{par@page}{1}%
2975 %

```

XX.2 mainmatter option of \Pages

The optional argument of \Pages could be equal to `mainmatter`. In this case the boolean `\ifPages@mainmatter` is set to true, and some special things are done in `\Pages@mainmatter`, called by `\cleartol@devenpage`.

```

\ifPages@mainmatter76 \newif\ifPages@mainmatter
\Pages@mainmatter77 \newcommand{\Pages@mainmatter}{%
 2978   \ifPages@mainmatter%
 2979     \pagenumbering{arabic}%
 2980     \addtocounter{page}{1}%
 2981     \addtocounter{par@page}{-1}%
 2982     \patchcmd{\thepage}{page}{par@page}{}{%
 2983       \fi%
 2984     }
 2985   %

```

XXI Sections' titles' commands

As switching from left to right pages does not clear the page since v1.13.0, but only creates new pages, no `\vbox{}` is inserted, and consequently parallel chapters are misaligned.

So we patch the `\chapter` command in order to prevent this problem.

```

\chapter86 \preto{\chapter}{%
 2987   \ifl@dprintingpages%
 2988     \vbox{}%
 2989   \fi%
 2990   }%
 2991   {}%
 2992   {}%
 2993 %

```

`\eledsectnotoc` `\eledsectnotoc` just saves its content `\@eledsectnotoc`, which will be tested where sectioning commands will be printed.

```

 2994 \newcommand{\eledsectnotoc}[1]{\xdef\@eledsectnotoc{#1}}
 2995 \eledsectnotoc{R}
 2996 %

```

`\eledsectmark` `\eledsectmark` just saves its content `\@eledsectmark`, which will be tested where sectioning commands will be printed.

```

 2997 \newcommand{\eledsectmark}[1]{\xdef\@eledsectmark{#1}}
 2998 \eledsectmark{L}
 2999 %

```

\eledsection@correcting@skip Because the vertical correction needed after inserting a title in parallel depends whether we are in parallel columns or parallel pages, we stock its length in \eledsection@correcting@skip.

```
3000 \newskip\eledsection@correcting@skip
3001 %
```

\eled@sectioningR@out We save the sectioning commands of the right side in the \eled@sectioningR@out file.

```
3002 \newwrite\eled@sectioningR@out
3003 %
```

XXII Page break/no page break, depending on the specific line

We need to adapt the macro of the homonym section of elemac to elepar.

\prev@pbR The \l@prev@pbR macro is a etoolbox's list, which contains the lines in which page breaks occur (before or after). The \l@prev@nopbR macro is a etoolbox list, which contains the lines in which NO page breaks occur (before or after).

```
3004 \def\l@prev@pbR{}
3005 \def\l@prev@nopbR{}
3006 %
```

\ledpbR The \ledpbR macro writes the call to \led@pbR in line-list file. The \ledpbnumR macro writes the call to \led@pbnumR in line-list file. The \lednopbR macro writes the call to \led@nopbR in line-list file. The \lednopbnumR macro writes the call to \led@nopbnumR in line-list file.

```
3007 \newcommand{\ledpbR}{\write\linenum@outR{\string\led@pbR}}
3008 \newcommand{\ledpbnumR}[1]{\write\linenum@outR{\string\led@pbnumR{#1}}}
3009 \newcommand{\lednopbR}{\write\linenum@outR{\string\led@nopbR}}
3010 \newcommand{\lednopbnumR}[1]{\write\linenum@outR{\string\led@nopbnumR{#1}}}
3011 %
```

\led@pbR The \led@pbR add the absolute line number in the \prev@pbR list. The \led@pbnumR add the argument in the \prev@pbR list. The \led@nopbR add the absolute line number in the \prev@nopbR list. The \led@nopbnumR add the argument in the \prev@nopbR list.

```
3012 \newcommand{\led@pbR}{\listxadd{\l@prev@pbR}{\the\absline@numR}}
3013 \newcommand{\led@pbnumR}[1]{\listxadd{\l@prev@pbR}{#1}}
3014 \newcommand{\led@nopbR}{\listxadd{\l@prev@nopbR}{\the\absline@numR}}
3015 \newcommand{\led@nopbnumR}[1]{\listxadd{\l@prev@nopbR}{#1}}
3016 %
```

XXIII Parallel ledgroup

- \parledgroup@ The marks \parledgroup@ contains information about the beginnings and endings of notes in a parallel ledgroup. \parledgroup@series contains the footnote series. \parledgroup@type@ \parledgroup@type contains the type of the footnote: critical (Xfootnote) or familiar (footnoteX).

```

3017 \newmarks\parledgroup@
3018 \newmarks\parledgroup@series
3019 \newmarks\parledgroup@type
3020 %

```

- \parledgroup@notes@startL \parledgroup@notes@startL and \parledgroup@notes@startR are used to mark the beginning of a note series in a parallel ledgroup.

```

3021 \newcommand{\parledgroup@notes@startL}{%
3022   \ifnum\usenamecount{l@dmaxlinesinpar\the\l@dpscL}>0%
3023     \IfStrEq{\splitfirstmarks\parledgroup@type}{footnoteX}{\csuse{%
3024       bhooknoteX@\splitfirstmarks\parledgroup@series}}{}%
3025     \IfStrEq{\splitfirstmarks\parledgroup@type}{Xfootnote}{\csuse{%
3026       bhookXnote@\splitfirstmarks\parledgroup@series}}{}%
3027     \fi%
3028   \global\ledgroupnotesL@true%
3029   \insert@noterule@ledgroup{L}%
3030 }
3031 \newcommand{\parledgroup@notes@startR}{%
3032   \ifnum\usenamecount{l@dmaxlinesinpar\the\l@dpscR}>0%
3033     \IfStrEq{\splitfirstmarks\parledgroup@type}{footnoteX}{\csuse{%
3034       bhooknoteX@\splitfirstmarks\parledgroup@series}}{}%
3035     \IfStrEq{\splitfirstmarks\parledgroup@type}{Xfootnote}{\csuse{%
3036       bhookXnote@\splitfirstmarks\parledgroup@series}}{}%
3037     \fi%
3038   \global\ledgroupnotesR@true%
3039   \insert@noterule@ledgroup{R}%
3040 }
3041 %

```

- \parledgroup@notes@startL \parledgroup@notes@endL and \parledgroup@notes@endR are used to mark the end of a note series in a parallel ledgroup.

```

3038 \newcommand{\parledgroup@notes@endL}{%
3039   \global\ledgroupnotesL@false%
3040 }
3041 \newcommand{\parledgroup@notes@endR}{%
3042   \global\ledgroupnotesR@false%
3043 }
3044 %

```

- \insert@noterule@ledgroup A \vskip is not used when the boxes are constructed. So we insert it before ledgroup note series when parallel lines are constructed. This is the goal of \insert@noterule@ledgroup

```

3045 \newcommand{\insert@noterule@ledgroup}[1]{
3046   \IfStrEq{\splitbotmarks\parledgroup@}{begin}{%
3047     \IfStrEq{\splitbotmarks\parledgroup@type}{Xfootnote}{%
3048       \csuse{ifledgroupnotes#1@}
3049       \vskip\skip\csuse{mp\splitbotmarks\parledgroup@series footins}
3050       \csuse{\splitbotmarks\parledgroup@series footnoterule}
3051     \fi
3052   }
3053   {}
3054   \IfStrEq{\splitbotmarks\parledgroup@type}{footnoteX}{%
3055     \csuse{ifledgroupnotes#1@}
3056     \vskip\skip\csuse{mpfootins\splitbotmarks\parledgroup@series}
3057     \csuse{footnoterule\splitbotmarks\parledgroup@series}
3058     \fi
3059   }{%
3060   }
3061 {}%
3062 }%
3063 %

```

`\@parledgroupnotespacing` `\@parledgroupnotespacing` can be redefined by the user to change the interline spacing of ledgroup notes.

```

3064 \newcommand{\setparledgroupnotespacing}[1]{\gdef\@parledgroupnotespacing
3065 {#1}}
3066 \newcommand{\@parledgroupnotespacing}{}%
3067 %

```

`\parledgroup@notespacing@correction` `\parledgroup@notespacing@set@correction` `\parledgroup@notespacing@correction` is the difference between a normal line skip and a line skip in a note. It is set by `\parledgroup@notespacing@set@correction`, called at the beginning of `\Pages`.

```

3068 \dimdef{\parledgroup@notespacing@correction}{0pt}
3069 \newcommand{\parledgroup@notespacing@set@correction}{{%
3070   \c@getfirstseries\csuse{Xnote fontsize@\c@firstseries}}%We suppose all the
3071   series has the same footnote size setup
3072   \c@parledgroupnotespacing\dimdef{\temp@spacing}{\baselineskip}}%
3073   \dimdef{\parledgroup@notespacing@correction}{\baselineskip-\temp@spacing}%
3074 }%
3075 }%
3076 %
3077 %

```

`\ledgroup@correction@notespacing@init` `\parledgroup@correction@notespacing@init` sets the value of accumulated corrections of note spacing to 0 pt. It is called at the beginning of each pages AND at the end of each ledgroup.

```

3074 \newcommand{\parledgroup@correction@notespacing@init}{%
3075   \dimdef{\parledgroup@notespacing@correction@accumulated}{0pt}
3076   \dimdef{\parledgroup@notespacing@correction@modulo}{0pt}
3077 }%

```

```
3078 \parledgroup@correction@notespacing@init
3079 %
```

rection@notespacing@final \parledgroup@correction@notespacing@final adds the total space deleted because of correction for notes, in a parallel ledgroup. It also adds the space needed by the other side spaces between note rules and notes. It is called after the print of each pstart/pend.

```
3080 \newcommand{\parledgroup@correction@notespacing@final}[1]{
3081     \ifparledgroup
3082         \vspace{\parledgroup@notespacing@correction@accumulated}
3083         \parledgroup@correction@notespacing@init%
3084         \ifstreq{\#1}{L}{
3085             \numdef{@checking}{\the\l@dpscL-1}
3086         }{
3087             \numdef{@checking}{\the\l@dpscR-1}
3088         }
3089         \dimdef{@beforenotes@current@diff}{\csuse{\parledgroup@beforenotes@\@checking L}-\csuse{\parledgroup@beforenotes@\@checking R}}%
3090         \ifstreq{\#1}{L}%
3091             {%
3092                 \ifdimgreater{@beforenotes@current@diff}{0pt}{\vspace{-\@beforenotes@current@diff}}%
3093             }%
3094             {%
3095                 \ifdimgreater{@beforenotes@current@diff}{0pt}{\vspace{-\@beforenotes@current@diff}}%
3096             }%
3097         \fi
3098     }
3099 }
```

up@correction@notespacing \parledgroup@correction@notespacing is used before each printed line. If it is a line of notes in parallel ledgroup, the space \parledgroup@notespacing@correction is decreased, to make interline space correct. The decreased space is added to \parledgroup@notespacing@correction and \parledgroup@notespacing@correction@modulo. If \parledgroup@notespacing@correction@modulo is equal or greater than \baselineskip:

- It is decreased by \baselineskip.
- The total of line number in the current page is decreased by one.

For example, suppose an normal interline of 24 pt and interline for note of 12 pt. That means that the two lines of notes take the place of one normal line. For every two lines of notes, the line total for the current place is decreased by one.

```
3100 \newcommand{\parledgroup@correction@notespacing}[1]{%
3101     \csuse{ifledgroupnotes#1@}%
3102     \vspace{-\parledgroup@notespacing@correction}%
```

```

3103   \dimdef{\parledgroup@notespacing@correction@accumulated}{\
3104     parledgroup@notespacing@correction@accumulated+\\
3105     parledgroup@notespacing@correction}%
3106   \dimdef{\parledgroup@notespacing@correction@modulo}{\
3107     parledgroup@notespacing@correction@modulo+\\
3108     parledgroup@notespacing@correction}%
3109   \ifdimless{\parledgroup@notespacing@correction@modulo}{\baselineskip}%
3110   }{\advance\numpagelinesL -\@ne}%
3111   \dimdef{\parledgroup@notespacing@correction@modulo}{\
3112     parledgroup@notespacing@correction@modulo-\baselineskip}%
3113   }% mean greater than equal
3114   \fi%
3115 }
3116 %

```

\parledgroup@beforenotesL \parledgroup@beforenotesL and \parledgroup@beforenotesR store the total of space before notes in the current parallel ledgroup.

```

3111 \dimdef{\parledgroup@beforenotesL}{0pt}
3112 \dimdef{\parledgroup@beforenotesR}{0pt}
3113 %

```

\parledgroup@beforenotes@save The macro \parledgroup@beforenotes@save dumps the space before notes of the current parallel ledgroup in a macro named with the current pstart number.

```

3114 \newcommand{\parledgroup@beforenotes@save}[1]{
3115   \ifparledgroup
3116     \csdimgdef{\parledgroup@beforenotes@\the\csuse{10dnumstarts#1}#1}{\
3117       \csuse{\parledgroup@beforenotes#1}}
3118     \csdimgdef{\parledgroup@beforenotes#1}{0pt}
3119   \fi
3120 }
3121 %

```

XXIV Compatibility with elemac

Here, we define some command for the elemac-compat option.

```

3121 \ifelemaccompat%
3122
3123
3124 \unless\ifnocritical@
3125   \let\onlyXside\Xonlyside
3126   \fi
3127 \fi
3128 %

```

XXV The End

</code>

Appendix A Some things to do when changing version

Appendix A.1 Migration to elepar 1.4.3

Version 1.4.3 corrects a bug added in version 0.12, which made hanging verse always flush right, despite the value of the first element in the `\setstanzaindents` command.

However, if you want to return to automatic flushright margins for verses with hanging indents, you have to redefine the `\hangingsymbol` command.

```
\renewcommand{\hangingsymbol}{\protect\hfill}
```

See the following two examples:

With standard `\hangingsymbol`:

A very long verse should sometimes be hanging. The position of the hanging verse is fixed.

With the modification of the `\hangingsymbol`:

A very long verse should sometimes be hanging. And we can see that a hanging verse is flush right.

Appendix A.2 Migration from elepar to reledpar

As for migration from `elemac` to `reledmac`:

- One option has been removed because it is deprecated.
- Some of the customizations previously made by `\renewcommand` have been replaced with commands.
- Some command names have been changed in order to have a more logical and uniform pattern.

Appendix A.2.1 Deprecated options

The `shiftedverses` option has been removed. Use the general `shiftedpstart` option instead.

Appendix A.2.2 `\renewcommand` replaced with command

Many uses of `\renewcommand` have been replaced with uses of specific commands. Please read the handbook about these particular commands.

<i>Deprecated \renewcommand</i>	<i>Replaced with</i>
<code>\goalfraction</code>	<code>\setgoalfraction</code>
<code>\parledgroupnotespacing</code>	<code>\setparledgroupnotespacing</code>
<code>\Rlineflag</code>	<code>\setRlineflag</code>

Appendix A.2.3 Commands the names of which have changed

In order to ease the migration from eleedpar to reledpar, you may load `reledmac` with `eleedmac-compat` option. However, it is advised to change the command names.

<i>Old command</i>	<i>New command</i>
<code>\onlyXside</code>	<code>\Xonlyside</code>

Appendix A.3 Migration to reledpar 2.2.0

The `astanza` can take now an option argument. Consequently, if the first line of verse in a `astanza` environment starts with brackets `[]`, you must precede them with a `\relax`. If you do not do it, the content of the brackets will be considered as an optional argument of the `astanza` environment.

Appendix A.4 Migration to reledpar 2.3.0

The line number style (alphabetic, numeric, etc.) for the notes of the right side are now defined by the value you set to `\linenumberstyleR` or `\linenumberstyle*`, and not by the value you set to `\linenumberstyle` which is kept for left side.

The same is true for sub-line number styles and `\sublinenumberstyleR` or `\sublinenumberstyle*`, which are distinct from `\sublinenumberstyle`.

Consequently, if you have changed line number representation in footnotes with `\linenumberstyle` and `\sublinenumberstyle`, check your settings for these control sequences.

Appendix A.5 Migration to reledpar 2.4.0

We have fixed a bug which misaligned left and right sides when a line contained a dotted letter.

We have tested and saw no problem with this correction, but if you see a difference in alignment between version 2.3.0 and 2.4.0, please contact us.

Appendix A.6 Migration to reledpar 2.5.0

If you use either `\stanza` or `astanza` environment, please read Appendix A.12 p. 320.

Appendix A.7 Migration to reledpar 2.6.0

`\printlinenumR` was deleted. Use `\Xlineflag` instead.

Appendix A.8 Migration to reledpar 2.6.1

If you use `perpage` package to control footnote numbering, please read the handbook on 5.3.3 p. 14.

References

- [LW90] John Lavagnino and Dominik Wujastyk. ‘An overview of `edmac`: a PLAIN TeX format for critical editions’. *TUGboat*, **11**, 4, pp. 623–643, November 1990. (Code available from CTAN in `macros/plain/contrib/edmac`)
- [Wil02] Peter Wilson. *The memoir class for configurable typesetting*. November 2002. (Available from CTAN in `macros/latex/contrib/memoir`)
- [Wil04] Peter Wilson and Maïeul Rouquette. *eledmac A presumptuous attempt to port EDMAC, TABMAC and EDSTANZA to LaTeX*. December 2004. (Available from CTAN in `macros/latex/contrib/eledmac`)

Index

Symbols

\@adv	1
\@castanza@line	1
\@cs@linesinparL	1
\@cs@linesinparR	1
\@cs@linesonpageL	1
\@cs@linesonpageR	1
\@donereallinesL	1
\@donereallinesR	1
\@donetotallinesL	1
\@donetotallinesR	1
\@eledsectionL	1
\@eledsectionR	1
\@lab	1
\@lopL	1
\@lopR	1
\@nl	1
\@nl@regR	1
\@outputpage	1
\@par@sync@option	1
\@par@this@sync@option	1
\@parledgroupnotespacing	1
\@pend	1
\@pendR	1
\@pstart	1
\@pstartR	1
\@pstartsfalse	1
\@pstartstrue	1
\@ref	1
\@ref@regR	1
\@set	1
\@stopastanza	1
\@writelnlinesinparL	1

\@writelinesinparR	1
\@writelinesonpageL	1
\@writelinesonpageR	1
\@writepageofparL	1
\@writepageofparR	1
CLASSmemoir	111
COMMAND\+	48
COMMAND\@Rlineflag	75, 146
COMMAND\@adv	38, 145
COMMAND\@cs@linesinparL	102
COMMAND\@cs@linesonpageL	102
COMMAND\@eledsectionL	85
COMMAND\@eledsectionR	85
COMMAND\@eledsectmark	113
COMMAND\@eledsectnotoc	113
COMMAND\@footnotetext	77
COMMAND\@goalfraction	12, 106
COMMAND\@l@dtempcsta	69
COMMAND\@lab	37, 75, 145
COMMAND\@lopL	43, 96, 103
COMMAND\@lopR	43, 103
COMMAND\@mempnum	111
COMMAND\@namedef	79
COMMAND\@namuse	79
COMMAND\@nl	37, 44, 75, 145
COMMAND\@nl@regR	37
COMMAND\@outputpage	111, 112
COMMAND\@page	75
COMMAND\@par@sync@option	37
COMMAND\@parledgroupnotespacing	116
COMMAND\@pend	42
COMMAND\@pendR	42
COMMAND\@pstart	42
COMMAND\@pstartstrue	84
COMMAND\@ref	40, 41, 44, 145
COMMAND\@ref@regR	40
COMMAND\@set	39, 145
COMMAND\@sw	41
COMMAND\AtBeginPairs	8, 50, 143
COMMAND\AtEveryPend	143, 145
COMMAND\AtEveryPstart	2, 17, 57, 86, 143, 145
COMMAND\AtEveryPstartCall	2, 17, 18, 57, 144
COMMAND\Clear the right lines for \read@linelist	36
COMMAND\Columns	7, 8, 17, 49, 85, 89, 140–142, 145, 146
COMMAND\Columns@print@after@pend	92
COMMAND\Columns@print@before@pstart	92
COMMAND\lcolwidth	8, 10, 94
COMMAND\Leftsidehook	140
COMMAND\Leftsidehookend	140
COMMAND\MakePerPage	14

COMMAND\Pages	4, 7, 10, 12, 13, 17, 48, 49, 67, 71, 72, 94, 100, 111, 113, 116, 140, 142, 144–146
COMMAND\Pages@mainmatter	113
COMMAND\Pairs	48
COMMAND\Rcolwidth	8, 10, 94
COMMAND\Rightsidehook	140
COMMAND\Rightsidehookend	140
COMMAND\Rlineflag	120
COMMAND\Xendlineflag	15, 146
COMMAND\Xlineflag	15, 121, 146
COMMAND\Xmaxhnotes	13
COMMAND\Xnoteswidthliketwocolumns	9, 143
COMMAND\Xonlyside	14, 71, 121
COMMAND\&	18
COMMAND\absline@numR	36
COMMAND\add@penalties	69
COMMAND\add@penaltiesL	69
COMMAND\advanceline	38, 44, 145
COMMAND\affixline@num	65
COMMAND\affixline@numR	65, 140, 141
COMMAND\affixpstart@num	67
COMMAND\affixpstart@numR	67
COMMAND\affixside@note	76
COMMAND\aftercolumnseparator	9, 89, 143
COMMAND\araw@textfalse	84
COMMAND\araw@texttrue	84
COMMAND\at@begin@pairs	50
COMMAND\autopar	17
COMMAND\ballast@count	69
COMMAND\baselineskip	89, 117
COMMAND\bbl@set@language	80, 81, 145
COMMAND\beforecolumnseparator	9, 89, 143
COMMAND\begin	18
COMMAND\beginnumbering	15–17, 27, 37, 90, 141, 143, 145
COMMAND\beginnumberingR	31, 43
COMMAND\bf	141
COMMAND\bfseries	141
COMMAND\brokenpenalty	69
COMMAND\chapter	113, 140
COMMAND\check@goal	106
COMMAND\check@pstarts	84
COMMAND\checkpageL	96, 103
COMMAND\checkpb@columns	89
COMMAND\checkpbL	104
COMMAND\checkpbR	104
COMMAND\checkraw@text	84
COMMAND\checkverseL	105
COMMAND\checkverseR	105
COMMAND\clear(double)page	101
COMMAND\clearl@leftpage	101
COMMAND\clearl@rightpage	101

COMMAND\clearpage	101, 144
COMMAND\cleartoevenpage	101
COMMAND\cleartol@devenpage	101, 113
COMMAND\columnrulewidth	9, 89
COMMAND\columns@position	89
COMMAND\columnseparator	9
COMMAND\columnsposition	9, 143
COMMAND\correct@Xfootins@box	72, 73, 144
COMMAND\correct@footinsX@box	72, 144
COMMAND\critext	144
COMMAND\csname	49
COMMAND\displaywidowpenalty	69
COMMAND\do@actions	63
COMMAND\do@actions@fixedcode	140
COMMAND\do@actions@nextR	63
COMMAND\do@actionsR	63, 140
COMMAND\do@ballast	69
COMMAND\do@ballastR	63
COMMAND\do@insidelineLhook	142
COMMAND\do@insidelineRhook	142
COMMAND\do@line	57
COMMAND\do@line(L/R)	60
COMMAND\do@lineL	58, 69, 140, 141
COMMAND\do@lineLhook	140
COMMAND\do@lineR	60, 140, 141, 143
COMMAND\do@lineRhook	140
COMMAND\do@lockoff	145
COMMAND\do@lockoffR	39
COMMAND\do@lockon	145
COMMAND\do@lockonR	39
COMMAND\doinsidelineLhook	143
COMMAND\doinsidelineRhook	143
COMMAND\dolineLhook	143
COMMAND\dolineRhook	143
COMMAND\edindex	144
COMMAND\edlabel	141, 144
COMMAND\edtext	40, 44, 45, 143, 144
COMMAND\eled@sectioningR@out	114
COMMAND\eledchapter	144
COMMAND\eledsection	143, 144, 146
COMMAND\eledsection@correcting@skip	114
COMMAND\eledsectmark	20, 113
COMMAND\eledsectnotoc	20, 113
COMMAND\eledxxx	143
COMMAND\end	18
COMMAND\endgraf	56
COMMAND\endlock	44, 145
COMMAND\endnumbering	9, 15, 17, 28, 145
COMMAND\endsub	44, 145
COMMAND\endumbering	15

COMMAND\expandafter	47
COMMAND\extensionchars	27
COMMAND\firstlinenum	16, 142, 145, 146
COMMAND\firstsublinenum	142, 145, 146
COMMAND\fix@page	38, 145
COMMAND\flag@end	44, 140, 143
COMMAND\flag@start	44, 143
COMMAND\flush@notesR	70
COMMAND\footnote	49
COMMAND\footnoteX	46
COMMAND\footnoteX@reading	147
COMMAND\footnoteXmk	14
COMMAND\footnoteXnomk	14, 46
COMMAND\frontmatter	13, 21
COMMAND\get@nextboxL	141
COMMAND\get@nextboxR	141
COMMAND\getline@numL	62
COMMAND\getline@numR	62
COMMAND\getlinesfrompagelistL	102
COMMAND\getlinesfrompagelistR	102
COMMAND\getlinesfromparlistL	102
COMMAND\getlinesfromparlistR	102
COMMAND\gl@p	47
COMMAND\goalfraction	120
COMMAND\hangingsymbol	120, 141
COMMAND\hfill	88, 89
COMMAND\hidenumbering	16, 145
COMMAND\if@getnextbox	106
COMMAND\ifPages@mainmatter	113
COMMAND\ifbypage@	146
COMMAND\ifbypstart@R	146
COMMAND\ifdim	88
COMMAND\ifinserthangingsymbol	77
COMMAND\ifinserthangingsymbolR	77
COMMAND\ifl@dpagefull	103
COMMAND\ifl@dpaging	25, 143
COMMAND\ifl@dpairing	25, 140
COMMAND\ifl@dsamelang	143
COMMAND\ifl@dsamepage	103
COMMAND\ifl@pagefull	96
COMMAND\ifledRcol	25
COMMAND\iflinenumberLevenifblank	35
COMMAND\iflinenumberRevenifblank	35
COMMAND\iflledRcol	141
COMMAND\ifnumberedpar@	53
COMMAND\ifnumberingR	141
COMMAND\ifnumberpstart	49
COMMAND\ifpst@rtedL	27, 28, 53, 140
COMMAND\ifpst@rtedR	27
COMMAND\ifsublines@	39

COMMAND\insert@countR	40
COMMAND\insert@noterule@ledgroup	115
COMMAND\insertlines@list	40
COMMAND\insertlines@listR	40
COMMAND\inserts@list	53
COMMAND\inserts@listR	69
COMMAND\l@d@nums	45
COMMAND\l@d@set	39, 44, 145
COMMAND\l@dLcolrawbox	52
COMMAND\l@dLcolrawbox1	83
COMMAND\l@dLcolrawbox2	83
COMMAND\l@dRcolrawbox	52
COMMAND\l@dbfnote	77, 145
COMMAND\l@dcalc@maxoftwo	103
COMMAND\l@dcalc@minoftwo	103
COMMAND\l@dchecklang	140, 142
COMMAND\l@desnote	143
COMMAND\l@yleftbox	57, 96, 144
COMMAND\l@dlinenumR	35, 140
COMMAND\l@dlsnote	143
COMMAND\l@dmake@labels	75
COMMAND\l@dmaxlinesinpar	95
COMMAND\l@dmaxlinesinpar1	83
COMMAND\l@dminpagelines	95, 140
COMMAND\l@dnumpstartsL	82, 140
COMMAND\l@dprintingcolumnstrue	144
COMMAND\l@dprintingpagestrue	144
COMMAND\l@dpscL	86, 95, 108
COMMAND\l@dpscR	86, 95
COMMAND\l@drsnote	143
COMMAND\l@dsetupmaxlinecounts	83
COMMAND\l@duSelLanguage	81, 140
COMMAND\l@dzeroMaxLineCounts	83
COMMAND\l@prev@nopbR	114
COMMAND\l@prev@pbR	114
COMMAND\labelpstarttrue	141
COMMAND\labelref@list	75
COMMAND\labelref@listR	75
COMMAND\lang	80
COMMAND\last@page@numR	38
COMMAND\led	141
COMMAND\led@nopbR	114
COMMAND\led@nopbnumR	114
COMMAND\led@pbR	114
COMMAND\led@pbnumR	114
COMMAND\ledinnerrote	19
COMMAND\ledleftnote	19
COMMAND\lednoph	19, 89, 104
COMMAND\lednophR	114
COMMAND\lednopbnumR	114

COMMAND\ledouterote	19
COMMAND\ledpb	89, 104
COMMAND\ledpbR	114
COMMAND\ledpbnumR	114
COMMAND\ledrightnote	19
COMMAND\ledsidenote	19
COMMAND\ledstrutL	140
COMMAND\ledstrutR	140, 146
COMMAND\ledthegoal	106
COMMAND\ledtrutL	140, 146
COMMAND\leftlinenumR	35, 140
COMMAND\let	47
COMMAND\line@list@R	41
COMMAND\line@list@stuff	37, 43
COMMAND\line@margin	32
COMMAND\line@marginR	32, 140
COMMAND\line@numR	36
COMMAND\lineation	16, 144
COMMAND\lineation*	16, 32, 143
COMMAND\lineationR	16, 31, 144
COMMAND\linenum@out	75
COMMAND\linenum@outR	43
COMMAND\linenumberLevenifblanktrue	17, 147
COMMAND\linenumberRevenifblank	147
COMMAND\linenumberRevenifblanktrue	17
COMMAND\linenumberberstyle	16, 121
COMMAND\linenumberberstyle*	121
COMMAND\linenumberberstyleR	16, 121
COMMAND\linenumincrement	16, 142, 145, 146
COMMAND\linenummargin	17, 32, 140, 145–147
COMMAND\linenummargin*	17, 32, 146
COMMAND\linenummarginR	17, 32, 146
COMMAND\linenumrepR	34, 140
COMMAND\linesinpar@listL	42, 102
COMMAND\linesonpage@listL	43, 102
COMMAND\lock@off	39
COMMAND\lock@on	39
COMMAND\mainmatter	2, 13, 21, 146
COMMAND\makeatletter	60
COMMAND\maxchunks	7, 18, 83
COMMAND\maxhnotesX	13
COMMAND\memorydump	15, 30
COMMAND\n@num	144
COMMAND\new@lineL	44
COMMAND\new@lineR	44
COMMAND\newhookcommand@series	48
COMMAND\newif	144
COMMAND\newpage	100, 101, 144
COMMAND\newseries	48
COMMAND\newseries@	45

COMMAND\newseries@par	45, 47, 48
COMMAND\noledxxx	143
COMMAND\nomark@	46
COMMAND\nomaxlines	42
COMMAND\normalbfnoteX	140, 145
COMMAND\notesXwidthliketwocolumns	9, 143
COMMAND\num@lines	69
COMMAND\num@lines(R)	53
COMMAND\numberingR	29
COMMAND\numberlinefalse	7
COMMAND\numberonlyfirstinline	141
COMMAND\numberpstartfalse	16
COMMAND\numberpstarttrue	16, 141, 146
COMMAND\one@line	53, 77
COMMAND\one@lineR	53
COMMAND\onlyXside	121
COMMAND\onlysideX	14, 71, 145
COMMAND\otherlanguage	145
COMMAND\page@action	39, 145
COMMAND\pagenumbering	111, 146
COMMAND\pages	13
COMMAND\pagetotal	96, 144
COMMAND\par@line	69
COMMAND\par@line(R)	53
COMMAND\par@patch@pagenumbering	111
COMMAND\par@patch@thepage	111
COMMAND\par@sync@option	23
COMMAND\parledgroup@	115
COMMAND\parledgroup@beforenotes@save	118
COMMAND\parledgroup@beforenotesL	118
COMMAND\parledgroup@beforenotesR	118
COMMAND\parledgroup@correction@notespacing	117
COMMAND\parledgroup@correction@notespacing@final	117
COMMAND\parledgroup@correction@notespacing@init	116
COMMAND\parledgroup@notes@endL	115
COMMAND\parledgroup@notes@endR	115
COMMAND\parledgroup@notes@startL	115
COMMAND\parledgroup@notes@startR	115
COMMAND\parledgroup@notespacing@correction	116, 117
COMMAND\parledgroup@notespacing@correction@accumulated	117
COMMAND\parledgroup@notespacing@correction@modulo	117
COMMAND\parledgroup@notespacing@set@correction	116
COMMAND\parledgroup@series	115
COMMAND\parledgroup@type	115
COMMAND\parledgroupnotespacing	120
COMMAND\parledgrouptrue	19
COMMAND\patchcmd	146
COMMAND\pausenumbering	9, 30, 147
COMMAND\pend	3, 7, 10, 17–19, 49, 52, 53, 56, 57, 82, 92, 143, 145, 146
COMMAND\pendL	142

COMMAND\pendR	142
COMMAND\pends	17
COMMAND\perpage	14
COMMAND\prev@nopbR	114
COMMAND\prev@pbR	114
COMMAND\prevpgstyle	24
COMMAND\print@Xnotes	71
COMMAND\print@Xnotes@forpages	71, 144
COMMAND\print@columnseparator	88, 142
COMMAND\print@eledsectionL	59
COMMAND\print@line	59
COMMAND\print@lineL	59
COMMAND\print@notesX@forpages	144
COMMAND\printlinenumR	121
COMMAND\printlinesR	146
COMMAND\pstart	3, 7, 10, 16–19, 31, 44, 49, 52, 53, 56, 57, 82, 86, 92, 141, 143, 145, 146
COMMAND\pstartL	57, 142
COMMAND\pstartR	57, 141, 142
COMMAND\pstartinfofootnote	144
COMMAND\raw@text	82
COMMAND\read@linelist	36, 37, 123, 145
COMMAND\ref@reg	40
COMMAND\ref@regR	40, 145
COMMAND\relax	121
COMMAND\reledmac	145
COMMAND\renewcommand	120
COMMAND\resumenumbering	9, 30, 143, 147
COMMAND\resumenumberingR	31, 143
COMMAND\rightlinenumR	35, 140
COMMAND\section	140
COMMAND\section@num	27
COMMAND\selectlanguage	18, 80, 81
COMMAND\set@continuousnumberingforR	31
COMMAND\set@line	45, 145
COMMAND\set@line@action	39, 145
COMMAND\setRlineflag	17, 120
COMMAND\setgoalfraction	12, 120
COMMAND\sethangingsymbol	18
COMMAND\setline	39, 44, 145
COMMAND\setlinenum	39, 44, 145
COMMAND\setnoteposition...	90
COMMAND\setparledgroupnotespacing	120, 146
COMMAND\setposition...	90
COMMAND\setstanzaindents	9, 18, 120
COMMAND\setwidth...	90
COMMAND\sidenotemargin	19, 142
COMMAND\sidenotemargin*	19, 143
COMMAND\skipnumbering	16, 144
COMMAND\sloppy	8
COMMAND\stanza	7, 9, 16, 18, 51, 78, 121, 141

COMMAND\stanzanumtrue	19
COMMAND\startlock	44, 145
COMMAND\startsub	44, 145
COMMAND\sub@action	39, 145
COMMAND\sub@off	75
COMMAND\sub@on	75
COMMAND\subline@numR	36
COMMAND\sublinenumberstyle	16, 121
COMMAND\sublinenumberstyle*	121
COMMAND\sublinenumberstyleR	16, 121
COMMAND\sublinenumincrement	142, 145, 146
COMMAND\sublinenumrepR	34, 140
COMMAND\syntaxonly	147
COMMAND\sza@0@	18
COMMAND\textheight	13
COMMAND\textwidth	50
COMMAND\the@labelX	146
COMMAND\thefootnoteX	142
COMMAND\theledlanguageL	81
COMMAND\theledlanguageR	81
COMMAND\thepage	20, 111
COMMAND\thepstartL	16, 141
COMMAND\thepstartR	16, 141
COMMAND\thestanzaL	19
COMMAND\thestanzaR	19
COMMAND\vbox	54
COMMAND\vl@dbfnote	77
COMMAND\vskip	115
COMMAND\vsplit	69
COMMAND\widthliketwocolumns	9
COMMAND\widthliketwocolumnsfalse	9
COMMAND\widthliketwocolumnstrue	9
COMMAND\xflagref	146
COMMAND\xright@appenditem	47
COMMAND\xspace	22
COMMAND\xxxfootstart	90
COMMAND\xxxmatter	111
ENVIRONMENTLeftside	51
ENVIRONMENTRightside	52
ENVIRONMENTastanza	18, 78, 121, 146
ENVIRONMENTcolumns	29, 147
ENVIRONMENTledgroup	6, 147
ENVIRONMENTleft	16
ENVIRONMENTpages	29, 50, 146, 147
ENVIRONMENTpairs	50, 146
PACKAGEEDMAC	122
PACKAGEEDSTANZA	122
PACKAGEEledmac	45, 144
PACKAGEEledpar	144
PACKAGETABMAC	122

PACKAGEbabel	18, 80–82, 147
PACKAGEedmac	122
PACKAGEeledmac	4, 82, 118, 120, 122, 142, 143, 145, 146
PACKAGEeledpar	5, 6, 13, 33, 120, 121, 142–144
PACKAGEetoolbox	88, 114
PACKAGEledmac	6
PACKAGEledpar	1, 6
PACKAGEMemoir	122
PACKAGEmusixtex	143
PACKAGEperpage	2, 14, 121, 147
PACKAGEpolyglossia	18, 80–82, 147
PACKAGEReledmac	1, 3, 5–9, 13, 16–20, 22, 24, 25, 27, 28, 32, 33, 35–40, 42–46, 48, 49, 59, 67, 75, 77, 94, 100, 120, 121, 145–147
PACKAGEReledpar	1, 3, 5–9, 11, 12, 18–24, 31, 35, 36, 42, 43, 45, 48, 49, 75, 120, 121, 146
PACKAGESetspace	2, 20
PACKAGESyntonly	147
PACKAGEXkeyval	22
PACKAGEXTR	147

A

\absline@numR	1
\actionlines@listR	1
\actions@listR	1
\add@inserts@nextR	1
\add@insertsR	1
\add@penaltiesL	1
\add@penaltiesR	1
\advanceline	1
\affixline@numR	1
\affixpstart@numL	1
\affixpstart@numR	1
\affixside@noteR	1
\aftercolumnseparator	1, 9
\araw@textfalse	1
\araw@texttrue	1
astanza (environment)	18
\AtBeginPairs	1, 8
\AtEveryPstartCall	1
\autopar	17

B

\bblobset@language	1
\beforecolumnseparator	1, 9
\beginnumbering	15
\beginnumberingR	1

C

\c@firstlinenumR	1
\c@firstsublinenumR	1
\c@linenumincrementR	1

\c@sublinenumincrementR	1
\ch@ck@l@ckR	1
\ch@cksub@l@ckR	1
\chapter	1
\chapterinpages	1
\check@goal	1
\check@pstarts	1
\checkpageL	1
\checkpageR	1
\checkpb@columns	1
\checkpbL	1
\checkpbR	1
\checkraw@text	1
\checkverseL	1
\checkverseR	1
\clearl@leftpage	1
\clearl@rightpage	1
\cleartoevenpage	1
\cleartol@evenpage	1
\columnrulewidth	1, 9
\Columns	1, 8
\columns@position	1
\Columns@print@after@pend	1
\Columns@print@before@pstart	1
\columnseparator	1, 9
\columnsposition	1, 9
\correct@footinsX@box	1
\correct@Xfootins@box	1
\countLline	1
\countRline	1
\critext	1

D

\do@actions@fixedcodeR	1
\do@actions@nextR	1
\do@actionsR	1
\do@ballastR	1
\do@insidelineLhook	1
\do@insidelineRhook	1
\do@lineL	1
\do@lineLhook	1
\do@lineR	1
\do@lineRhook	1
\do@lockoff	1
\do@lockoffR	1
\do@lockon	1
\do@lockonR	1
\doinsidelineLhook	1
\doinsidelineRhook	1
\dolineLhook	1

\dolineRhook	1
\dump@pstartL@pc	1
\dump@pstartR@pc	1

E

\edlabel	1
\edtext	1
\eled@sectioning@out	1
\eled@section@correcting@skip	1
\eledsectmark	1, 20
\eledsectnotoc	1, 20
\endlock	1
\endnumbering	1, 15
\endnumberingR	1
\endsub	1
environments:	
astanza	18
Leftside	15
pages	10
pairs	8
Rightside	15

F

\f@x@l@cksR	1
\finish@Pages@notes	1
\first@linenum@out@Rfalse	1
\first@linenum@out@Rtrue	1
\firstlinenum	1, 16
\firstlinenum*	1, 16
\firstlinenumR	1, 16
\firstsublinenum	1, 16
\firstsublinenum*	1, 16
\firstsublinenumR	1, 16
\fix@page	1
\flag@end	1
\flag@start	1
\flush@notesR	1
\footnote@reading	1
\footnote@typeset	1
\footnoteXmk	14
\footnoteXnomk	14

G

\get@familiarfootnote@number	1
\get@nextboxL	1
\get@nextboxR	1
\getline@numR	1
\getlinesfrompagelistL	1
\getlinesfrompagelistR	1
\getlinesfromparlistL	1

\getlinesfromparlistR	1
\goalfraction	1

H

\hidenumbering	16
--------------------------	----

I

\if@getnextbox	1
\if@pstarts	1
\ifaraw@text	1
\iffirst@linenum@out@R	1
\ifinstanzaL	1
\ifinstanzaR	1
\ifl@dpagefull	1
\ifl@dpaging	1
\ifl@dpairing	1
\ifl@dsamepage	1
\ifl@dusedbabel	1
\ifledRcol	1
\iflinenumberLevenifblank	1
\iflinenumberRevenifblank	1
\ifnomaxlines	1
\ifnosyncpstarts	1
\ifPages@mainmatter	1
\ifprevpgnotnumbered	1
\ifprint@last@after@pendL	1
\ifprint@last@after@pendR	1
\ifpst@rtedL	1
\ifpst@rtedR	1
\ifpstartnumR	1
\ifsameparallelpagenumber	1
\ifshiftedpstarts	1
\ifwidthliketwocolumns	1
\ifwrittenlinesL	1
\init@series@par	1
\initnumbering@sectcountR	1
\insert@countR	1
\insert@noterule@ledgroup	1
\inserthangingsymbolL	1
\inserthangingsymbolR	1
\insertlines@listR	1
\inserts@listR	1

L

\l@d@set	1
\l@dbfnote	1
\l@dc@maxchunks	1
\l@dcalc@maxoftwo	1
\l@dcalc@minoftwo	1
\l@dcalcnunm	1

\l@dchecklang	1
\l@dleftbox	1
\l@dlinenumR	1
\l@dmake@labelsR	1
\l@dminpagelines	1
\l@dnumpstartsL	1
\l@dnumpstartsR	1
\l@dpagefullfalse	1
\l@dpagefulltrue	1
\l@drightbox	1
\l@dsamepagefalse	1
\l@dsamepagetrue	1
\l@dsetupmaxlinecounts	1
\l@dsetuprawboxes	1
\l@dskipversenumberR	1
\l@dusedbabelfalse	1
\l@dusedbabeltrue	1
\l@duselanguage	1
\l@dzeromaxlinecounts	1
\l@pscL	1
\l@pscR	1
\labelref@listR	1
\last@page@numR	1
\Lcolwidth	1, 8, 10
\led@err@BadLeftRightPstarts	1
\led@err@Columns@InsideEnv	1
\led@err@Columns@WithoutEnv	1
\led@err@LeftOnRightPage	1
\led@err@Leftside@PreviousNotPrinted	1
\led@err@Pages@InsideEnv	1
\led@err@Pages@WithoutEnv	1
\led@err@RightOnLeftPage	1
\led@err@Rightside@PreviousNotPrinted	1
\led@err@TooManyPstarts	1
\led@error@fail@patch@@mempnum	1
\led@error@fail@patch@@outputpage	1
\led@error@fail@patch@pagenumbering	1
\led@error@fail@patch@thepage	1
\led@nopbnumR	1
\led@nopbR	1
\led@pbnumR	1
\led@pbR	1
\led@warn@ChangeSyncOption	1
\led@warn@setting@in@rightsides	1
\lednopbnum	1
\lednopbnumR	1
\ledpbnumR	1
\ledpbR	1
\ledstrutL	1
\ledstrutR	1

\ledthegoal	1
\leftlinenumR	1
\leftpstartnumL	1
\leftpstartnumR	1
Leftside (environment)	15
\Leftsidehook	1
\Leftsidehookend	1
\line@list@stuffR	1
\line@listR	1
\line@marginR	1
\line@numR	1
\lineation*	1, 16
\lineationR	1, 16
\linenum@outR	1
\linenumberLevenifblanktrue	17
\linenumberRevenifblanktrue	17
\linenumberstyle*	1, 16
\linenumberstyleR	1, 16
\linenumincrement	1, 16
\linenumincrement*	1, 16
\linenumincrementR	1, 16
\linenummargin	1
\linenummargin*	1, 17
\linenummarginR	1, 17
\linenumrepR	1
\linesinpar@listL	1
\linesinpar@listR	1
\list@clearing@regR	1
\list@pstartL@pc	1
\list@pstartR@pc	1
\lock@off	1

M

\maxchunks	1, 7
\maxlinesinpar@list	1
\memorydump	15
\memorydumpL	1
\memorydumpR	1

N

\n@num	1
\namebox	1
\new@lineL	1
\new@lineR	1
\newnamebox	1
\newnamecount	1
\newseries@par	1
\normalbfnoteX	1
\notesXwidthliketwocolumns	9
\num@linesR	1

\numberpstartfalse	16
\numberpstarttrue	16
\numpagelinesL	1
\numpagelinesR	1

O

\one@lineR	1
\onlysideX	14
optionadvancedshiftedpstarts	10, 12
optioncontinuousnumberingwithcolumns	9, 147
optionnomaxlines	10, 11, 23
optionnosyncpstarts	12, 23, 106
optionshiftedpstarts	6, 12, 23
optionwidthliketwocolumns	9

P

\page@action	1
\page@numR	1
\Pages	1, 10
pages (environment)	10
\Pages@mainmatter	1
pairs (environment)	8
\par@lineR	1
\par@patch@pagenumbering	1
\par@patch@thepage	1
\parledgroup@	1
\parledgroup@beforenotes@save	1
\parledgroup@beforenotesL	1
\parledgroup@beforenotesR	1
\parledgroup@correction@notespacing	1
\parledgroup@correction@notespacing@final	1
\parledgroup@correction@notespacing@init	1
\parledgroup@notes@startL	1
\parledgroup@notes@startR	1
\parledgroup@notespacing@correction	1
\parledgroup@notespacing@set@correction	1
\parledgroupseries@	1
\parledgrouptype@	1
\pausenumberingR	1
\pend	17
\pendL	1
\pendR	1
\prev@nopbR	1
\prev@pbR	1
\prevpgstyle	1
\print@columnseparator	1
\print@eledsectionL	1
\print@eledsectionR	1
\print@lineL	1
\print@lineR	1

\print@notesX@forpages	1
\print@Xnotes@forpages	1
\pstart	17
\pstartL	1
\pstartR	1

R

\Rcolwidth	1, 8, 10
\read@linelist	1
\reledpar@error	1
\reledpar@warning	1
\restore@pstartL@pc	1
\restore@pstartR@pc	1
\resumenumberingR	1
\rightlinenumR	1
\rightpstartnumL	1
\rightpstartnumR	1
Rightside (environment)	15
\Rightsidehook	1
\Rightsidehookend	1
\Rlineflag	1

S

\save@familiarfootnote@number	1
\save@section@number	1
\section@numR	1
\selectlanguage	1
\set@continuousnumberingforR	1
\set@line	1
\set@line@action	1
\set@sectcountR	1
\setgoalfraction	1, 12
\sethangingsymbol	18
\setline	1
\setlinenum	1
\setnamebox	1
\setnotepositionliketwocolumns@C	1
\setnotepositionliketwocolumns@L	1
\setnotepositionliketwocolumns@R	1
\setpositionliketwocolumns@C	1
\setpositionliketwocolumns@L	1
\setpositionliketwocolumns@R	1
\setRlineflag	17
\setwidthliketwocolumns@C	1
\setwidthliketwocolumns@L	1
\setwidthliketwocolumns@R	1
\sidenote@marginR	1
\sidenotemargin*	1
\skip@lockoff	1
\skipnumbering	1, 16

\startlock	1
\startsub	1
\sub@action	1
\subline@numR	1
\sublinenumberstyle*	<u>1</u> , 16
\sublinenumberstyleR	<u>1</u> , 16
\sublinenumincrement	<u>1</u> , 16
\sublinenumincrement*	<u>1</u> , 16
\sublinenumincrementR	<u>1</u> , 16
\sublinenumrepR	1
T	
\theledlanguageL	1
\theledlanguageR	1
\thepar@page	1
\thepstartL	16
\thepstartR	16
\thestanzaL	<u>1</u> , 19
\thestanzaR	<u>1</u> , 19
U	
\unhnamebox	1
\unvnamebox	1
\usenamecount	1
W	
\widthliketwocolumns	9
X	
\Xendlineflag	15
\Xlineflag	15
\Xnoteswidthliketwocolumns	9
\Xonlyside	14

Change History

v0.1.0.

General: First public release 1

v0.2.0.

\Columns: Added \l@dchecklang and \l@duselanguage to \Columns 86

\Pages: Added \l@duselanguage to \Pages 96

General: Added section of babel related code 80

Fix babel problems 1

v0.3.0.

\Pages: Added \ledstrutL to \Pages 96

Added \ledstrutR to \Pages 98

\Rightsidehookend: Added \Leftsidehook, \Leftsidehookend, \Rightsidehook

and \Rightsidehookend 51

\affixline@numR: Changed \affixline@numR to match new elemac 65

\do@actions@nextR: Used \do@actions@fixedcode in \do@actionsR 63

\do@lineL: Added \do@lineLhook to \do@lineL 58

Simplified \do@lineL by using macros for some common code 58

\do@lineR: Changed \do@lineR similarly to \do@lineL 60

\flag@end: Removed extraneous spaces from \flag@end 44

\ifledRcol: Moved \ifl@dpairing to elemac 25

\ifpst@rtedR: Moved \ifpst@rtedL to elemac 27

\l@dlinenumR: Simplified \leftlinenumR and \rightlinenumR by introducing

\l@dlinenumR 35

\l@dnumpstartsR: Moved \l@dnumpstartsL to elemac 82

\ledstrutR: Added \ledstrutL and \ledstrutR 100

\normalbfnoteX: Removed extraneous spaces from \normalbfnoteX 77

\sublinenumrepR: Added \linenumrepR and \sublinenumrepR 34

General: Added \do@lineLhook and \do@lineRhook 60

Added hooks into Leftside environment 51

Reorganize for ledarab 1

v0.3.a.

\line@marginR: Do not just set \line@marginR in \linenummargin 32

General: Minor \linenummargin fix 1

v0.3.b.

\Pages: Added \l@dminpagelines calculation for succeeding page pairs 99

General: Improved parallel page balancing 1

v0.3.c.

General: Compatibility with Polyglossia 1

v0.4.0.

General: No more ledparpatch. All patches are now in the main file. 1

v0.5.0.

General: Corrections about \section and other titles in numbered sections 1

v0.6.0.

General: Be able to use \chapter in parallel pages. 1

v0.7.0.

General: Option ‘shiftedverses’ which make there is no blank between two parallel
verses with unequal length. 1

v0.8.0.	
General: Possibility to have a symbol on each hanging of verses, like in the french typography. Redefine the commande \hangingsymbol to define the character.	1
v0.9.0.	
\ifledRcol: Moved \if1ledRcol and \ifnumberingR to elemac	25
General: Possibility to number \pstart.	16
Possibilty to number the pstart with the commands \numberpstarttrue.	1
v0.9.1.	
General: The numbering of the pstarts restarts on each \beginnumbering.	1
v0.9.2.	
General: Debug : with \Columns, the hanging indentation now runs on the left columns and the hanging symbol is shown only when \stanza is used.	1
v0.9.3.	
General: \thepstartL and \thepstartR use now \bfseries and not \bf, which is deprecated and makes conflicts with memoir class.	1
v0.10.0.	
General: \edlabel commands on the right side are now correctly indicated.	1
\edlabel commands which start a paragraph are now put in the right place.	1
v0.11.0.	
\Columns: Line numbering by pstart.	87
\affixline@numR: Changed \affixline@numR to allow to disable line numbering (like in elemac 0.15).	65
\get@nextboxR: Change \get@nextboxL and \get@nextboxR to allow to disable line numbering (like in elemac 0.15).	107
Pstart number can be printed in side	108
\inserthangingsymbolR: Prevent the column separator for hanging verse from shifting	77
General: Change \do@lineL and \do@lineR to allow line numbering by pstart (like in elemac 0.15).	58
Lineation can be by pstart (like in elemac 0.15).	31
New management of hangingsymbol insertion, preventing undesirable insertions.	77
v0.12.0.	
General: New management of hangingsymbol insertion, preventing undesirable insertions.	77
v1.0.0.	
General: Compatibility with elemac. Change name to elepar.	1
Debug in lineation by pstart	31
v1.0.1.	
General: Correction on \numberonlyfirstinline with lineation by pstart or by page.	1
v1.1.0.	
\pstartR: Add \labelpstarttrue (from elemac).	53
General: Shiftedverses becomes shiftedpstarts.	1
v1.1.1.	
\pstartR: Correct \pstartR bug introduced by 1.1.	53
v1.1.2.	
\affixside@noteR: Remove spurious space between line number and line content	76
v1.2.0.	
General: Support for \led<section> commands in parallel texts.	1
v1.2.1.	
\set@sectcountR: For the right section, the counter is defined only once.	29

v1.3.0.	
\edtext: Manage RTL language.	45
v1.3.1.	
\l@dbfnote: Compatibility of standard footnotes with elemac when theses footnotes contain any commands.	77
v1.3.2.	
General: Debug with some classes.	1
v1.3.3.	
\l@dbfnote: Spurious space with footnote in right column.	77
General: Debugging the left notes of the right column.	76
v1.3.4.	
General: Allow use of commands in sidenotes, as introduced by elemac 1.0.	76
v1.3.5.	
\normalbfnoteX: Allows one to redefine \thefootnoteX with alph when some packages are loaded.	77
v1.4.0.	
General: Added \do@insidelineLhook and \do@insidelineRhook	60
v1.4.1.	
\normalbfnoteX: Fix bug with normal familiar footnotes when mixing RTL and LTR text.	77
General: Enable the use of stanzaidentsrepetition within astanza environment.	78
v1.4.3.	
\inserthangingsymbolR: Hanging verse is no longer automatically flush right.	77
\pendL: Spurious spaces in \pendL.	56
\pendR: Spurious spaces in \pstartR.	56
\pstartR: Spurious spaces in \pstartL and \pstartR.	53
General: Corrects a false hanging verse when a verse is exactly the length of a line.	1
v1.5.0.	
\sublinenumincrement*: Add starred version of \firstlinenum, \linenumincrement, \firstsublinenum, \sublinenumincrement to change both Left and Rightside.	33
General: Add, as in elemac, features to manage page breaks.	1
v1.6.0.	
General: Add tool and documentation for parallel ledgroups	19
v1.7.0.	
General: Add, as in elemac, features to make crossrefs with pstart numbers.	1
v1.8.0.	
\Columns: Modify \Columns to enable to add section's title.	85
Suppress \l@dchecklang from \Columns.	86
\Pages: Modify \Pages to enable to add section's title.	94
\l@dchecklang: Suppress \l@dchecklang which did not work and was not logical, because both columns could have the same language but not the main language of the document.	80
\pendL: As in elemac, \pendL can have an optional argument.	56
\pendR: As in elemac, \pendR can have an optional argument.	56
\print@columnseparator: Move some code of \Columns to \print@columnseparator.	88
\pstartR: As in elemac, \pendL and \pendR can have an optional argument.	53
\sidenotemargin*: \sidenotemargin is now directly defined in elemac to be able to manage elepar.	76

Add \sidenotemargin*	76
\theledlanguageR: Correct left/right language setting with polyglossia.	82
General: \beginnumbering is defined only on <code>eledmac</code> , not on <code>eledpar</code> .	27
\l@dlsnote, \l@drsnote and \l@dcnote defined only one time, in <code>eledmac</code> .	76
Add \beforecolumnseparator and \aftercolumnseparator.	9
Add \columnsposition.	9
Add, as in <code>eledmac</code> , new system of sectioning commands.	1
Add, as in <code>eledmac</code> , option to insert something after \pends / verses.	1
Add, as in <code>eledmac</code> , option to insert something between \pstarts / verse.	1
Change \do@lineR and \do@lineR to allow new sectioning commands.	58
Compatibility with <code>musixtex</code> .	1
Debug <code>eledmac</code> sectioning command after using \resumenumbers.	1
New sectioning commands, as in <code>eledmac</code> .	20
Suppress \ifl@dsamelang which did not work and was not logical, because both columns could have the same language but not the main language of the document.	80
v1.8.1.	
\do@lineL: Fix a bug with critical notes at the begining of a page, (maybe added by v1.8.0) (?).	58
\do@lineR: Fix a bug with critical notes at the begining of a page, added by v1.8.0 (?).	60
v1.8.2.	
\flag@end: \flag@start and \flag@end are now defined only one time for <code>eledmac</code> and <code>eledpar</code>	44
\lineation*: Add \lineation*	32
\reledpar@error: Errors specific to <code>eledpar</code> send to <code>eledpar</code> handbook	25
General: Debug \eletedxxx with some paper sizes	1
Debug left and side note (bugs added by 1.8.0)	1
v1.8.3.	
\Pages: Debug blank pages when using optional argument in the last \pend.	94
\doinsidelineRhook: Added \dolineLhook, \dolineRhook, \doinsidelineLhook and \doinsidelineRhook	60
\resumenumbersR: Debug \resumenumbersR	30
General: Add \noeledxxx, as in <code>eledmac</code>	1
v1.9.0.	
\ifwidthliketwocolumns: Added widthliketwocolumns option	24
\theledlanguageR: Debug left/right language switching with polyglossia. Do not write in .aux file when setting left/right lines.	82
General: Add \AtBeginPairs macro	8
Compatibility with \Xnoteswidthliketwocolumns and \notesXwidthliketwocolumns	1
v1.9.1.	
\ifledRcol: Moved \ifl@dpaging to <code>eledmac</code>	25
v1.10.0.	
\Pages: Debug wrong pages splitting when no optional argument is used in last \pend (bug was added in v.1.8.3).	94
Debug wrong parallel pages synchronization when an \edtext falls across two pages.	94
General: Compatibility with \AtEveryPstart and \AtEveryPend	1
Restore critical notes in \eledsection in parallel columns (this bug was added in 1.8.2).	1

v1.10.1.	
\line@list@stuffR: Revert modification of 1.4.2, which makes bugs with numbering.	
Leave vertical mode to solve spurious space before minipage.	43
v1.11.0.	
\edtext: \critext and \edtext are now defined only in elemac.	45
General: Compatibility of standard footnotes with some biblatex styles.	1
v1.12.0.	
\Columns: Add \l@dprintingcolumnstrue	85
\Pages: Add \l@dprintingpagestrue	94
\edlabel: \edlabel and \edindex works now with hyperref when using elepar.	75
\edlabel is now defined only one time for both elemac and elepar	75
\print@eledsectionL: Compatibility with Lua ^T E _X RTL languages.	59
\print@eledsectionR: Compatibility with Lua ^T E _X RTL languages.	62
\print@lineL: Compatibility with Lua ^T E _X RTL languages.	59
General: Compatibility with Lua ^T E _X RTL languages.	1
v1.12.1.	
\print@eledsectionL: Fixes bug with Lua ^T E _X RTL \eledsection.	59
v1.13.0.	
\Pages: Prevent false overfull hboxes when using \Pages outside of pages environment.	94
When using shiftedpstarts option, a \l@dleftbox with a null height will advance the	
\pagetotal in any case.	94
\clear@drighthpage: Use \newpage instead of \clearpage.	101
\ifledRcol: Remove false boolean settings which are not needed.	25
General: Enable the use of optional argument of & in astanza environment.	78
Fix bug in shiftedpstarts when size difference between pstarts is very important.	1
With parallel pages, long notes can now flow from the Left to the right side and from	
the Right to the left side.	1
v1.13.1.	
\Pages: Prevent false empty page after \Pages (bug added in 1.13.0)	94
\correct@footinsX@box: Call \correct@footinsX@box and	
\correct@Xfootins@box directly in \print@notesX@forpages and	
\print@Xnotes@forpages.	71
Correct \correct@footinsX@box and \correct@Xfootins@box	71
v1.14.0.	
General: Fix bug with line number position when using \eledsection and similar	
commands for RTL texts with Lua ^T E _X	1
The \newifs are not followed by boolean values set to false, because it is the T _E _X	
default setting.	1
v1.15.0.	
\do@actions@nextR: Add action 1008 and 1009	63
\inserthangingsymbolR: Prevent more efficiently the column separator from shifting	
when a verse is hanging	77
\lineationR: As \lineation, \lineationR automatically set the	
\pststartinfofootnote.	31
\n@num: \n@num defined only one time for both Elemac and Elepar.	40
\skipnumbering: \skipnumbering defined only one time for both Elemac and	
Elepar	45
General: Add \AtEveryPstartCall.	1
Add sameparallelpagenumber option.	12
Fix vertical spurious space before right \eledchapter (bug added in v1.13.0).	1

Prevent vertical space when using \AtEveryPstart or \AtEveryPend with a command which prints nothing	1
v1.16.0.	
\newseries@par: Fix bug with \onlysideX.	45
General: Error message when calling \Pages inside ‘pages’ environment and \Columns inside ‘pairs’ environment.	1
Error message when starting a Leftside/a Rightside while the previous one has not been yet typeset.	1
Error message when using \beginnumbering... \endnumbering without \pstart.	1
Fix bug with nofamiliar / nocritical option of elemac.	1
New package option sameparallelpagenumber to have the same page number for both left and right side.	1
v1.16.1.	
General: Write information about line-list file version in the correct file.	1
v1.16.2.	
General: Fix bug when adding empty lines before a \pend in combination with some specific penalties setting.	1
v1.17.0.	
General: Add compatibility of optional argument of \pstart/\pend and \AtEveryPstart/\AtEveryPend with two columns mode.	1
v1.21.0.	
General: Add \hidenumbering	16
v2.0.0.	
\@adv: \@adv defined only in reledmac.	38
\@lab: \@lab defined only in elemac.	75
\@ref@regR: \@ref defined only in reledmac, code specific to right side moved in \ref@regR.	40
\@set: \@set defined only in reledmac.	39
\advanceline: \advanceline defined only in reledmac.	44
\bb@\set@language: Patch \bb@\set@language instead of redefining it	80
\do@lockonR: \do@lockon defined only in reledmac.	39
\endlock: \startlock and \endlock defined only in reledmac.	44
\endsub: \startsub and \endsub defined only in reledmac.	44
\fix@page: \fix@page is defined only once in reledmac	38
\l@d@set: \l@d@set defined only in reledmac.	39
\l@dbfnote: \l@dbfnote defined only in reledmac.	77
\line@marginR: \linenummargin now defined only once time in reledmac.	32
\normalbfnoteX: \normalbfnoteX defined only in reledmac.	77
\page@action: \page@action defined only in reledmac.	39
\read@linelist: \read@linelist is defined only once time in \reledmac.	37
\set@line: \set@line defined only in reledmac.	45
\set@line@action: \set@line@action defined only in reledmac.	39
\setline: \setline defined only in reledmac.	44
\setlinenum: \setlinenum defined only in reledmac.	44
\skip@lockoff: \do@lockoff defined only in reledmac.	39
\sub@action: \sub@action defined only in reledmac.	39
\sublinenumincrement*: \firstlinenum, \linenumincrement, \firstsublinenum, \sublinenumincrement are now defined only in reledmac.	33
\theledlanguageR: Patch \otherlanguage instead of redefining it.	82
General: \onl is now defined only in reledmac.	37

\ifbypage@ and \ifbypstart@R defined in <code>elemac</code>	31
Fix some bugs with ‘ <code>sameparallelpagenumber</code> ’ option.	1
Many code refactored and moved to <code>reledmac</code>	1
Package’s name becomes <code>reledpar</code>	1
Totally new implementation of ‘ <code>sameparallelpagenumber</code> ’ option.	1
<code>chapterinpages</code> : Deleting the old system of managing parallel chapter, keep only the new one with <code>\patchcmd</code>	50
v2.1.0.	
General: Fix bug when using <code>\uledsection</code> and related on right pages when page width is short.	1
Fix bug when using <code>\pagenumbering</code> with memoir (bug added in v2.0.0).	1
Fix bug with <code>\setparledgroupnotespacing</code> with the <code>shiftedstarts</code> option.	1
Fix incompatibility between optional argument of <code>\pstart</code> and <code>\numberpstarttrue</code>	1
Options to custom empty right page before <code>\Pages</code>	1
v2.2.0.	
General: <code>astanza</code> environment can take an optional argument, which will be the optional argument of <code>\pstart</code> started by this environment.	1
New tools to number stanza	1
v2.2.1.	
General: Fix bug with optional argument of last left <code>\pend</code>	1
v2.3.0.	
<code>\Pages</code> : Fix bug when calling <code>\Columns</code> after a <code>\Pages</code> (bug added in v1.13.0).	94
General: Change some internal codes in order to provide compatibility with L ^A T _E X release of october 2015	1
Fix bug with title number in parallel columns	1
New line setting command suffixed by R to set only the right side.	1
v2.4.0.	
<code>\ledstrutR</code> : Deleted <code>\ledtrutL</code> and <code>\ledstrutR</code>	100
Fix bug with dotted letter	100
General: New way of (not) synchronizing the parallel pages.	1
Option to switch to <code>\mainmatter</code> when calling <code>\Pages</code>	1
v2.5.0.	
General: Disable empty lines as paragraph in <code>astanza</code>	1
Fix bug introduced in v1.15.0 which made hanging indentation in verse not work anymore.	1
New commands <code>\linenummarginR</code> and <code>\linenummargin*</code>	1
v2.5.1.	
General: Fix spurious space when using optional argument of <code>astanza</code> environment (introduced in v2.5.0).	1
v2.5.2.	
General: Fix bug introduced in v2.5.0 with <code>\linenummargin</code> , <code>\firstlinenum</code> , <code>\linenumincrement</code> , <code>\firstsublinenum</code> , <code>\sublinenumincrement</code>	1
v2.6.0.	
<code>\l@dmake@labelR</code> : <code>\@Rlineflag</code> is not stored directly after the line number, but as a fifth argument of <code>\the@labelX</code> . Can be retrieved by <code>\xflagref</code>	75
General: <code>\Xlineflag</code> and <code>\Xendlineflag</code> added	1
<code>\printlinesR</code> deleted	1
Error message when calling <code>\Pages</code> or <code>\Columns</code> without previous <code>pages</code> or <code>pairs</code> environment.	1

Fix bug with footnote numbering when using the same series of familiar footnotes on both sides.	1
Fix bug with right side title number when using title commands before <code>pages</code> or <code>columns</code> environments.	1
Fix compatibility with <code>babel</code> (broken in v.2.0.0).	1
No error messages about ends of left / right page when using the <code>\syntaxonly</code> command of the <code>syntonly</code> package.	1
v2.6.1.	
General: Fix bug, introduced in v2.6.0, with footnote numbering when using <code>perpage</code> package.	1
v2.6.2.	
<code>\newseries@par</code> : The TeX counter <code>\footnoteX@reading</code> is defined in <code>reledmac</code>	46
General: Fix (again) bugs with footnote numbering in parallel typesetting while using <code>ledgroup</code> environments (bug added in v2.6.0).	1
Fix bug (added in v2.6.0) with footnote numbering in parallel typesetting while using <code>polyglossia</code> with specific numbering systems (like Greek).	1
v2.6.3.	
General: Fix spurious dot when using <code>\linenummargin</code> on right side (introduced in v2.5.0).	1
v2.7.0.	
General: <code>reledmac</code> cross-referencing can take advantage of <code>xr</code> package.	1
v2.7.1.	
General: Fix bug added in <code>reledmac</code> 2.8.2, when typesetting parallel text just after a sectioning command	1
v2.8.0.	
General: Allow continuing line numbering between normal text and parallel text, using <code>\pausenumbering</code> and <code>\resumenumbering</code> and the <code>continuousnumberingwithcolumns</code> options.	1
Add <code>\linenumberLevenifblanktrue</code> and <code>\linenumberRevenifblank</code> commands	1
Fix bug when the right line number style is not the same to the left line number style	1