NAME

pdftex - PDF output from TeX

SYNOPSIS

pdftex [options] [&format] [file|\commands]

DESCRIPTION

Run the pdfT_EX typesetter on *file*, usually creating *file.pdf*. If the file argument has no extension, ".tex" will be appended to it. Instead of a filename, a set of pdfT_EX commands can be given, the first of which must start with a backslash. With a & *format* argument pdfT_EX uses a different set of precompiled commands, contained in *format*.fmt; it is usually better to use the -fmt *format* option instead.

 $pdfT_{E}X$ is a version of $T_{E}X$, with the e- $T_{E}X$ extensions, that can create *PDF* files as well as *DVI* files.

In DVI mode, $pdfT_EX$ can be used as a complete replacement for the T_EX engine.

The typical use of $pdfT_EX$ is with a pregenerated formats for which PDF output has been enabled. The **pdftex** command uses the equivalent of the plain T_EX format, and the **pdflatex** command uses the equivalent of the LATEX format. To generate formats, use the **-ini** switch.

The **pdfinitex** and **pdfvirtex** commands are $pdfT_EX$'s analogues to the **initex** and **virtex** commands. In this installation, if the links exist, they are symbolic links to the **pdftex** executable.

In *PDF* mode, pdfT_EX can natively handle the *PDF*, *JPG*, *JBIG2*, and *PNG* graphics formats. pdfT_EX cannot include PostScript or Encapsulated PostScript (EPS) graphics files; first convert them to PDF using **epstopdf**(1). pdfT_EX's handling of its command-line arguments is similar to that of of the other T_EX programs in the *web2c* implementation.

OPTIONS

This version of pdfT_EX understands the following command line options.

-draftmode

Sets $\pdfdraftmode so pdfTEX doesn't write a PDF and doesn't read any included images, thus speeding up execution.$

- -enc Enable the encT_EX extensions. This option is only effective in combination with -ini. For documentation of the encT_EX extensions see http://www.olsak.net/enctex.html.
- -etex Enable the e-T_EX extensions. This option is only effective in combination with -ini. See etex(1).

-file-line-error

Print error messages in the form *file:line:error* which is similar to the way many compilers format them.

-no-file-line-error

Disable printing error messages in the *file:line:error* style.

-file-line-error-style

This is the old name of the **-file-line-error** option.

-fmt format

Use *format* as the name of the format to be used, instead of the name by which $pdfT_{EX}$ was called or a %& line.

-halt-on-error

Exit with an error code when an error is encountered during processing.

- -help Print help message and exit.
- -ini Start in *INI* mode, which is used to dump formats. The *INI* mode can be used for typesetting, but no format is preloaded, and basic initializations like setting catcodes may be required.

-interaction mode

Sets the interaction mode. The mode can be either *batchmode*, *nonstopmode*, *scrollmode*, and *errorstopmode*. The meaning of these modes is the same as that of the corresponding \commands.

-ipc Send DVI or PDF output to a socket as well as the usual output file. Whether this option is available is the choice of the installer.

-ipc-start

As **-ipc**, and starts the server at the other end as well. Whether this option is available is the choice of the installer.

-jobname name

Use *name* for the job name, instead of deriving it from the name of the input file.

-kpathsea-debug bitmask

Sets path searching debugging flags according to the bitmask. See the *Kpathsea* manual for details.

-mktex fmt

Enable mktex *fmt*, where *fmt* must be either *tex* or *tfm*.

-mltex Enable MLT_EX extensions. Only effective in combination with -ini.

-no-mktex fmt

Disable mktex *fmt*, where *fmt* must be either *tex* or *tfm*.

-output-comment string

In *DVI* mode, use *string* for the *DVI* file comment instead of the date. This option is ignored in *PDF* mode.

-output-directory directory

Write output files in *directory* instead of the current directory. Look up input files in *directory* first, the along the normal search path.

-output-format format

Set the output format mode, where *format* must be either *pdf* or *dvi*. This also influences the set of graphics formats understood by pdfT_EX.

-parse-first-line

If the first line of the main input file begins with %& parse it to look for a dump name or a **-translate-file** option.

-no-parse-first-line

Disable parsing of the first line of the main input file.

-progname name

Pretend to be program *name*. This affects both the format used and the search paths.

-recorder

Enable the filename recorder. This leaves a trace of the files opened for input and output in a file with extension *.fls*.

-shell-escape

Enable the \write18{command} construct. The command can be any shell command. This construct is normally disallowed for security reasons.

-no-shell-escape

Disable the \write18{command} construct, even if it is enabled in the *texmf.cnf* file.

-src-specials

In *DVI* mode, insert source specials into the *DVI* file. This option is ignored in *PDF* mode.

-src-specials where

In *DVI* mode, insert source specials in certain placed of the *DVI* file. *where* is a comma-separated value list: *cr*, *display*, *hbox*, *math*, *par*, *parent*, or *vbox*. This option is ignored in *PDF* mode.

-translate-file tcxname

Use the *tcxname* translation table to set the mapping of input characters and re-mapping of output characters.

-default-translate-file tcxname

Like **-translate-file** except that a %& line can overrule this setting.

-version

Print version information and exit.

ENVIRONMENT

See the Kpathsea library documentation (e.g., the 'Path specifications' node) for precise details of how the environment variables are used. The **kpsewhich** utility can be used to query the values of the variables.

One caveat: In most $pdfT_EX$ formats, you cannot use ~ in a filename you give directly to $pdfT_EX$, because ~ is an active character, and hence is expanded, not taken as part of the filename. Other programs, such as Metafont, do not have this problem.

TEXMFOUTPUT

Normally, $pdfT_EX$ puts its output files in the current directory. If any output file cannot be opened there, it tries to open it in the directory specified in the environment variable TEXMFOUTPUT. There is no default value for that variable. For example, if you say *pdftex paper* and the current directory is not writable and TEXMFOUTPUT has the value */tmp*, $pdfT_EX$ attempts to create */tmp/paper.log* (and */tmp/paper.pdf*, if any output is produced.) TEXMFOUTPUT is also checked for input files, as T_EX often generates files that need to be subsequently read; for input, no suffixes (such as ".tex") are added by default, the input name is simply checked as given.

TEXINPUTS

Search path for *input* and *openin* files. This should start with ".", so that user files are found before system files. An empty path component will be replaced with the paths defined in the *texmf.cnf* file. For example, set TEXINPUTS to ".:/home/user/tex:" to prepend the current directory and "/home/user/tex" to the standard search path.

TEXFORMATS

Search path for format files.

TEXEDIT

Command template for switching to editor. The default, usually vi, is set when pdfT_EX is compiled.

TFMFONTS

Search path for font metric (.tfm) files.

SOURCE_DATE_EPOCH

If set, its value, taken to be in epoch-seconds, will be used for the timestamps in the PDF output, such as the CreationDate and ModDate keys. This is useful for making reproducible builds.

SOURCE_DATE_EPOCH_TEX_PRIMITIVES

If set to the value "1", the time-related T_EX primitives (\year, \month, \day, \time) are also initialized from the value of SOURCE_DATE_EPOCH. This is not recommended if there is any viable alternative.

 $pdfT_EX$ also has several primitives to support reproducible builds, which are preferable to setting these environment variables; see the main manual.

Many, many more environment variables may be consulted related to path searching. See the Kpathsea manual.

FILES

The location of the files mentioned below varies from system to system. Use the **kpsewhich** utility to find their locations.

pdftex.map

Font name mapping definitions.

- *.*tfm* Metric files for pdfT_EX's fonts.
- *.fmt Predigested pdfT_EX format (. fmt) files.

NOTES

Starting with version 1.40, pdfT_EX incorporates the e-T_EX extensions, and pdfeT_EX is just a copy of pdfT_EX. See **etex**(1). This manual page is not meant to be exhaustive. The complete documentation for this version of pdfT_EX can be found in the *pdf*T_EX *manual* and the info manual *Web2C: A TeX implementation*.

BUGS

This version of $pdfT_EX$ fails to trap arithmetic overflow when dimensions are added or subtracted. Cases where this occurs are rare, but when it does the generated *DVI* file will be invalid. Whether a generated *PDF* file would be usable is unknown.

AVAILABILITY

 $pdfT_EX$ is available for a large variety of machine architectures and operating systems. $pdfT_EX$ is part of all major T_EX distributions.

The pdfT_EX home page: http://www.pdftex.org.

pdfT_EX on CTAN: http://www.ctan.org/pkg/pdftex.

pdfT_EX mailing list for all discussion: http://lists.tug.org/pdftex.

SEE ALSO

The full $pdfT_EX$ manual can be accessed from the home page or CTAN page. Same for the Web2C, Kpathsea, and other manuals. Some related programs: epstopdf(1), etex(1), latex(1), luatex(1), mptopdf(1), tex(1), mf(1).

AUTHORS

The primary authors of pdfT_EX are Han The Thanh, Petr Sojka, Jiri Zlatuska, and Peter Breitenlohner (eT_EX).

 T_EX was designed by Donald E. Knuth, who implemented it using his WEB system for Pascal programs. It was ported to Unix at Stanford by Howard Trickey, and at Cornell by Pavel Curtis. The version now offered with the Unix T_EX distribution is that generated by the WEB to C system (**web2c**), originally written by Tomas Rokicki and Tim Morgan.

The encT_EX extensions were written by Petr Olsak.