# NAME

pdfetex, pdfeinitex, pdfevirtex – PDF output from e-TeX

# SYNOPSIS

pdfetex [options] [& format ] [ file | \ commands ]

# DESCRIPTION

Run the pdfeT<sub>E</sub>X typesetter on *file*, usually creating *file.pdf*. If the file argument has no extension, ".tex" will be appended to it. Instead of a filename, a set of pdfeT<sub>E</sub>X commands can be given, the first of which must start with a backslash. With a & *format* argument pdfeT<sub>E</sub>X uses a different set of precompiled commands, contained in *format.fint*; it is usually better to use the **-fmt** *format* option instead.

pdfeT<sub>E</sub>X is a version of e-T<sub>E</sub>X that can create PDF files as well as DVI files.

In DVI mode, pdfeT<sub>E</sub>X can be used as a complete replacement of the e-T<sub>E</sub>X engine.

The typical use of pdfeT<sub>E</sub>X is with a pregenerated formats for which PDF output has been enabled. The **pdfetex** command uses the equivalent of the plain e-T<sub>E</sub>X format, and the **pdfelatex** command uses the equivalent of the e-LAT<sub>E</sub>X format. To generate formats, use the **-ini** switch.

The **pdfeinitex** and **pdfevirtex** commands are  $pdfeT_EX$ 's analogues to the **einitex** and **evirtex** commands. In this installation, they are symbolic links to the **pdfetex** executable. These symbolic links may not exist at all.

In *PDF* mode, pdfeT<sub>E</sub>X can natively handle the *PDF*, *JPG*, *JBIG2*, and *PNG* graphics formats. pdfeT<sub>E</sub>X cannot include PostScript or Encapsulated PostScript (EPS) graphics files; first convert them to PDF using **epstopdf**(1). pdfeT<sub>E</sub>X's handling of its command-line arguments is similar to that of of the other T<sub>E</sub>X programs in the *web2c* implementation.

# **OPTIONS**

This version of pdfeT<sub>E</sub>X understands the following command line options.

# -draftmode

Sets  $\pdfdraftmode so pdfT_EX$  doesn't write a PDF and doesn't read any included images, thus speeding up execution.

- -enc Enable the encT<sub>E</sub>X extensions. This option is only effective in combination with
- -etex Enable the  $e-T_EX$  extensions. This option is only effective in combination with -ini. See etex(1).
- -ini. For documentation of the encT<sub>E</sub>X extensions see http://www.olsak.net/enctex.html. -file-line-error Print error messages in the form *file:line:error* which is similar to the way many compilers format them.

### -no-file-line-error

Disable printing error messages in the *file:line:error* style.

# -file-line-error-style

This is the old name of the **-file-line-error** option.

# -fmt format

Use *format* as the name of the format to be used, instead of the name by which  $pdfeT_{EX}$  was called or a %& line.

### -halt-on-error

Exit with an error code when an error is encountered during processing.

- -help Print help message and exit.
- -ini Start in *INI* mode, which is used to dump formats. The *INI* mode can be used for typesetting, but no format is preloaded, and basic initializations like setting catcodes may be required.

### -interaction mode

Sets the interaction mode. The mode can be either *batchmode*, *nonstopmode*, *scrollmode*, and *errorstopmode*. The meaning of these modes is the same as that of the corresponding \commands.

-ipc Send DVI or PDF output to a socket as well as the usual output file. Whether this option is available is the choice of the installer.

#### -ipc-start

As **-ipc**, and starts the server at the other end as well. Whether this option is available is the choice of the installer.

#### -jobname name

Use name for the job name, instead of deriving it from the name of the input file.

#### -kpathsea-debug bitmask

Sets path searching debugging flags according to the bitmask. See the *Kpathsea* manual for details.

### -mktex fmt

Enable mktex *fmt*, where *fmt* must be either *tex* or *tfm*.

-mltex Enable MLT<sub>E</sub>X extensions. Only effective in combination with -ini.

### -no-mktex *fmt*

Disable mktex *fmt*, where *fmt* must be either *tex* or *tfm*.

#### -output-comment string

In *DVI* mode, use *string* for the *DVI* file comment instead of the date. This option is ignored in *PDF* mode.

### -output-directory directory

*directory* instead of the current directory. Look up input files in *directory* first, the along the normal search path.

## -output-format format

Set the output format mode, where *format* must be either *pdf* or *dvi*. This also influences the set of graphics formats understood by  $pdfeT_{FX}$ .

#### -parse-first-line

If the first line of the main input file begins with %& parse it to look for a dump name or a **-translate-file** option.

# -no-parse-first-line

Disable parsing of the first line of the main input file.

### -progname name

Pretend to be program *name*. This affects both the format used and the search paths.

### -recorder

Enable the filename recorder. This leaves a trace of the files opened for input and output in a file with extension *.fls*.

#### -shell-escape

Enable the \write18{*command*} construct. The *command* can be any shell command. This construct is normally disallowed for security reasons.

### -no-shell-escape

Disable the \write18{command} construct, even if it is enabled in the *texmf.cnf* file.

#### -src-specials

In *DVI* mode, insert source specials into the *DVI* file. This option is ignored in *PDF* mode.

### -src-specials where

In *DVI* mode, insert source specials in certain placed of the *DVI* file. *where* is a comma-separated value list: *cr*, *display*, *hbox*, *math*, *par*, *parent*, or *vbox*. This option is ignored in *PDF* mode.

### -translate-file *tcxname*

Use the *tcxname* translation table to set the mapping of input characters and re-mapping of output characters.

## -default-translate-file tcxname

Like **-translate-file** except that a %& line can overrule this setting.

#### -version

Print version information and exit.

# **ENVIRONMENT**

See the Kpathsearch library documentation (the 'Path specifications' node) for precise details of how the environment variables are used. The **kpsewhich** utility can be used to query the values of the variables.

One caveat: In most pdfeT<sub>E</sub>X formats, you cannot use  $\tilde{}$  in a filename you give directly to pdfeT<sub>E</sub>X, because  $\tilde{}$  is an active character, and hence is expanded, not taken as part of the filename. Other programs, such as METAFONT, do not have this problem.

#### TEXMFOUTPUT

Normally, pdfeT<sub>E</sub>X puts its output files in the current directory. If any output file cannot be opened there, it tries to open it in the directory specified in the environment variable TEXMFOUTPUT. There is no default value for that variable. For example, if you say *pdfetex paper* and the current directory is not writable, if TEXMFOUTPUT has the value */tmp*, pdfeT<sub>E</sub>X attempts to create */tmp/paper.log* (and */tmp/paper.pdf*, if any output is produced.)

### TEXINPUTS

Search path for  $\input$  and  $\openin$  files. This should probably start with ".", so that user files are found before system files. An empty path component will be replaced with the paths defined in the *texmf.cnf* file. For example, set TEXINPUTS to ".:/home/usr/tex:" to prepend the current directory and "/home/user/tex" to the standard search path.

## TEXFORMATS

Search path for format files.

## TEXPOOL

search path for **pdfetex** internal strings.

## TEXEDIT

Command template for switching to editor. The default, usually vi, is set when  $pdfeT_{EX}$  is compiled.

## TFMFONTS

Search path for font metric (.*tfm*) files.

# FILES

The location of the files mentioned below varies from system to system. Use the **kpsewhich** utility to find their locations.

## pdfetex.pool

Text file containing pdfeT<sub>E</sub>X's internal strings.

## pdftex.map

Filename mapping definitions.

\*.*tfm* Metric files for pdfeT<sub>E</sub>X's fonts.

\*.*fmt* Predigested pdfeT<sub>E</sub>X format (. fmt) files.

# NOTES

Starting with version 1.40, pdfT<sub>E</sub>X incorporates the e-T<sub>E</sub>X extensions, and pdfeT<sub>E</sub>X is just a copy of pdfT<sub>E</sub>X. See **pdftex**(1). This manual page is not meant to be exhaustive. The complete documentation for this version of pdfeT<sub>E</sub>X can be found in the *pdf*T<sub>E</sub>X *manual* and the info manual *Web2C: A TeX implementation*.

# BUGS

This version of  $pdfeT_EX$  implements a number of optional extensions. In fact, many of these extensions conflict to a greater or lesser extent with the definition of  $pdfeT_EX$ . When such extensions are enabled, the banner printed when  $pdfeT_EX$  starts is changed to print **pdfeTeXk** instead of **pdfeTeX**.

This version of pdfeT<sub>E</sub>X fails to trap arithmetic overflow when dimensions are added or subtracted. Cases where this occurs are rare, but when it does the generated DVI file will be invalid. Whether a generated PDF file would be usable is unknown.

# AVAILABILITY

 $pdfeT_{EX}$  is available for a large variety of machine architectures and operation systems.  $pdfeT_{EX}$  is part of all major  $T_{EX}$  distributions.

Information on how to get  $pdfeT_EX$  and related information is available at the **http://www.pdf-tex.org**  $pdfT_EX$  website.

The following pdfT<sub>E</sub>X related mailing list is available: **pdftex@tug.org**. This is a mailman list; to subscribe send a message containing *subscribe* to **pdftex-request@tug.org**. More about the list can be found at the **http://tug.org/mailman/listinfo/pdftex** *mailing list* website.

# **SEE ALSO**

etex(1), mf(1), pdftex(1), tex(1).

# AUTHORS

The primary authors of pdfeT<sub>E</sub>X are Han The Thanh, Petr Sojka, Jiri Zlatuska, and Peter Breitenlohner (eT<sub>E</sub>X).

 $T_EX$  was designed by Donald E. Knuth, who implemented it using his system for Pascal programs. It was ported to Unix at Stanford by Howard Trickey, and at Cornell by Pavel Curtis. The version now offered with the Unix  $T_EX$  distribution is that generated by the to C system (**web2c**), originally written by Tomas Rokicki and Tim Morgan.

The encT<sub>E</sub>X extensions were written by Petr Olsak.