

The `zref` package

Heiko Oberdiek

<oberdiek@uni-freiburg.de>

2007/05/28 v2.1

Abstract

Package `zref` tries to get rid of the restriction in L^AT_EX's reference system that only two properties are supported. The package implements an extensible referencing system, where properties are handled in a more flexible way. It offers an interface for macro programmers for the access to the system and some applications that uses the new reference scheme.

Contents

1	Introduction	3
1.1	Standard L ^A T _E X behaviour	3
1.2	Basic idea	3
1.3	Interfaces	4
2	Interface for programmers	4
2.1	Entities	4
2.2	Property list	4
2.3	Property	5
2.4	Reference generation	5
2.5	Data extraction	6
2.6	Setup	7
2.7	Declared properties	7
2.8	Wrapper for advanced situations	7
2.9	Counter for unique names	8
3	User interface	8
3.1	Module user	8
3.2	Module <code>abspage</code>	9
3.3	Module <code>lastpage</code>	9
3.4	Module <code>totpages</code>	9
3.5	Module <code>perpage</code>	9
3.6	Module <code>counter</code>	10
3.7	Module <code>titleref</code>	10
3.8	Module <code>savepos</code>	11
3.9	Module <code>dotfill</code>	11
3.10	Module <code>xr</code>	12
4	ToDo	12
5	Example	12

6 Implementation	15
6.1 Package <code>zref</code>	15
6.1.1 Identification	15
6.1.2 Load basic module	15
6.1.3 Process options	15
6.2 Module base	15
6.2.1 Prefixes	15
6.2.2 Identification	16
6.2.3 Utilities	16
6.2.4 Check for ε - <code>TeX</code>	16
6.2.5 Auxiliary file stuff	17
6.2.6 Property lists	17
6.2.7 Properties	19
6.2.8 Reference generation	20
6.2.9 Reference querying and extracting	21
6.2.10 Compatibility with <code>babel</code>	23
6.2.11 Unique counter support	23
6.2.12 Setup	24
6.3 Module user	24
6.4 Module <code>abspage</code>	25
6.5 Module <code>counter</code>	26
6.6 Module <code>lastpage</code>	26
6.7 Module <code>totpages</code>	26
6.8 Module <code>perpage</code>	27
6.9 Module <code>titleref</code>	29
6.9.1 Implementation	29
6.9.2 User interface	30
6.9.3 Patches for section and caption commands	31
6.10 Module <code>xr</code>	33
6.11 Module <code>hyperref</code>	37
6.12 Module <code>savepos</code>	37
6.12.1 Identification	37
6.12.2 Availability	38
6.12.3 Setup	38
6.12.4 User macros	38
6.13 Module <code>dotfill</code>	39
7 Installation	40
7.1 Download	40
7.2 Bundle installation	40
7.3 Package installation	40
7.4 Refresh file name databases	41
7.5 Some details for the interested	41
8 References	42
9 History	42
[2006/02/20 v1.0]	42
[2006/05/03 v1.1]	42
[2006/05/25 v1.2]	42
[2006/09/08 v1.3]	42
[2007/01/23 v1.4]	42
[2007/02/18 v1.5]	42
[2007/04/06 v1.6]	43
[2007/04/17 v1.7]	43
[2007/04/22 v1.8]	43
[2007/05/02 v1.9]	43
[2007/05/06 v2.0]	43

1 Introduction

Standard L^AT_EX's reference system with \label, \ref, and \pageref supports two properties, the appearance of the counter that is last incremented by \refstepcounter and the page with the \label command.

Unhappily L^AT_EX does not provide an interface for adding another properties. Packages such as hyperref, nameref, or titleref are forced to use ugly hacks to extend the reference system. These ugly hacks are one of the causes for hyperref's difficulty regarding compatibility with other packages.

1.1 Standard L^AT_EX behaviour

References are created by the \label command:

```
\chapter{Second chapter}
\section{First section on page 7} % section 2.1
\label{myref}
```

Now L^AT_EX records the section number 2.1 and the page 7 in the reference. Internally the reference is a list with two entries:

```
\r@myref → {2.1}{7}
```

The length of the list is fixed in the L^AT_EX kernel. An interface for adding new properties is missing.

There are several tries to add new properties:

hyperref uses a list of five properties instead of the standard list with two entries.
This causes many compatibility problems with L^AT_EX and other packages.

titleref stores its title data into the first entry in the list. L^AT_EX is happy because it does only see its list with two entries. The situation becomes more difficult, if more properties are added this way. Then the macros form a nested structure inside the first reference argument for the label. Expandable extractions will then become painful.

1.2 Basic idea

Some time ago Morten Høgholm sent me an experimental cross referencing mechanism as “expl3” code. His idea is:

```
\g_xref_mylabel plist →
\xref_dance_key{salsa}\xref_name_key{Morten}...
```

The entries have the following format:

```
\xref_{your key}_key{(some text)}
```

This approach is much more flexible:

- New properties can easily be added, just use a new key.
- The length of the list is not fixed. A reference can use a subset of the keys.
- The order of the entries does not matter.

Unhappily I am not familiar with the experimental code for L^AT_EX3 that will need some time before its first release. Thus I have implemented it as L^AT_EX 2_ε package without disturbing the existing L^AT_EX reference system.

1.3 Interfaces

The package provides a generic *interface for programmers*. Commands of this interface are prefixed by `\zref@`.

Option `user` enables the *user interface*. Here the commands are prefixed by `\z` to avoid name clashes with existing macros.

Then the packages provides some *modules*. They are applications for the reference system and can also be considered as examples how to use the reference system.

The modules can be loaded as packages. The package name is prefixed with `zref-`, for example:

```
\RequirePackage{zref-abspage}
```

This is the preferred way if the package is loaded from within other packages to avoid option clashes.

As alternative package `zref` can be used and the modules are given as options:

```
\usepackage[perpage,user]{zref}
```

2 Interface for programmers

The user interface is described in the next section 3.

2.1 Entities

Reference. Internally a reference is a list of key value pairs:

```
\Z@R@myref → \default{2.1}\page{7}
```

The generic format of a entry is:

```
\Z@R@⟨refname⟩ → \⟨propname⟩{⟨value⟩}
```

`⟨refname⟩` is the name that denoted references (the name used in `\label` and `\ref`). `⟨propname⟩` is the name of the property or key. The property key macro is never executed, it is used in parameter text matching only.

Property. Because the name of a property is used in a macro name that must survive the `.aux` file, the name is restricted to letters and ‘@’.

Property list. Often references are used for special purposes. Thus it saves memory if just the properties are used in this reference that are necessary for its purpose.

Therefore this package uses the concept of *property lists*. A property list is a set of properties. The set of properties that is used by the default `\label` command is the *main property list*.

2.2 Property list

^{exp} means that the implementation of the marked macro is expandable.

```
\zref@newlist {⟨listname⟩}
```

Declares a new empty property list.

```
\zref@addprop {⟨listname⟩} {⟨propname⟩}
```

Adds the property `⟨propname⟩` to the property list `⟨listname⟩`. The property and list must exist.

```
\zref@listexists {\⟨listname⟩} {\⟨then⟩}
```

Executes *⟨then⟩* if the property list *⟨listname⟩* exists or raise an error otherwise.

```
\zref@iflistundefinedexp {\⟨listname⟩} {\⟨then⟩} {\⟨else⟩}
```

Executes *⟨then⟩* if the list exists or *⟨else⟩* otherwise.

```
\zref@iflistcontainsprop {\⟨listname⟩} {\⟨propname⟩} {\⟨then⟩} {\⟨else⟩}
```

Executes *⟨then⟩* if the property *⟨propname⟩* is part of property list *⟨listname⟩* or otherwise it runs the *⟨else⟩* part.

2.3 Property

```
\zref@newprop* {\⟨propname⟩} [⟨default⟩] {\⟨value⟩}
```

This command declares and configures a new property with name *⟨propname⟩*.

In case of unknown references or the property does not exist in the reference, the *⟨default⟩* is used as value. If it is not specified here, a global default is used, see `\zref@setdefault`.

The correct values of some properties are not known immediately but at page shipout time. Prominent example is the page number. These properties are declared with the star form of the command.

```
\zref@setcurrent {\⟨propname⟩} {\⟨value⟩}
```

This sets the current value of the property *⟨propname⟩*. It is a generalization of setting L^AT_EX's `\currentlabel`.

```
\zref@getcurrent {\⟨propname⟩} {\⟨value⟩}
```

This returns the current value of the property *⟨propname⟩*. The value may not be correct, especially if the property is bound to a page (start form of `\zref@newprop`) and the right value is only known at shipout time (e.g. property 'page').

```
\zref@propexists {\⟨propname⟩} {\⟨then⟩}
```

Calls *⟨then⟩* if the property *⟨propname⟩* is available or generates an error message otherwise.

```
\zref@ifpropundefinedexp {\⟨propname⟩} {\⟨then⟩} {\⟨else⟩}
```

Calls *⟨then⟩* or *⟨else⟩* depending on the existence of property *⟨propname⟩*.

2.4 Reference generation

```
\zref@label {\⟨refname⟩}
```

This works similar to `\label`. The reference *⟨refname⟩* is created and put into the `.aux` file with the properties of the main property list.

```
\zref@labelbylist {\langle refname\rangle} {\langle listname\rangle}
```

Same as `\zref@label` except that the properties are taken from the specified property list `\listname`.

```
\zref@labelbyprops {\langle refname\rangle} {\langle propnameA\rangle,\langle propnameB\rangle,\dots}
```

Same as `\zref@label` except that these properties are used that are given as comma separated list in the second argument.

```
\zref@newlabel {\langle refname\rangle} {\dots}
```

This is the macro that is used in the `.aux` file. It is basically the same as `\newlabel` apart from the format of the data in the second argument.

2.5 Data extraction

```
\zref@extractdefaultexp {\langle refname\rangle} {\langle propname\rangle} {\langle default\rangle}
```

This is the basic command that references the value of a property `\propname` for the reference `\refname`. In case of errors such as undefined reference the `\default` is used instead.

```
\zref@extractexp {\langle refname\rangle} {\langle propname\rangle}
```

The command is an abbreviation for `\zref@extractdefault`. As default the default of the property is taken, otherwise the global default.

Example for page references:

```
LATEX: \pageref{foobar}  
zref: \zref@extract{foobar}{page}
```

Both `\zref@extract` and `\zref@extractdefault` are expandable. That means, these macros can directly be used in expandable calculations, see the example file. On the other side, babel's shorthands are not supported, there are no warnings in case of undefined references.

If an user interface doesn't need expandable macros then it can use `\zref@refused` and `\zref@wrapper@babel` for its user macros.

```
\zref@refused {\langle refname\rangle}
```

This command is not expandable. It causes the warnings if the reference `\refname` is not defined. Use the `\zref@extract` commands inside expandable contexts and mark their use outside by `\zref@refused`, see the example file.

```
\zref@ifrefundefinedexp {\langle refname\rangle} {\langle then\rangle} {\langle else\rangle}
```

A possibility to check whether a reference exists.

```
\zref@ifrefcontainspropexp {\langle refname\rangle} {\langle propname\rangle} {\langle then\rangle} {\langle else\rangle}
```

Test whether a reference provides a property.

2.6 Setup

```
\zref@default
```

Holds the global default for unknown values.

```
\zref@setdefault {\langle value \rangle}
```

Sets the global default for unknown values. The global default is used, if a property does not specify an own default and the value for a property cannot be extracted. This can happen if the reference is unknown or the reference does not have the property.

```
\zref@setmainlist {\langle value \rangle}
```

Sets the name of the main property list. The package sets and uses `main`.

2.7 Declared properties

Modul	Property	Property list	Default
	default	main	<empty>
	page	main	<empty>
abspage, totpages	abspage	main	0
perpage	pagevalue	perpage	0
	page	perpage	<empty>
	abspage	perpage	0
counter	counter	main	<empty>
titleref	title	main	<empty>
savepos	posx	savepos	0
	posy	savepos	0
hyperref	anchor	main	<empty>
	url		<empty>
xr	url		<empty>

2.8 Wrapper for advanced situations

```
\zref@wrapper@babel {...} {\langle name \rangle}
```

This macro helps to add shorthand support. The second argument is protected, then the code of the first argument is called with the protected name appended. Examples are in the sources.

```
\zref@wrapper@immediate {...}
```

There are situations where a label must be written instantly to the `.aux` file, for example after the last page. If the `\label` command is put inside this wrapper, immediate writing is enabled. See the implementation for option `lastpage`.

```
\zref@wrapper@unexpanded {...}
```

Assuming someone wants to extract a value for property `bar` and store the result in a macro `\foo` without traces of the expanding macros and without expanding the value. This (theoretical?) problem can be solved by this wrapper:

```
\edef\foo{%
  \zref@wrapper@unexpanded{%
    \zref@extract{someref}{bar}%
  }%
}
```

The `\edef` forces the expansion of `\zref@extract`, but the extraction of the value is prevented by the wrapper that uses ε - \TeX ' `\unexpanded` for this purpose.

2.9 Counter for unique names

Some modules (`titleref` and `dotfillmin`) need unique names for automatically generated label names.

`\zref@require@unique`

This command creates the unique counter `zref@unique` if the counter does not already exist.

`\thezref@unique`

This command is used to generate unique label names.

3 User interface

3.1 Module user

The user interface for this package and its modules is enabled by `zref`'s package option `user` or package `zref-user`. The names of user commands are prefixed by `z` in order to avoid name clashes with existing macros of the same functionality. Thus the package does not disturb the traditional reference scheme, both can be used together.

The syntax descriptions contain the following markers that are intended as hints for programmers:

- `babel` Babel shorthands are allowed.
- `robust` Robust macro.
- `exp` Expandable version:
 - robust, unless the extracted values are fragile,
 - no babel shorthand support.

The basic user interface of the package without modules are commands that mimic the standard \LaTeX behaviour of `\label`, `\ref`, and `\pageref`:

`\zlabel {\langle refname \rangle}^{\text{babel}}`

Similar to `\label`. It generates a label with name `\langle refname \rangle` in the new reference scheme.

`\zref [{\langle propname \rangle}] {\langle refname \rangle}^{\text{babel}}`

Without optional argument similar to `\ref`, it returns the default reference property. This property is named `default`:

$$\zref{x} \equiv \zref[\text{default}]{x}$$

```
\zpageref {\<refname>}babel
```

Convenience macro, similar to `\pageref`.

```
\zpageref{x} ≡ \zref[page]{x}
```

```
\zrefused {\<refname>}babel
```

Some of the user commands in the modules are expandable. The use of such commands do not cause any undefined reference warnings, because inside of expandable contexts this is not possible. However, if there is a place outside of expandable contexts, `\refused` is strongly recommended. The reference `<refname>` is marked as used, undefined ones will generate warnings.

3.2 Module `abspage`

With the help of package `atbegshi` a new counter `abspage` with absolute page numbers is provided. Also a new property `abspage` is defined and added to the main property list. Thus you can reference the absolute page number:

```
Section \zref{foo} is on page \zpageref{foo}.  
This is page \zref[abspage]{foo} of \zref[abspage]{LastPage}.
```

The example also makes use of option `lastpage`.

3.3 Module `lastpage`

Provides the functionality of package `lastpage` [3] in the new reference scheme. The label `LastPage` is put at the end of the document. You can refer the last page number with:

```
\zpageref{LastPage}
```

3.4 Module `totpages`

For the total number of pages of a document you need to know the absolute page number of the last page. Both options `abspage` and `lastpage` are necessary and automatically enabled.

```
\ztotpagesexp
```

Prints the total number of pages or 0 if this number is not yet known. This command can also be used in calculations or counter assignments.

3.5 Module `perpage`

With `\addtoreset` or `\numberwithin` a counter can be reset if another counter is incremented. This does not work well if the other counter is the page counter. The page counter is incremented in the output routine that is often called asynchronous somewhere on the next page. A reference mechanism costs at least two L^AT_EX runs, but ensures correct page counter values.

```
\zmakeperpage [\<reset>] {\<counter>}
```

At the start of a new page counter `<counter>` starts counting with value `<reset>` (default is 1). The macro has the same syntax and semantics as `\MakePerPage` of package `perpage` [5]. Also `perpage` of package `footmisc` [1] can easily be simulated by

```
\zmakeperpage{footnote} % \usepackage[perpage]{footmisc}
```

If footnote symbols are used, some people dislike the first symbol †. It can easily be skipped:

```
\zmakeperpage[2]{footnote}
```

```
\thezpage  
counter zpage
```

If the formatted counter value of the counter that is reset at a new page contains the page value, then you can use `\thezpage`, the page number of the current page. Or counter `zpage` can be used, if the page number should be formatted differently from the current page number. Example:

```
\newcounter{foobar}  
\zmakeperpage{foobar}  
\renewcommand*{\thefoobar}{\thezpage-\arabic{foobar}}  
% or  
\renewcommand*{\thefoobar}{\roman{zpage}-\arabic{foobar}}
```

```
\zunmakeperpage {\langle counter\rangle}
```

The reset mechanism for this counter is deactivated.

3.6 Module `counter`

This option just add the property `counter` to the main property list. The property stores the counter name, that was responsible for the reference. This is the property `hyperref`'s `\autoref` feature uses. Thus this property `counter` may be useful for a reimplementation of the autoref feature, see the section 4 with the todo list.

3.7 Module `titleref`

This option makes section and caption titles available to the reference system similar to packages `titleref` or `nameref`.

```
\ztitleref {\langle refname\rangle}^babel
```

Print the section or caption title of reference `\langle refname\rangle`, similar to `\nameref` or `\titleref`.

```
\ztitlerefsetup {key1=value1, key2=value2, ...}
```

This command allows to configure the behaviour of modul `titleref`. The following keys are available:

`title=⟨value⟩`

Sets the current title.

`stripperiod=true|false`

Follow package `nameref` that removes a last period. Default: `true`.

`expand=true|false`

Package `\titleref` expands the title first. This way garbage and dangerous commands can be removed, e.g. `\label`, `\index`.... See implementation section for more details. Default is `false`.

`cleanup={...}`

Hook to add own cleanup code, if method `expand` is used. See implementation section for more details.

3.8 Module `savepos`

This option supports a feature that pdf_TE_X provides (and Xe_TE_X). pdf_TE_X is able to tell the current position on the page. The page position is not instantly known. First the page must be constructed by _TE_X's asynchronous output routine. Thus the time where the position is known is the page shipout time. Thus a reference system where the information is recorded in the first run and made available for use in the second run comes in handy.

```
\zsavepos {\<refname>}
```

It generates a reference with name *<refname>* to the location where the command is executed.

```
\zposxexp {\<refname>}  
\zposyexp {\<refname>}
```

Get the position as number. Unit is sp. Horizontal positions by \zposx increase from left to right. Vertical positions by \zposy from bottom to top.

Do not rely on absolute page numbers. Because of problems with the origin the numbers may differ in DVI or PDF mode of pdf_TE_X. Therefore work with relative values by comparisons.

Both \zposx and \zposy are expandable and can be used inside calculations (\setcounter, \addtocounter, package calc, \numexpr). However this property prevents from notifying L_AT_EX that the reference is actually used (the notifying is not expandable). Therefore you should mark the reference as used by \zrefused.

This module uses pdf_TE_X's \pdfsavepos, \pdflastxpos, and \pdflastypos. They are available in PDF mode and since version 1.40.0 also in DVI mode.

3.9 Module `dotfill`

```
\zdotfill
```

This package provides the command \zdotfill that works similar to \dotfill, but can be configured. Especially it suppresses the dots if a minimum number of dots cannot be set.

```
\zdotfillsetup {key1=value1, key2=value2, ...}
```

This command allows to configure the behaviour of \zdotfill. The following keys are available:

`min=<count value>`

If the actual number of dots are smaller than *<count value>*, then the dots are suppressed. Default: 2.

`unit=<dimen value>`

The width of a dot unit is given by *<dimen value>*. Default: 0.44em (same as the unit in \dotfill).

`dot=<value>`

The dot itself is given by *<value>*. Default: . (dot, same as the dot in \dotfill).

3.10 Module xr

This package provides the functionality of package `xr`, see [8]. It also supports the syntax of `xr-hyper`.

```
\zexternaldocument* [<prefix>]babel {<external document>} [<url>]
```

See `\externaldocument` for a description of this option. The standard reference scheme and the scheme of this package use different name spaces for reference names. If the external document uses both systems. Then one import statement would put the names in one namespace and probably causing problems with multiple references of the same name. Thus the star form only looks for `\newlabel` in the `.aux` files, whereas without star only `\zref@newlabels` are used.

In the star form it tries to detect labels from `hyperref`, `titleref`, and `ntheorem`. If such an extended property from the packages before cannot be found or are empty, they are not included in the imported reference.

Warnings are given if a reference name is already in use and the item is ignored. Unknown properties will automatically be declared.

If the external references contain `anchor` properties, then we need also a url to be able to address the external file. As default the filename is taken with a default extension.

```
\zxrsetup {key1=value1, key2=value2, ...}
```

Currently the key `ext` is defined, this sets the url default extension.

```
\zref@xr@ext
```

If the `<url>` is not specified in `\zref@externaldocument`, then the url will be constructed with the file name and this macro as extension. `\XR@ext` is used if `hyperref` is loaded, otherwise `pdf`.

4 ToDo

Among other things the following issues are left for future work:

- The user land macros are not checked for robustness yet. They can be fragile. If this happens, use `\protect` until a later version of this package. The `\protect` will not disturb, if the protected macro become robust in the future.
- Other applications: `autoref`, `hyperref`, ...

5 Example

```
1 <*example>
2 \documentclass{book}
3
4 \usepackage[ngerman]{babel}%
5
6 \usepackage[savepos,totpages,titleref,dotfill,counter,user]{zref}
7
```

Chapters are wrapped inside `\ChapterStart` and `\ChapterStop`. The first argument `#1` of `\ChapterStart` is used to form a label id `chap:#1`. At the end of the chapter another label is set by `\zref@wrapper@immediate`, because otherwise

at the end of document a deferred write would not be written, because there is no page for shipout.

Also this example shows how chapter titles can be recorded. A new property `chapttitle` is declared and added to the main property list. In `\ChapterStart` the current value of the property is updated.

```

8 \makeatletter
9 \zref@newprop{chapttitle}{}
10 \zref@addprop{main}{chapttitle}
11
12 \newcommand*{\ChapterStart}[2]{%
13   \cleardoublepage
14   \def\current@chapid{\#1}%
15   \zref@setcurrent{chapttitle}{\#2}%
16   \chapter{\#2}%
17   \zlabel{chap:\#1}%
18 }
19 \newcommand*{\ChapterStop}{%
20   \cleardoublepage
21   \zref@wrapper@immediate{%
22     \zref@labelbyprops{chapend:\current@chapid}{abspage}%
23   }%
24 }
```

`\ChapterPages` calculates and returns the number of pages of the referenced chapter.

```

25 \newcommand*{\ChapterPages}[1]{%
26   \zrefused{chap:\#1}%
27   \zrefused{chapend:\#1}%
28   \number\numexpr
29     \zref@extract{chapend:\#1}{abspage}%
30   - \zref@extract{chap:\#1}{abspage}%
31   +1\relax
32 }
33 \makeatother
34 \begin{document}
```

As exception we use `\makeatletter` here, because this is just an example file that also should show some of programmer's interface.

```

35 \makeatletter
36
37 \frontmatter
38 \zlabel{documentstart}
39
40 \begin{itemize}
41   \item
42     The frontmatter part has
43     \number\numexpr\zref@extract{chap:first}{abspage}-1\relax~pages.
44   \item
45     Chapter \zref{chap:first} has \ChapterPages{first} page(s).
46   \item
47     Section \zref{hello} is on the
48     \ifcase\numexpr
49       \zref@extractdefault{hello}{page}{0}%
50     - \zref@extractdefault{chap:first}{page}{0}%
51     +1\relax
52     ??\or first\or second\or third\or forth\fi
53     ~page inside its chapter.
54   \item
55     The document has
56     \zref[abspage]{LastPage} pages.
57     This number is \ifodd\ztotpages odd\else even\fi.
58   \item
59     The last page is labeled with \zpageref{LastPage}.

```

```

60 \item
61   The title of chapter \zref{chap:next} is ``\zref[chaptitle]{chap:next}''.
62 \end{itemize}
63
64 \tableofcontents
65
66 \mainmatter
67 \ChapterStart{first}{First chapter}
68

```

The user level commands should protect babel shorthands where possible. On the other side, expandable extracting macros are useful in calculations, see above the examples with `\numexpr`.

```

69 \section{Test}
70 \zlabel{a"o}
71 Section \zref{a"o} on page
72 \zref@wrapper@babel\zref@extract{a"o}{page}.
73
74 Text.
75 \newpage
76
77 \section{Hello World}
78 \zlabel{hello}
79
80 \ChapterStop
81
82 \ChapterStart{next}{Next chapter with \emph{umlauts}: "a"o"u"s}
83

```

Here an example follows that makes use of pdf_TE_X's “`savepos`” feature. The position on the page is not known before the page is constructed and shipped out. Therefore the position ist stored in references and are available for calculations in the next L^AT_EX compile run.

```

84 The width of the first column is
85   \the\dimexpr \zposx{secondcol}sp - \zposx{firstcol}sp\relax,\\
86 the height difference of the two baselines is
87   \the\dimexpr \zposy{firstcol}sp - \zposy{secondline}sp\relax:\\
88 \begin{tabular}{ll}
89   \zsavepos{firstcol}Hello\zsavepos{secondcol}World\\
90   \zsavepos{secondline}Second line&foobar\\
91 \end{tabular}
92

```

With `\zrefused` L^AT_EX is notified, if the references are not yet available and L^AT_EX can generate the rerun hint.

```

93 \zrefused{firstcol}
94 \zrefused{secondcol}
95 \zrefused{secondline}
96
97 \ChapterStop

Test for module \dotfill.
98 \ChapterStart{dotfill}{Test for dotfill feature}
99 \newcommand*\dftest[1]{%
100   #1&
101   [\makebox[{#1}]{\dotfill}]&
102   [\makebox[{#1}]{\zdotfill}]\\
103 }
104 \begin{tabular}{rll}
105 & [\verb|\dotfill|] & [\verb|\zdotfill|]\\
106 \dftest{0.43em}
107 \dftest{0.44em}
108 \dftest{0.45em}
109 \dftest{0.87em}
110 \dftest{0.88em}

```

```

111 \dftest{0.89em}
112 \dftest{1.31em}
113 \dftest{1.32em}
114 \dftest{1.33em}
115 \end{tabular}
116 \ChapterStop
117 \end{document}
118 </example>

```

6 Implementation

6.1 Package `zref`

6.1.1 Identification

```

119 <*package>
120 \NeedsTeXFormat{LaTeX2e}
121 \ProvidesPackage{zref}
122 [2007/05/28 v2.1 New reference scheme for LaTeX2e (HO)]%

```

6.1.2 Load basic module

```
123 \RequirePackage{zref-base}[2007/05/28]
```

Abort package loading if `zref-base` could not be loaded successfully.

```
124 \@ifundefined{ZREF@baseok}{\endinput}{}%
```

6.1.3 Process options

Known modules are loaded and the release date is checked.

```

125 \def\ZREF@temp#1{%
126   \DeclareOption{#1}{%
127     \AtEndOfPackage{%
128       \RequirePackage{zref-#1}[2007/05/28]%
129     }%
130   }%
131 }
132 \ZREF@temp{abspage}
133 \ZREF@temp{counter}
134 \ZREF@temp{dotfill}
135 \ZREF@temp{hyperref}
136 \ZREF@temp{lastpage}
137 \ZREF@temp{perpage}
138 \ZREF@temp{savepos}
139 \ZREF@temp{titleref}
140 \ZREF@temp{totpages}
141 \ZREF@temp{user}
142 \ZREF@temp{xr}
143 \ProcessOptions\relax
144 </package>

```

6.2 Module base

6.2.1 Prefixes

This package uses the following prefixes for macro names:

`\zref@`: Macros of the programmer's interface.

`\ZREF@`: Internal macros.

`\Z@L@listname`: The properties of the list `<i>listname.`

`\Z@D@propname`: The default value for property `<i>propname.`

`\Z@E@propname`: Extract function for property `<i>propname.`

\Z@X@*propname*: Information whether a property value for property *<propname>* is expanded immediately or at shipout time.

\Z@C@*propname*: Current value of the property *<propname>*.

\Z@R@*labelname*: Data for reference *<labelname>*.

\ZREF@org@: Original versions of patched commands.

\z: For macros in user land, defined if option `user` is set.

The following family names are used for keys defined according to the `keyval` package:

ZREF@TR: Setup for `titleref`.

6.2.2 Identification

```
145 <*base>
146 \NeedsTeXFormat{LaTeX2e}
147 \ProvidesPackage{zref-base}%
148 [2007/05/28 v2.1 Module base for zref (HO)]%
```

6.2.3 Utilities

\ZREF@name: Several times the package name is used, thus we store it in \ZREF@name.

```
149 \def\ZREF@name{zref}
```

\ZREF@ErrorNoLine: An error message for this package without line information is generated by \ZREF@ErrorNoLine

```
150 \def\ZREF@ErrorNoLine#1#2{%
151   \begingroup
152   \let\on@line\@empty
153   \PackageError\ZREF@name{#1}{#2}%
154   \endgroup
155 }
```

\ZREF@UpdatePdfTeX: \ZREF@UpdatePdfTeX is used as help message text in error messages.

```
156 \def\ZREF@UpdatePdfTeX{Update pdfTeX.}
```

\ifZREF@found: The following switch is usded in list processing.

```
157 \newif\ifZREF@found
```

\ZREF@patch: Macro \ZREF@patch first checks the existence of the command and safes it.

```
158 \def\ZREF@patch#1{%
159   \begingroup\expandafter\expandafter\expandafter\endgroup
160   \expandafter\ifx\csname #1\endcsname\relax
161   \expandafter\@gobble
162   \else
163   \expandafter\let\csname ZREF@org@#1\expandafter\endcsname
164   \csname #1\endcsname
165   \expandafter\@firstofone
166   \fi
167 }
```

6.2.4 Check for ε -TeX

The use of ε -TeX should be standard nowadays for L^AT_EX. We test for ε -TeX in order to use its features later.

```
168 \begingroup
169 \@ifundefined{eTeXversion}{%
170   \ZREF@ErrorNoLine{%
171     Missing support for eTeX; package is abandoned%}}
```

```

172      }{%
173          Use a TeX compiler that support eTeX and enable eTeX %
174          in the format.%
175      }%
176      \endgroup
177      \endinput
178  }{%
179 \endgroup

180 \RequirePackage{etexcmds}[2007/09/09]
181 \ifeftex@unexpanded
182 \else
183     \ZREF@ErrorNoLine{%
184         Missing e-TeX's \string\unexpanded.\MessageBreak
185         Add \string\RequirePackage\string{etexcmds\string} before %
186         \string\documentclass%
187     }{%
188         Probably you are using some package (e.g. ConTeXt) that %
189         redefines \string\unexpanded%
190     }%
191     \expandafter\endinput
192 \fi

```

6.2.5 Auxiliary file stuff

We are using some commands in the `.aux` files. However sometimes these auxiliary files are interpreted by L^AT_EX processes that haven't loaded this package (e.g. package `xr`). Therefore we provide dummy definitions.

```

193 \RequirePackage{auxhook}
194 \AddLineBeginAux{%
195     \string\providetoggle\string\zref@newlabel[2]{}}%
196 }

```

`\zref@newlabel` For the implementation of `\zref@newlabel` we call the same internal macro `@newl@bel` that is used in `\newlabel`. Thus we have for free:

- `\ZCR@labelname` is defined.
- L^AT_EX's check for multiple references.
- L^AT_EX's check for changed references.

```

197 \def\zref@newlabel{%
198     \@newl@bel{ZCR}%
199 }

```

6.2.6 Property lists

`\zref@newlist` Property lists are stored as list of property names enclosed in curly braces. `\zref@newlist` creates a new list as empty list. Assignments to property lists are global.

```

200 \def\zref@newlist#1{%
201     \zref@iflistundefined{#1}{%
202         \@ifdefinable{Z@L@#1}{%
203             \global\expandafter\let\csname Z@L@#1\endcsname\empty
204             \PackageInfo{\zref}{New property list: #1}%
205         }%
206     }{%
207         \PackageError{\ZREF@name}{%
208             Property list '#1' already exists}%
209     }\@ehc
210 }%
211 }

```

```

\zref@iflistundefined \zref@iflistundefined checks the existence of the property list #1. If the property list is present, then #2 is executed and #3 otherwise.
212 \def\zref@iflistundefined#1{%
213   \expandafter\ifx\csname Z@L@#1\endcsname\relax
214     \expandafter\@firstoftwo
215   \else
216     \expandafter\@secondoftwo
217   \fi
218 }

\zref@listexists \zref@listexists only executes #2 if the property list #1 exists and raises an error message otherwise.
219 \def\zref@listexists#1{%
220   \zref@iflistundefined{#1}{%
221     \PackageError{\ZREF@name}{%
222       Property list '#1' does not exist}%
223   }{\@ehc
224 }
225 }

\zref@listcontainsprop \zref@listcontainsprop checks, whether a property #2 is already present in a property list #1.
226 \def\zref@listcontainsprop#1{%
227   \expandafter\ZREF@listcontainsprop\csname Z@L@#1\endcsname
228 }
229 \def\ZREF@listcontainsprop#1#2{%
230   \begingroup
231     \ZREF@foundfalse
232     \edef\y{#2}%
233     \ctfor{x:=#1}\do{%
234       \edef\x{\x}%
235       \ifx\x\y
236         \ZREF@foundtrue
237       \fi
238     }%
239   \expandafter\endgroup
240   \ifZREF@found
241     \expandafter\@firstoftwo
242   \else
243     \expandafter\@secondoftwo
244   \fi
245 }

\zref@addprop \zref@addprop adds the property #2 to the property list #1, if the property is not already in the list. Otherwise a warning is given.
246 \def\zref@addprop#1#2{%
247   \zref@listexists{#1}{%
248     \zref@propexists{#2}{%
249       \zref@listcontainsprop{#1}{#2}{%
250         \PackageWarning{\ZREF@name}{%
251           Property '#2' is already in list '#1}%
252       }%
253     }%
254     \expandafter\g@addto@macro\csname Z@L@#1\endcsname{#2}%
255   }%
256 }%
257 }%
258 }

```

6.2.7 Properties

\zref@ifpropundefined	\zref@ifpropundefined checks the existence of the property #1. If the property is present, then #2 is executed and #3 otherwise.
	<pre> 259 \def\zref@ifpropundefined#1{% 260 \expandafter\ifx\csname Z@E@#1\endcsname\relax 261 \expandafter\@firstoftwo 262 \else 263 \expandafter\@secondoftwo 264 \fi 265 }</pre>
\zref@propexists	Some macros rely on the existence of a property. \zref@propexists only executes #2 if the property #1 exists and raises an error message otherwise.
	<pre> 266 \def\zref@propexists#1{% 267 \zref@ifpropdefined{#1}{% 268 \PackageError{ZREF@name}{% 269 Property '#1' does not exist}% 270 }{\@ehc 271 }%</pre>
\zref@newprop	A new property is declared by \zref@newprop, the property name <i><propname></i> is given in #1. The property is created and configured. If the star form is given, then the expansion of the property value is delayed to page shipout time, when the reference is written to the .aux file.
	\Z@D@ <i>propname</i> : Stores the default value for this property.
	\Z@E@ <i>propname</i> : Extract function.
	\Z@X@ <i>propname</i> : Information whether the expansion of the property value is delayed to shipout time.
	\Z@C@ <i>propname</i> : Current value of the property.
	<pre> 273 \def\zref@newprop{% 274 \@ifstar{% 275 \let\ZREF@X\noexpand 276 \ZREF@newprop 277 }{% 278 \let\ZREF@X\empty 279 \ZREF@newprop 280 }% 281 } 282 \def\ZREF@newprop#1{% 283 \PackageInfo{zref}{New property: #1}% 284 \def\ZREF@P{#1}% 285 \@ifnextchar[\ZREF@@newprop{\ZREF@@newprop[\ZREF@@newprop[\zref@default]]}% 286 } 287 \def\ZREF@newprop[#1]{% 288 \global\@namedef{Z@D@ZREF@P}{#1}% 289 \global\expandafter\let\csname Z@X@ZREF@P\endcsname\ZREF@X 290 \expandafter\ZREF@@newprop\csname ZREF@P\endcsname 291 \zref@setcurrent\ZREF@P 292 } 293 \def\ZREF@@newprop#1{% 294 \expandafter\gdef\csname Z@E@ZREF@P\endcsname##1##2##3\ZREF@nil{##2}% 295 }</pre>
\zref@setcurrent	\zref@setcurrent sets the current value for a property.
	<pre> 296 \def\zref@setcurrent#1{% 297 \expandafter\def\csname Z@C@#1\endcsname 298 }</pre>

```

\zref@getcurrent \zref@getcurrent gets the current value for a property.
299 \def\zref@getcurrent#1{%
300   \csname Z@C@#1\endcsname
301 }

```

6.2.8 Reference generation

\zref@label Label macro that uses the main property list.

```

302 \def\zref@label#1{%
303   \zref@labelbylist{#1}\ZREF@mainlist
304 }

```

\zref@labelbylist Label macro that stores the properties, specified in the property list #2.

```

305 \def\zref@labelbylist#1#2{%
306   \@bsphack
307   \zref@listexists{#2}{%
308     \expandafter\expandafter\expandafter\ZREF@label
309     \expandafter\expandafter\expandafter{%
310       \csname Z@L@#2\endcsname
311     }{#1}%
312   }%
313   \@esphack
314 }

```

\zref@labelbyprops The properties are directly specified in a comma separated list.

```

315 \def\zref@labelbyprops#1#2{%
316   \@bsphack
317   \begingroup
318   \edef\l{#2}%
319   \toks@{ }%
320   \for\x:=#2\do{%
321     \zref@ifpropundefined{\x}{%
322       \PackageWarning{\ZREF@name}{%
323         Property '\x' is not known}%
324     }%
325   }%
326   \toks@\expandafter\expandafter\expandafter{%
327     \expandafter\the\expandafter\toks@\expandafter{\x}%
328   }%
329   }%
330 }%
331 \expandafter\endgroup
332 \expandafter\ZREF@label\expandafter{\the\toks@}{#1}%
333 \@esphack
334 }

```

\ifZREF@immediate The switch \ifZREF@immediate tells us, whether the label should be written immediately or at page shipout time. \ZREF@label need to be notified about this, because it must disable the deferred execution of property values, if the label is written immediately.

```
335 \newif\ifZREF@immediate
```

\zref@wrapper@immediate The argument of \zref@wrapper@immediate is executed inside a group where \write is redefined by adding \immediate before its execution. Also \ZREF@label is notified via the switch \ifZREF@immediate.

```

336 \long\def\zref@wrapper@immediate#1{%
337   \begingroup
338   \ZREF@immediatetrue
339   \let\ZREF@org@write\write
340   \def\write{\immediate\ZREF@org@write}%
341   #1%

```

```

342   \endgroup
343 }

\ZREF@label \ZREF@label writes the data in the .aux file. #1 contains the list of valid properties, #2 the name of the reference. In case of immediate writing, the deferred execution of property values is disabled. Also 21is made expandable in this case.
344 \def\ZREF@label#1#2{%
345   \if@filesw
346     \begingroup
347       \ifZREF@immediate
348         \let\ZREF@org@thepage\thepage
349       \fi
350       \protected@write\@auxout{%
351         \ifZREF@immediate
352           \let\thepage\ZREF@org@thepage
353         \fi
354         \let\ZREF@temp\@empty
355         \tfor\ZREF@P:=#1\do{%
356           \expandafter\ifx
357             \csname\ifZREF@immediate relax\else Z@X@{\ZREF@P}\fi\endcsname
358             \noexpand
359             \expandafter\let\csname Z@C@{\ZREF@P}\endcsname\relax
360           \fi
361           \toks@\expandafter{\ZREF@temp}%
362           \edef\ZREF@temp{%
363             \the\toks@
364             \expandafter\string\csname\ZREF@P\endcsname{%
365               \expandafter\noexpand\csname Z@C@{\ZREF@P}\endcsname
366             }%
367             }%
368             }%
369             }{%
370               \string\zref@newlabel{#2}{\ZREF@temp}%
371             }%
372           \endgroup
373         \fi
374 }
375 \def\ZREF@addtoks#1{%
376   \toks@\expandafter\expandafter\expandafter{%
377     \expandafter\the\expandafter\toks@#1%
378   }%
379 }

```

6.2.9 Reference querying and extracting

Design goal for the extracting macros is that the extraction process is full expandable. Thus these macros can be used in expandable contexts. But there are problems that cannot be solved by full expandable macros:

- In standard L^AT_EX undefined references sets a flag and generate a warning. Both actions are not expandable.
- Babel's support for its shorthand uses commands that use non-expandable assignments. However currently there is hope, that primitives are added to pdfL^AT_EX that allows the detection of contexts. Then the shorthand can detect, if they are executed inside \csname and protect themselves automatically.

\zref@ifrefundefined If a reference #1 is undefined, then macro \zref@ifrefundefined calls #2 and #3 otherwise.

```

380 \def\zref@ifrefundefined#1{%
381   \expandafter\ifx\csname Z@R@#1\endcsname\relax

```

```

382     \expandafter\@firstoftwo
383   \else
384     \expandafter\@secondoftwo
385   \fi
386 }

```

\zref@refused The problem with undefined references is addressed by the macro \zref@refused. This can be used outside the expandable context. In case of an undefined reference the flag is set to notify L^AT_EX and a warning is given.

```

387 \def\zref@refused#1{%
388   \zref@wrapper@babel\ZREF@refused{#1}%
389 }

```

\ZREF@refused

```

390 \def\ZREF@refused#1{%
391   \zref@ifrefundefined{#1}{%
392     \protect\G@refundefinedtrue
393     \G@latex@warning{%
394       Reference '#1' on page \thepage \space undefined%
395     }%
396   }{%
397 }

```

\zref@extract \zref@extract is an abbreviation for the case that the default of the property is used as default value.

```

398 \def\zref@extract#1#2{%
399   \expandafter\expandafter\expandafter\ZREF@extract
400   \expandafter\expandafter\expandafter{%
401     \csname Z@D@#2\endcsname
402   }{#1}{#2}%
403 }
404 \def\ZREF@extract#1#2#3{%
405   \zref@extractdefault{#2}{#3}{#1}%
406 }

```

\zref@ifrefcontainsprop \zref@ifrefcontainsprop looks, if the reference #1 has the property #2 and calls then #3 and #4 otherwise.

```

407 \def\zref@ifrefcontainsprop#1#2{%
408   \zref@ifrefundefined{#1}{%
409     \G@secondoftwo
410   }{%
411     \expandafter\ZREF@ifrefcontainsprop
412     \csname Z@E@#2\expandafter\endcsname
413     \csname#2\expandafter\expandafter\expandafter\endcsname
414     \expandafter\expandafter\expandafter{%
415       \csname Z@R@#1\endcsname
416     }%
417   }%
418 }
419 \def\ZREF@ifrefcontainsprop#1#2#3{%
420   \expandafter\ifx\expandafter\ZREF@novalue
421   #1#3#2\ZREF@novalue\ZREF@nil\empty
422   \expandafter\G@secondoftwo
423 \else
424   \expandafter\G@firstoftwo
425 \fi
426 }
427 \def\ZREF@novalue{\ZREF@NOVALUE}

```

\zref@extractdefault The basic extracting macro is \zref@extractdefault with the reference name in #1, the property in #2 and the default value in #3 in case for problems.

```

428 \def\zref@extractdefault#1#2#3{%
429   \zref@ifrefundefined{#1}{%
430     \ZREF@unexpanded{#3}%
431   }{%
432     \expandafter\expandafter\expandafter\ZREF@unexpanded
433     \expandafter\expandafter\expandafter{%
434       \csname Z@E@#2\expandafter\expandafter\expandafter\endcsname
435       \csname Z@R@#1\expandafter\expandafter\endcsname
436       \csname#2\endcsname{#3}\ZREF@nil
437     }%
438   }%
439 }

\zref@wrapper@unexpanded

440 \long\def\zref@wrapper@unexpanded#1{%
441   \let\ZREF@unexpanded\etex@unexpanded
442   #1%
443   \let\ZREF@unexpanded\@firstofone
444 }
445 \let\ZREF@unexpanded\@firstofone

```

6.2.10 Compatibility with babel

```

\zref@wrapper@babel

446 \long\def\zref@wrapper@babel#1#2{%
447   \ifcsname if@safemode@actives\endcsname
448     \expandafter\@firstofone
449   \else
450     \expandafter\@secondoftwo
451   \fi
452   {%
453     \if@safemode@actives
454       \expandafter\@secondoftwo
455     \else
456       \expandafter\@firstoftwo
457     \fi
458   }%
459   \begingroup
460     \csname @safemode@activestrue\endcsname
461     \edef\x{#2}%
462     \expandafter\endgroup
463     \expandafter\ZREF@wrapper@babel\expandafter{\x}{#1}%
464   }%
465 }{%
466   #1{#2}%
467 }%
468 }
469 \long\def\ZREF@wrapper@babel#1#2{%
470   #2{#1}%
471 }

```

6.2.11 Unique counter support

\zref@require@unique Generate the counter `zref@unique` if the counter does not already exist.

```

472 \def\zref@require@unique{%
473   \@ifundefined{c@zref@unique}{%
474     \begingroup
475       \let\@addtoreset\@gobbletwo
476       \newcounter{zref@unique}%
477     \endgroup

```

\thezref@unique \thezref@unique is used for automatically generated unique labelnames.

```
478     \renewcommand*\thezref@unique}{%
479         zref@\number\c@zref@unique
480     }%
481 }{}}%
482 }
```

6.2.12 Setup

\zref@setdefault Standard L^AT_EX prints “??” in bold face if a reference is not known. \zref@default holds the text that is printed in case of unknown references and is used, if the default was not specified during the definition of the new property by \ref@newprop. The global default value can be set by \zref@setdefault.

```
483 \def\zref@setdefault#1{%
484   \def\zref@default{\#1}%
485 }
```

\zref@default Now we initialize \zref@default with the same value that L^AT_EX uses for its undefined references.

```
486 \zref@setdefault{%
487   \nfss@text{\reset@font\bfseries ??}%
488 }
```

Main property list.

\zref@setmainlist The name of the default property list is stored in \ZREF@mainlist and can be set by \zref@setmainlist.

```
489 \def\zref@setmainlist#1{%
490   \def\ZREF@mainlist{\#1}%
491 }
492 \zref@setmainlist{main}
```

Now we create the list.

```
493 \zref@newlist\ZREF@mainlist
```

Main properties. The two properties `default` and `page` are created and added to the main property list. They store the data that standard L^AT_EX uses in its references created by \label.

`default` the appearance of the latest counter that is incremented by \refstepcounter
`page` the appearance of the page counter

```
494 \zref@newprop{default}{\@currentlabel}
495 \zref@newprop*{page}{\thepage}
496 \zref@addprop\ZREF@mainlist{default}
497 \zref@addprop\ZREF@mainlist{page}
```

Mark successful loading

```
498 \let\ZREF@baseok\@empty
499 </base>
```

6.3 Module user

```
500 <*user>
501 \NeedsTeXFormat{LaTeX2e}
502 \ProvidesPackage{zref-user}%
503 [2007/05/28 v2.1 Module user for zref (HO)]%
504 \RequirePackage{zref-base}[2007/05/28]
505 \Ifundefined{\ZREF@baseok}{\endinput}{}%
```

Option `zuser` enables a small user interface. All macros are prefixed by `\z`.

First we define the pendants to the standard L^AT_EX referencing commands `\label`, `\ref`, and `\pageref`.

- `\zlabel` Similar to `\label` the macro `\zlabel` writes a reference entry in the `.aux` file. The main property list is used. Also we add the babel patch. The `\label` command can also be used inside section titles, but it must not go into the table of contents. Therefore we have to check this situation.

```
506 \newcommand*\zlabel{%
507   \ifx\label\@gobble
508     \expandafter\@gobble
509   \else
510     \expandafter\zref@wrapper@babel\expandafter\zref@label
511   \fi
512 }%
```

- `\zref` Macro `\zref` is the corresponding macro for `\ref`. Also it provides an optional argument in order to select another property.

```
513 \newcommand*{\zref}[2][default]{%
514   \zref@propexists{#1}{%
515     \zref@wrapper@babel\ZREF@zref{#2}{#1}%
516   }%
517 }%
518 \def\ZREF@zref#1{%
519   \zref@refused{#1}%
520   \zref@extract{#1}%
521 }%
```

- `\zpageref` For macro `\zpageref` we just call `\zref` with property `page`.

```
522 \newcommand*\zpageref{%
523   \zref[page]%
524 }%
```

- `\zrefused` For the following expandible user macros `\zrefused` should be used to notify L^AT_EX in case of undefined references.

```
525 \newcommand*{\zrefused}{\zref@refused}%
526 </user>
```

6.4 Module `abspage`

```
527 <*abspage>
528 \NeedsTeXFormat{LaTeX2e}
529 \ProvidesPackage{zref-abspage}%
530 [2007/05/28 v2.1 Module abspage for zref (HO)]%
531 \RequirePackage{zref-base}[2007/05/28]
532 \@ifundefined{ZREF@baseok}{\endinput}{}%
```

Module `abspage` adds a new property `abspage` to the `main` property list for absolute page numbers. These are recorded by the help of package `atbegshi`.

```
533 \RequirePackage{atbegshi}%
```

The counter `abspage` must not go in the clear list of `\c@ckpt` that is used to set counters in `.aux` files of included T_EX files.

```
534 \begingroup
535   \let\@addtoreset\@gobbletwo
536   \newcounter{abspage}%
537 \endgroup
538 \setcounter{abspage}{0}%
539 \AtBeginShipout{%
540   \stepcounter{abspage}%
541 }%
542 \zref@newprop*{abspage}[0]{\the\c@abspage}%
```

```
543 \zref@addprop\ZREF@mainlist{abspage}%
```

Note that counter `abspage` shows the previous page during page processing. Before shipout the counter is incremented. Thus the property is correctly written with deferred writing. If the counter is written using `\zref@wrapper@immediate`, then the number is too small by one.

```
544 </abspage>
```

6.5 Module counter

```
545 <*counter>
546 \NeedsTeXFormat{LaTeX2e}
547 \ProvidesPackage{zref-counter}%
548 [2007/05/28 v2.1 Module counter for zref (HO)]%
549 \RequirePackage{zref-base}[2007/05/28]
550 \@ifundefined{ZREF@baseok}{\endinput}{}%
```

For features such as `hyperref`'s `\autoref` we need the name of the counter. The property `counter` is defined and added to the main property list.

```
551 \zref@newprop{counter}{}%
552 \zref@addprop\ZREF@mainlist{counter}
```

`\refstepcounter` is the central macro where we know which counter is responsible for the reference.

```
553 \AtBeginDocument{%
554   \ZREF@patch{refstepcounter}{%
555     \def\refstepcounter#1{%
556       \zref@setcurrent{counter}{#1}%
557       \ZREF@org@refstepcounter{#1}%
558     }%
559   }%
560 }
561 </counter>
```

6.6 Module lastpage

```
562 <*lastpage>
563 \NeedsTeXFormat{LaTeX2e}
564 \ProvidesPackage{zref-lastpage}%
565 [2007/05/28 v2.1 Module lastpage for zref (HO)]%
566 \RequirePackage{zref-base}[2007/05/28]
567 \@ifundefined{ZREF@baseok}{\endinput}{}%
```

The Module `lastpage` implements the service of package `lastpage` by setting a reference `LastPage` at the end of the document. If option `abspage` is given, also the absolute page number is available, because the properties of the main property list are used.

```
568 \AtBeginDocument{%
569   \AtEndDocument{%
570     \if@filesw
571       \clearpage
572       \begin{group}
573         \advance\c@page\m@ne
574         \zref@wrapper@immediate{\zref@label{LastPage}}%
575       \end{group}
576     \fi
577   }%
578 }
579 </lastpage>
```

6.7 Module totpages

```
580 <*totpages>
581 \NeedsTeXFormat{LaTeX2e}
582 \ProvidesPackage{zref-totpages}%
583 [2007/05/28 v2.1 Module totpages for zref (HO)]%
```

```

584 \RequirePackage{zref-base}[2007/05/28]
585 \ifundefined{ZREF@baseok}{\endinput}{}}

The absolute page number of the last page is the total page number.
586 \RequirePackage{zref-abspage}[2007/05/28]
587 \RequirePackage{zref-lastpage}[2007/05/28]

\ztotpages Macro \ztotpages contains the number of pages. It can be used inside expandable
calculations. It expands to zero if the reference is not yet available.
588 \newcommand*\ztotpages{\%
589   \zref@extractdefault{LastPage}{abspage}{0}%
590 }

```

Also we mark the reference `LastPage` as used:

```

591 \AtBeginDocument{%
592   \zref@refused{LastPage}%
593 }
594 
```

6.8 Module `perpage`

```

595 <*perpage>
596 \NeedsTeXFormat{LaTeX2e}
597 \ProvidesPackage{zref-perpage}%
598 [2007/05/28 v2.1 Module perpage for zref (HO)]%
599 \RequirePackage{zref-base}[2007/05/28]
600 \ifundefined{ZREF@baseok}{\endinput}{}}

```

This module resets a counter at page boundaries. Because of the asynchronous output routine page counter properties cannot be asked directly, references are necessary.

For detecting changed pages module `abspage` is loaded.

```
601 \RequirePackage{zref-abspage}[2007/05/28]
```

We group the properties for the needed references in the property list `perpage`. The property `pagevalue` records the correct value of the page counter.

```

602 \zref@newprop*{pagevalue}[0]{\number\c@page}
603 \zref@newlist{perpage}
604 \zref@addprop{perpage}{abspage}
605 \zref@addprop{perpage}{page}
606 \zref@addprop{perpage}{pagevalue}

```

The page value, known by the reference mechanism, will be stored in counter `zpage`.

```
607 \newcounter{zpage}
```

Counter `zref@unique` helps in generating unique reference names.

```
608 \zref@require@unique
```

In order to be able to reset the counter, we hook here into `\stepcounter`. In fact two nested hooks are used to allow other packages to use the first hook at the beginning of `\stepcounter`.

```

609 \let\ZREF@org@stepcounter\stepcounter
610 \def\stepcounter#1{%
611   \ifcsname @stepcounterhook#1\endcsname
612     \csname @stepcounterhook#1\endcsname
613   \fi
614   \ZREF@org@stepcounter{#1}%
615 }

```

`\zmakeperpage` Makro `\zmakeperpage` resets a counter at each page break. It uses the same syntax and semantics as `\MakePerPage` from package `perpage` [5]. The initial start value can be given by the optional argument. Default is one that means after the first `\stepcounter` on a new page the counter starts with one.

```
616 \newcommand*\zmakeperpage{%
```

```

617  \c@ifnextchar[\ZREF@makeperpage@opt{\ZREF@makeperpage[\z@]}%
618 }

```

We hook before the counter is incremented in `\stepcounter`, package `perpage` afterwards. Thus a little calculation is necessary.

```

619 \def\ZREF@makeperpage@opt[#1]{%
620   \begingroup
621     \edef\x{\endgroup
622       \noexpand\ZREF@makeperpage[\number\numexpr#1-1\relax]%
623     }%
624   \x
625 }

626 \def\ZREF@makeperpage[#1]#2{%
627   \c@ifundefined{@stepcounterhook@#2}{%
628     \expandafter\gdef\csname @stepcounterhook@#2\endcsname{}%
629   }{}%
630   \expandafter\gdef\csname ZREF@perpage@#2\endcsname{%
631     \ZREF@perpage@step{#2}{#1}%
632   }%
633   \expandafter\g@addto@macro\csname @stepcounterhook@#2\endcsname{%
634     \ifcsname ZREF@perpage@#2\endcsname
635       \csname ZREF@perpage@#2\endcsname
636     \fi
637   }%
638 }

```

`\ZREF@perpage@step` The heart of this module follows.

```
639 \def\ZREF@perpage@step#1#2{%
```

First the reference is generated.

```

640   \global\advance\c@zref@unique\@ne
641   \begingroup
642     \expandafter\zref@labelbylist\expandafter{\thezref@unique}{perpage}%

```

The `\expandafter` commands are necessary, because `\ZREF@temp` is also used inside of `\zref@labelbylist`.

The evaluation of the reference follows. If the reference is not yet known, we use the page counter as approximation.

```

643   \zref@ifrefundefined{\thezref@unique}{%
644     \global\c@zpage=\c@page
645     \global\let\thezpage\thepage
646     \expandafter\xdef\csname ZREF@abspage@#1\endcsname{\number\c@abspage}%
647   }{%

```

The reference is used to set `\thezpage` and counter `zpage`.

```

648   \global\c@zpage=\zref@extract{\thezref@unique}{pagevalue}\relax
649   \xdef\thezpage{\noexpand\zref@extract{\thezref@unique}{page}}%
650   \expandafter\xdef\csname ZREF@abspage@#1\endcsname{%
651     \zref@extractdefault{\thezref@unique}{abspage}\number\c@abspage}%
652   }%
653 }

```

Page changes are detected by a changed absolute page number.

```

654   \expandafter\ifx\csname ZREF@abspage@#1\expandafter\endcsname
655     \csname ZREF@currentabspage@#1\endcsname
656   \else
657     \global\csname c@#1\endcsname=\#2\relax
658     \global\expandafter\let
659       \csname ZREF@currentabspage@#1\expandafter\endcsname
660       \csname ZREF@abspage@#1\endcsname
661   \fi
662 \endgroup
663 }

```

```
\zunmakeperpage Macro \zunmakeperpage cancels the effect of \zmakeperpage.
664 \newcommand*{\zunmakeperpage}[1]{%
665   \global\expandafter\let\csname ZREF@perpage@\#1\endcsname\@undefined
666 }
667 
```

6.9 Module titleref

```
668 <*titleref>
669 \NeedsTeXFormat{LaTeX2e}
670 \ProvidesPackage{zref-titleref}%
671 [2007/05/28 v2.1 Module titleref for zref (HO)]%
672 \RequirePackage{zref-base}[2007/05/28]
673 \ifundefined{ZREF@baseok}{\endinput}{}%
```

6.9.1 Implementation

```
674 \RequirePackage{keyval}
```

This module makes section and caption titles available for the reference system. It uses some of the ideas of package `nameref` and `titleref`.

`\zref@titleref@current` Later we will redefine the section and caption macros to catch the current title and remember the value in `\zref@titleref@current`.

```
675 \let\zref@titleref@current\empty
```

Now we can add the property `title` is added to the main property list.

```
676 \zref@newprop{title}{\zref@titleref@current}%
677 \zref@addprop{ZREF@mainlist}{title}{}%
```

The title strings go into the `.aux` file, thus they need some kind of protection. Package `titleref` uses a protected expansion method. The advantage is that this can be used to cleanup the string and to remove `\label`, `\index` and other macros unwanted for referencing. But there is the risk that fragile stuff can break.

Therefore package `nameref` does not expand the string. Thus the entries can safely be written to the `.aux` file. But potentially dangerous macros such as `\label` remain in the string and can cause problems when using the string in references.

`\ifzref@titleref@expand` The switch `\ifzref@titleref@expand` distinguishes between the both methods. Package `nameref`'s behaviour is achieved by setting the switch to false, otherwise `titleref`'s expansion is used. Default is false.

```
678 \newif\ifzref@titleref@expand
```

`\ZREF@titleref@hook` The hook `\ZREF@titleref@hook` allows to extend the cleanup for the expansion method. Thus unnecessary macros can be removed or dangerous commands removed. The hook is executed before the expansion of `\zref@titleref@current`.

```
679 \let\ZREF@titleref@hook\empty
```

`\zref@titleref@cleanup` The hook should not be used directly, instead we provide the macro `\zref@titleref@cleanup` to add stuff to the hook and prevents that a previous non-empty content is not discarded accidentally.

```
680 \def\zref@titleref@cleanup#1{%
681   \begingroup
682   \toks@\expandafter{%
683     \ZREF@titleref@hook
684     #1%
685   }%
686   \expandafter\endgroup
687   \expandafter\def\expandafter\ZREF@titleref@hook\expandafter{%
688     \the\toks@
689   }%
690 }%
```

\ifzref@titleref@stripperiod	Sometimes a title contains a period at the end. Package <code>nameref</code> removes this. This behaviour is controlled by the switch <code>\ifzref@titleref@stripperiod</code> and works regardless of the setting of option <code>expand</code> . Period stripping is the default.
	<pre> 691 \newif\ifzref@titleref@stripperiod 692 \zref@titleref@stripperiodtrue </pre>
\zref@titleref@setcurrent	Macro <code>\zref@titleref@setcurrent</code> sets a new current title stored in <code>\zref@titleref@current</code> . Some cleanup and expansion is performed that can be controlled by the previous switches.
	<pre> 693 \def\zref@titleref@setcurrent#1{% 694 \def\zref@titleref@current{\#1}% 695 \ifzref@titleref@expand 696 \begin{group} 697 \let\label\gobble 698 \let\index\gobble 699 \let\glossary\gobble 700 \let\markboth\gobbletwo 701 \let\mkboth\gobbletwo 702 \let\markright\gobble 703 \let\protect\unexpandable@protect 704 \ZREF@titleref@hook 705 \edef\x{\endgroup 706 \noexpand\def\noexpand\zref@titleref@current{% 707 \zref@titleref@current 708 }% 709 }% 710 \x 711 \fi 712 \edef\zref@titleref@current{% 713 \detokenize\expandafter{\zref@titleref@current}% 714 }% 715 \ifzref@titleref@stripperiod 716 \edef\zref@titleref@current{% 717 \expandafter\ZREF@stripperiod\zref@titleref@current 718 \empty.\empty@\nil 719 }% 720 \fi 721 }% </pre>
\ZREF@stripperiod	If <code>\ZREF@stripperiod</code> is called, the argument consists of space tokens and tokens with catcode 12 (other), because of ε -TEX's <code>\detokenize</code> .
	<pre> 722 \def\ZREF@stripperiod#1.\empty#\empty@\nil{\#1}% </pre>

6.9.2 User interface

\ztitlerefsetup	The behaviour of option <code>titleref</code> is controlled by switches and a hook. They can be set by <code>\ztitlerefsetup</code> with a key value interface, provided by package <code>keyval</code> . Also the current title can be given explicitly by the key <code>title</code> .
	<pre> 723 \define@key{ZREF@TR}{expand}[true]{% 724 \csname zref@titleref@expand#1\endcsname 725 }% 726 \define@key{ZREF@TR}{stripperiod}[true]{% 727 \csname zref@titleref@stripperiod#1\endcsname 728 }% 729 \define@key{ZREF@TR}{cleanup}{% 730 \zref@titleref@cleanup{#1}% 731 }% 732 \define@key{ZREF@TR}{title}{% 733 \def\zref@titleref@current{\#1}% 734 }% 735 \newcommand*\ztitlerefsetup{% </pre>

```

736   \setkeys{ZREF@TR}{%
737 }%

```

\ztitleref The user command \ztitleref references the title. For safety \label is disabled to prevent multiply defined references.

```

738 \newcommand*{\ztitleref}{%
739   \zref@wrapper@babel\ZREF@titleref
740 }%
741 \def\ZREF@titleref#1{%
742   \begingroup
743     \zref@refused{#1}%
744     \let\label\@gobble
745     \zref@extract{#1}{title}%
746   \endgroup
747 }%

```

6.9.3 Patches for section and caption commands

The section and caption macros are patched to extract the title data.

Captions of figures and tables.

```

748 \AtBeginDocument{%
749   \ZREF@patch{@caption}{%
750     \long\def\@caption#1[#2]{%
751       \zref@titleref@setcurrent{#2}%
752       \ZREF@org@@caption{#1}[{#2}]%
753     }%
754 }%

```

Section commands without star. The title version for the table of contents is used because it is usually shorter and more robust.

```

755 \ZREF@patch{@part}{%
756   \def\@part[#1]{%
757     \zref@titleref@setcurrent{#1}%
758     \ZREF@org@@part[{#1}]%
759   }%
760 }%
761 \ZREF@patch{@chapter}{%
762   \def\@chapter[#1]{%
763     \zref@titleref@setcurrent{#1}%
764     \ZREF@org@@chapter[{#1}]%
765   }%
766 }%
767 \ZREF@patch{@sect}{%
768   \def\@sect#1#2#3#4#5#6[#7]{%
769     \zref@titleref@setcurrent{#7}%
770     \ZREF@org@@sect{#1}{#2}{#3}{#4}{#5}{#6}[{#7}]%
771   }%
772 }%

```

The star versions of the section commands.

```

773 \ZREF@patch{@spart}{%
774   \def\@spart#1{%
775     \zref@titleref@setcurrent{#1}%
776     \ZREF@org@@spart{#1}%
777   }%
778 }%
779 \ZREF@patch{@schapter}{%
780   \def\@schapter#1{%
781     \zref@titleref@setcurrent{#1}%
782     \ZREF@org@@schapter{#1}%
783   }%
784 }%
785 \ZREF@patch{@ssect}{%

```

```

786      \def\@sect#1#2#3#4#5{%
787          \zref@titleref@setcurrent{#5}%
788          \ZREF@org@@sect{#1}{#2}{#3}{#4}{#5}%
789      }%
790  }%

```

Class beamer.

```

791  \@ifclassloaded{beamer}{%
792      \ZREF@patch{beamer@section}{%
793          \long\def\beamer@section[#1]{%
794              \zref@titleref@setcurrent{#1}%
795              \ZREF@org@beamer@section[{#1}]%
796          }%
797      }%
798      \ZREF@patch{beamer@subsection}{%
799          \long\def\beamer@subsection[#1]{%
800              \zref@titleref@setcurrent{#1}%
801              \ZREF@org@beamer@subsection[{#1}]%
802          }%
803      }%
804      \ZREF@patch{beamer@subsubsection}{%
805          \long\def\beamer@subsubsection[#1]{%
806              \zref@titleref@setcurrent{#1}%
807              \ZREF@org@beamer@subsubsection[{#1}]%
808          }%
809      }%
810  }{}%

```

Package titlesec.

```

811  \@ifpackageloaded{titlesec}{%
812      \ZREF@patch{ttl@sect@i}{%
813          \def\ttl@sect@i#1#2[#3]#4{%
814              \zref@titleref@setcurrent{#4}%
815              \ZREF@org@ttl@sect@i{#1}{#2}{#3}{#4}%
816          }%
817      }%
818  }{}%

```

Package longtable: some support for its \caption. However \label inside the caption is not supported.

```

819  \@ifpackageloaded{longtable}{%
820      \ZREF@patch{LT@c@option}{%
821          \def\LT@c@option#1[#2]#3{%
822              \ZREF@org@LT@c@option{#1}{#2}{#3}%
823              \zref@titleref@setcurrent{#2}%
824          }%
825      }%
826  }{}%

```

Package listings: support for its caption.

```

827  \@ifpackageloaded{listings}{%
828      \ZREF@patch{lst@MakeCaption}{%
829          \def\lst@MakeCaption{%
830              \ifx\lst@label\empty
831              \else
832                  \expandafter\zref@titleref@setcurrent\expandafter{%
833                      \lst@caption
834                  }%
835              \fi
836              \ZREF@org@lst@MakeCaption
837          }%
838      }%
839  }{}%
840 }

```

```
841 </titleref>
```

6.10 Module xr

```
842 <*xr>
843 \NeedsTeXFormat{LaTeX2e}
844 \ProvidesPackage{zref-xr}%
845 [2007/05/28 v2.1 Module xr for zref (HO)]%
846 \RequirePackage{zref-base}[2007/05/28]
847 \@ifundefined{ZREF@baseok}{\endinput}{}%
848 \RequirePackage{keyval}
```

We declare property `url`, because this is added, if a reference is imported and has not already set this field. Or if `hyperref` is used, then this property can be asked.

```
849 \zref@newprop{url}{}%
```

Most code, especially the handling of the `.aux` files are taken from David Carlisle's `xr` package. Therefore I drop the documentation for these macros here.

`\zref@xr@ext` If the URL is not specied, then assume processed file with a guessed extension. Use the setting of `hyperref` if available.

```
850 \providecommand*\zref@xr@ext{}%
851 \ifundefined{XR@ext}{pdf}{\XR@ext}%
852 }%
```

`\ifZREF@xr@zreflabel` The use of the star form of `\zexternaldocument` is remembered in the switch `\ifZREF@xr@zreflabel`.

```
853 \newif\ifZREF@xr@zreflabel
```

`\zexternaldocument` In its star form it looks for `\newlabel`, otherwise for `\zref@newlabel`. Later we will read `.aux` files that expects @ to have catcode 11 (letter).

```
854 \newcommand*\zexternaldocument{}%
855 \begingroup
856 \csname @safe@actives@true\endcsname
857 \makeatletter
858 \ifstar{%
859 \ZREF@xr@zreflabelfalse
860 \@testopt\ZREF@xr@externaldocument{}%
861 }{%
862 \ZREF@xr@zreflabeltrue
863 \@testopt\ZREF@xr@externaldocument{}%
864 }%
865 }%
```

If the `\include` featur was used, there can be several `.aux` files. These files are read one after another, especially they are not recursively read in order to save read registers. Thus it can happen that the read order of the newlabel commands differs from L^AT_EX's order using `\input`.

`\ZREF@xr@externaldocument` It reads the remaining arguments. `\newcommand` comes in handy for the optional argument.

```
866 \def\ZREF@xr@externaldocument[#1]#2{%
867 \def\ZREF@xr@prefix{#1}%
868 \let\ZREF@xr@filelist\empty
869 \edef\ZREF@xr@file{\#2.aux}%
870 \filename@parse{\#2}%
871 \testopt\ZREF@xr@graburl{\#2.\zref@xr@ext}%
872 }%
873 \def\ZREF@xr@graburl[#1]{%
874 \edef\ZREF@xr@url{#1}%
875 \ZREF@xr@checkfile
876 \endgroup
877 }%
```

\ZREF@xr@processfile We follow xr here, \IfFileExists offers a nicer test, but we have to open the file anyway.

```

878 \def\ZREF@xr@checkfile{%
879   \openin\@inputcheck\ZREF@xr@file\relax
880   \ifeof\@inputcheck
881     \PackageWarning{zref/xr}{%
882       File '\ZREF@xr@file' not found or empty, \MessageBreak
883       labels not imported}
884   }%
885 \else
886   \PackageInfo{zref/xr}{%
887     Label \ifZREF@xr@zreflabel (zref) \fi import from '\ZREF@xr@file'%
888   }%
889   \def\ZREF@xr@found{0}%
890   \def\ZREF@xr@ignored{0}%
891   \ZREF@xr@processfile
892   \closein\@inputcheck
893   \begingroup
894     \let\on@line\@empty
895     \PackageInfo{zref/xr}{%
896       Statistics for '\ZREF@xr@file': %
897       \ZREF@xr@found\space found, %
898       \ZREF@xr@ignored\space ignored}
899   }%
900   \endgroup
901 \fi
902 \ifx\ZREF@xr@filelist\@empty
903 \else
904   \edef\ZREF@xr@file{\expandafter\@car\ZREF@xr@filelist\@nil}%
905   \edef\ZREF@xr@filelist{\expandafter\@cdr\ZREF@xr@filelist\@nil}%
906   \expandafter\ZREF@xr@checkfile
907 \fi
908 }%


\ZREF@xr@processfile

909 \def\ZREF@xr@processfile{%
910   \read\@inputcheck to\ZREF@xr@line
911   \expandafter\ZREF@xr@processline\ZREF@xr@line..\ZREF@nil
912   \ifeof\@inputcheck
913   \else
914     \expandafter\ZREF@xr@processfile
915   \fi
916 }%
```

\ZREF@xr@processline The most work must be done for analyzing the arguments of \newlabel.

```

917 \long\def\ZREF@xr@processline#1#2#3\ZREF@nil{%
918   \def\x{\#1}%
919   \toks@{\#2}%
920   \ifZREF@xr@zreflabel
921     \ifx\x\ZREF@xr@zref@newlabel
922       \expandafter\ZREF@xr@process@zreflabel\ZREF@xr@line... \ZREF@nil
923     \fi
924   \else
925     \ifx\x\ZREF@xr@newlabel
926       \expandafter\ZREF@xr@process@label\ZREF@xr@line... [] \ZREF@nil
927     \fi
928   \fi
929   \ifx\x\ZREF@xr@input
930     \edef\ZREF@xr@filelist{%
931       \etex@unexpanded\expandafter{\ZREF@xr@filelist}%
932       {\filename@area\the\toks@}%
933     }%
```

```

934   \fi
935   \ifeof\@inputcheck
936   \else
937     \expandafter\ZREF@xr@processfile
938   \fi
939 }%
940 \def\ZREF@xr@process@zreflabel{\zref@newlabel#1#2#3\ZREF@nil{%
941   \def\ZREF@xr@refname{Z@R@ \ZREF@xr@prefix#1}%
942   \edef\ZREF@xr@found{\the\numexpr\ZREF@xr@found+1\relax}%
943   \def\x{#2}%
944   \@ifundefined{\ZREF@xr@refname}{%
945     \let\ZREF@xr@list\x
946     \ifx\ZREF@xr@list\@empty
947       \PackageWarningNoLine{zref/xr}%
948       Label '#1' without properties ignored\MessageBreak
949       in file '\ZREF@xr@file'%
950     }%
951     \edef\ZREF@xr@ignored{\the\numexpr\ZREF@xr@ignored+1\relax}%
952   \else
953     \expandafter\ZREF@xr@checklist\x\ZREF@nil
954     \expandafter\global\expandafter\let
955       \csname \ZREF@xr@refname\endcsname\x
956   \fi
957   \ZREF@xr@urlcheck{\ZREF@xr@prefix#1}%
958 }{%
959   \ZREF@xr@ignorewarning{\ZREF@xr@prefix#1}%
960 }%
961 }%
962 \def\ZREF@xr@process@label{\newlabel#1#2#3[#4]#5\ZREF@nil{%
963   \def\ZREF@xr@refname{Z@R@ \ZREF@xr@prefix#1}%
964   \edef\ZREF@xr@found{\the\numexpr\ZREF@xr@found+1\relax}%
965   \def\x{#2}%
966   \@ifundefined{\ZREF@xr@refname}{%
967     \expandafter\ZREF@xr@scanparams
968       \csname\ZREF@xr@refname\expandafter\endcsname
969       \x{}{}{}{}{}{}{}{}\ZREF@nil
970     \ifx\#4\%
971     \else
972       % ntheorem knows an optional argument at the end of \newlabel
973       \zref@ifpropundefined{theotype}{%
974         \zref@newprop{theotype}{}%
975       }{%
976         \expandafter\g@addto@macro
977           \csname\ZREF@xr@refname\endcsname{\theotype{#4}}%
978       \fi
979       \ZREF@xr@urlcheck{\ZREF@xr@prefix#1}%
980   }{%
981     \ZREF@xr@ignorewarning{\ZREF@xr@prefix#1}%
982   }%
983 }%
984 \def\ZREF@xr@zref@newlabel{\zref@newlabel}%
985 \def\ZREF@xr@newlabel{\newlabel}%
986 \def\ZREF@xr@@input{\@input}%

\ZREF@xr@ignorewarning
987 \def\ZREF@xr@ignorewarning#1{%
988   \PackageWarningNoLine{zref/xr}%
989   Label '#1' is already in use\MessageBreak
990   in file '\ZREF@xr@file'%
991 }%
992   \edef\ZREF@xr@ignored{\the\numexpr\ZREF@xr@ignored+1\relax}%
993 }%

```

```

\ZREF@xr@checklist
994 \def\ZREF@xr@checklist#1#2#3\ZREF@nil{%
995   \ifx\@undefined#1\relax
996     \expandafter\ZREF@xr@checkkey\string#1\@nil
997   \fi
998   \ifx\#3\%
999   \else
1000     \oReturnAfterFi{%
1001       \ZREF@xr@checklist#3\ZREF@nil
1002     }%
1003   \fi
1004 }%
1005 \long\def\oReturnAfterFi#1\fi{\fi#1}%
1006 \def\ZREF@xr@checkkey#1#2\@nil{%
1007   \zref@ifpropundefined{#2}{%
1008     \zref@newprop{#2}{}}%
1009   }{}%
1010 }%

\ZREF@xr@scanparams
1011 \def\ZREF@xr@scanparams#1#2#3#4#5#6#7\ZREF@nil{%
1012   \global\let#1\empty
1013   \ZREF@foundfalse
1014   \ZREF@xr@scantitleref#1#2\TR@TitleReference{}{}\ZREF@nil
1015   \ifZREF@found
1016   \else
1017     \g@addto@macro#1{\default{#2}}%
1018   \fi
1019   % page
1020   \g@addto@macro#1{\page{#3}}%
1021   % nameref title
1022   \ifZREF@found
1023   \else
1024     \ifx\#4\%
1025     \else
1026       \zref@ifpropdefined{title}{%
1027         \zref@newprop{title}{}}%
1028       }{}%
1029       \g@addto@macro#1{\title{#4}}%
1030     \fi
1031   \fi
1032   % anchor
1033   \ifx\#5\%
1034   \else
1035     \zref@ifpropdefined{anchor}{%
1036       \zref@newprop{anchor}{}}%
1037       }{}%
1038       \g@addto@macro#1{\anchor{#5}}%
1039   \fi
1040   \ifx\#6\%
1041   \else
1042     \zref@ifpropdefined{url}{%
1043       \zref@newprop{url}{}}%
1044       }{}%
1045       \g@addto@macro#1{\url{#6}}%
1046   \fi
1047 }%

\ZREF@xr@scantitleref
1048 \def\ZREF@xr@scantitleref#1#2\TR@TitleReference#3#4#5\ZREF@nil{%
1049   \ifx\#5\%
1050   \else

```

```

1051     \g@addto@macro#1{%
1052         \default{#3}%
1053         \title{#4}%
1054     }%
1055     \ZREF@foundtrue
1056 \fi
1057 }%


\ZREF@xr@urlcheck
1058 \def\ZREF@xr@urlcheck#1{%
1059     \zref@ifrefcontainsprop{#1}{anchor}{%
1060         \zref@ifrefcontainsprop{#1}{url}{%
1061             }{%
1062                 \expandafter\g@addto@macro\csname Z@R@#1\expandafter\endcsname
1063                 \expandafter{%
1064                     \expandafter\url\expandafter{\ZREF@xr@url}}%
1065                 }%
1066             }%
1067         }{%
1068     }%
1069 }%


\zxrsetup Just one key for setting the default extension is currently used.
1070 \define@key{ZREF@XR}{ext}{%
1071     \def\zref@xr@ext{#1}%
1072 }%
1073 \newcommand*\zxrsetup{%
1074     \setkeys{ZREF@XR}{%
1075 }%


1076 </xr>

```

6.11 Module `hyperref`

UNFINISHED :-(

```

1077 <*hyperref>
1078 \NeedsTeXFormat{LaTeX2e}
1079 \ProvidesPackage{zref-hyperref}%
1080 [2007/05/28 v2.1 Module hyperref for zref (HO)]%
1081 \RequirePackage{zref-base}[2007/05/28]
1082 \Ifundefined{ZREF@baseok}{\endinput}{}

1083 \zref@newprop{anchor}[]{%
1084     \Ifundefined{@currentHref}{}{\@currentHref}%
1085 }%
1086 \zref@addprop\ZREF@mainlist{anchor}%
1087 </hyperref>

```

6.12 Module `savepos`

Option `savepos` provides an interface for pdfTeX's `\pdfsavepos`, see the manual for pdfTeX.

6.12.1 Identification

```

1088 <*savepos>
1089 \NeedsTeXFormat{LaTeX2e}
1090 \ProvidesPackage{zref-savepos}%
1091 [2007/05/28 v2.1 Module savepos for zref (HO)]%
1092 \RequirePackage{zref-base}[2007/05/28]
1093 \Ifundefined{ZREF@baseok}{\endinput}{}

```

6.12.2 Availability

First we check, whether the feature is available.

```
1094 \begingroup
1095   \@ifundefined{pdfsavepos}{%
1096     \ZREF@ErrorNoLine{%
1097       \string\pdfsavepos\space is not supported.\MessageBreak
1098       It is provided by pdfTeX (1.40) or XeTeX%
1099     }\ZREF@UpdatePdfTeX
1100   \endgroup
1101   \endinput
1102 }{}%
1103 \endgroup
```

In PDF mode we are done. However support for DVI mode was added later in version 1.40.0. In earlier versions `\pdfsavepos` is defined, but its execution raises an error. Note that XeTeX also provides `\pdfsavepos`.

```
1104 \RequirePackage{ifpdf}
1105 \ifpdf
1106 \else
1107   \begingroup\expandafter\expandafter\expandafter\endgroup
1108   \expandafter\ifx\csname pdftexversion\endcsname\relax
1109   \else
1110     \ifnum\pdftexversion<140 %
1111       \ZREF@ErrorNoLine{%
1112         \string\pdfsavepos\space is not supported in DVI mode\MessageBreak
1113         of this pdfTeX version%
1114       }\ZREF@UpdatePdfTeX
1115     \expandafter\expandafter\expandafter\endinput
1116   \fi
1117 \fi
1118 \fi
```

6.12.3 Setup

```
1119 \zref@newlist{savepos}
1120 \zref@newprop*{posx}[0]{\the\pdflastxpos}
1121 \zref@newprop*{posy}[0]{\the\pdflastypos}
1122 \zref@addprop{savepos}{posx}
1123 \zref@addprop{savepos}{posy}
```

6.12.4 User macros

`\zsavepos` The current location is stored in a reference with the given name.

```
1124 \def\zsavepos#1{%
1125   @bsphack
1126   \if@filesw
1127     \pdfsavepos
1128     \zref@labelbylist{#1}{savepos}%
1129   \fi
1130   @esphack
1131 }
```

`\zposx` The horizontal and vertical position are available by `\zposx` and `\zposy`. Do not rely on absolute positions. They differ in DVI and PDF mode of pdfTeX. Use differences instead. The unit of the position numbers is sp.

```
1132 \newcommand*{\zposx}[1]{%
1133   \zref@extract{#1}{posx}%
1134 }%
1135 \newcommand*{\zposy}[1]{%
1136   \zref@extract{#1}{posy}%
1137 }%
```

Typically horizontal and vertical positions are used inside calculations. Therefore the extracting macros should be expandable and babel's patch is not applicable.

Also it is in the responsibility of the user to marked used positions by `\zrefused` in order to notify L^AT_EX about undefined references.

```
1138 </savepos>
```

6.13 Module `dotfill`

```
1139 <*dotfill>
1140 \NeedsTeXFormat{LaTeX2e}
1141 \ProvidesPackage{zref-dotfill}%
1142 [2007/05/28 v2.1 Module dotfill for zref (HO)]%
1143 \RequirePackage{zref-base}[2007/05/28]
1144 \@ifundefined{ZREF@baseok}{\endinput}{}%
```

For measuring the width of `\zdotfill` we use the features provided by module `savepos`.

```
1145 \RequirePackage{zref-savepos}[2007/05/28]
```

For automatically generated label names we use the unique counter of module `base`.

```
1146 \zref@require@unique
```

Configuration is done by the key value interface of package `keyval`.

```
1147 \RequirePackage{keyval}
```

The definitions of the keys follow.

```
1148 \define@key{ZREF@DF}{unit}{%
1149   \def\ZREF@df@unit{\#1}%
1150 }
1151 \define@key{ZREF@DF}{min}{%
1152   \def\ZREF@df@min{\#1}%
1153 }
1154 \define@key{ZREF@DF}{dot}{%
1155   \def\ZREF@df@dot{\#1}%
1156 }
```

Defaults are set, see user interface.

```
1157 \providecommand\ZREF@df@min{2}
1158 \providecommand\ZREF@df@unit{.44em}
1159 \providecommand\ZREF@df@dot{.}
```

`\zdotfillsetup` Configuration of `\zdotfill` is done by `\zdotfillsetup`.

```
1160 \newcommand*{\zdotfillsetup}{\setkeys{ZREF@DF}}
```

`\zdotfill` `\zdotfill` sets labels at the left and the right to get the horizontal position.

`\zsavepos` is not used, because we do not need the vertical position.

```
1161 \newcommand*{\zdotfill}{%
1162   \leavevmode
1163   \global\advance\c@zref@unique\@ne
1164   \begingroup
1165     \def\ZREF@temp{zref@\number\c@zref@unique}%
1166     \pdfsavepos
1167     \zref@labelbyprops{\thezref@unique L}{posx}%
1168     \setlength{\dimen0}{\ZREF@df@unit}%
1169     \zref@ifrefundefined{\thezref@unique R}{%
1170       \ZREF@dotfill
1171     }{%
1172       \ifnum\numexpr\zposx{\thezref@unique R}-\zposx{\thezref@unique L}\relax
1173         <\dimexpr\ZREF@df@min\dimen0\relax
1174         \hfill
1175       \else
1176         \ZREF@dotfill
1177       \fi
1178     }
```

```

1178      }%
1179      \pdfsavepos
1180      \zref@labelbyprops{\thezref@unique R}{posx}%
1181      \endgroup
1182      \kern\z@%
1183 }

\ZREF@dotfill Help macro that actually sets the dots.

1184 \def\ZREF@dotfill{%
1185   \cleaders\hb@xt@\dimen@{\hss\ZREF@df@dot\hss}\hfill
1186 }

1187 </dotfill>

```

7 Installation

7.1 Download

Package. This package is available on CTAN¹:

CTAN:macros/latex/contrib/oberdiek/zref.dtx The source file.

CTAN:macros/latex/contrib/oberdiek/zref.pdf Documentation.

Bundle. All the packages of the bundle ‘oberdiek’ are also available in a TDS compliant ZIP archive. There the packages are already unpacked and the documentation files are generated. The files and directories obey the TDS standard.

CTAN:install/macros/latex/contrib/oberdiek.tds.zip

TDS refers to the standard “A Directory Structure for *TEX* Files” (CTAN:tds/tds.pdf). Directories with *texmf* in their name are usually organized this way.

7.2 Bundle installation

Unpacking. Unpack the *oberdiek.tds.zip* in the TDS tree (also known as *texmf* tree) of your choice. Example (linux):

```
unzip oberdiek.tds.zip -d ~/texmf
```

Script installation. Check the directory *TDSScripts/oberdiek/* for scripts that need further installation steps. Package *attachfile2* comes with the Perl script *pdflatfi.pl* that should be installed in such a way that it can be called as *pdflatfi*. Example (linux):

```
chmod +x scripts/oberdiek/pdflatfi.pl
cp scripts/oberdiek/pdflatfi.pl /usr/local/bin/
```

7.3 Package installation

Unpacking. The *.dtx* file is a self-extracting *docstrip* archive. The files are extracted by running the *.dtx* through plain-*TEX*:

```
tex zref.dtx
```

¹[ftp://ftp.ctan.org/tex-archive/](http://ftp.ctan.org/tex-archive/)

TDS. Now the different files must be moved into the different directories in your installation TDS tree (also known as `texmf` tree):

```

zref.sty           → tex/latex/oberdiek/zref.sty
zref-base.sty     → tex/latex/oberdiek/zref-base.sty
zref-abspage.sty  → tex/latex/oberdiek/zref-abspage.sty
zref-counter.sty  → tex/latex/oberdiek/zref-counter.sty
zref-dotfill.sty  → tex/latex/oberdiek/zref-dotfill.sty
zref-hyperref.sty → tex/latex/oberdiek/zref-hyperref.sty
zref-lastpage.sty → tex/latex/oberdiek/zref-lastpage.sty
zref-perpage.sty  → tex/latex/oberdiek/zref-perpage.sty
zref-savepos.sty  → tex/latex/oberdiek/zref-savepos.sty
zref-titleref.sty → tex/latex/oberdiek/zref-titleref.sty
zref-totpages.sty → tex/latex/oberdiek/zref-totpages.sty
zref-user.sty      → tex/latex/oberdiek/zref-user.sty
zref-xr.sty        → tex/latex/oberdiek/zref-xr.sty
zref.pdf          → doc/latex/oberdiek/zref.pdf
zref-example.tex   → doc/latex/oberdiek/zref-example.tex
zref.dtx          → source/latex/oberdiek/zref.dtx

```

If you have a `docstrip.cfg` that configures and enables `docstrip`'s TDS installing feature, then some files can already be in the right place, see the documentation of `docstrip`.

7.4 Refresh file name databases

If your `TeX` distribution (`teTeX`, `mikTeX`, ...) relies on file name databases, you must refresh these. For example, `teTeX` users run `texhash` or `mktexlsr`.

7.5 Some details for the interested

Attached source. The PDF documentation on CTAN also includes the `.dtx` source file. It can be extracted by AcrobatReader 6 or higher. Another option is `pdftk`, e.g. unpack the file into the current directory:

```
pdftk zref.pdf unpack_files output .
```

Unpacking with L^AT_EX. The `.dtx` chooses its action depending on the format:

plain-`TeX`: Run `docstrip` and extract the files.

L^AT_EX: Generate the documentation.

If you insist on using L^AT_EX for `docstrip` (really, `docstrip` does not need L^AT_EX), then inform the autodetect routine about your intention:

```
latex \let\install=y\input{zref.dtx}
```

Do not forget to quote the argument according to the demands of your shell.

Generating the documentation. You can use both the `.dtx` or the `.drv` to generate the documentation. The process can be configured by the configuration file `ltxdoc.cfg`. For instance, put this line into this file, if you want to have A4 as paper format:

```
\PassOptionsToClass{a4paper}{article}
```

An example follows how to generate the documentation with pdfL^AT_EX:

```

pdflatex zref.dtx
makeindex -s gind.ist zref.idx
pdflatex zref.dtx
makeindex -s gind.ist zref.idx
pdflatex zref.dtx

```

8 References

- [1] Package `footmisc`, Robin Fairbairns, 2004/01/23 v5.3a.[CTAN:macros/latex/contrib/footmisc/footmisc.dtx](#)
- [2] Package `hyperref`, Sebastian Rahtz, Heiko Oberdiek, 2006/08/16 v6.75c.[CTAN:macros/latex/contrib/hyperref/](#)
- [3] Package `lastpage`, Jeff Goldberg, 1994/06/25 v0.1b.[CTAN:macros/latex/contrib/lastpage/](#)
- [4] Package `nameref`, Sebastian Rahtz, Heiko Oberdiek, 2006/02/12 v2.24.[CTAN:macros/latex/contrib/hyperref/nameref.dtx](#)
- [5] Package `perpage`, David Kastrup, 2002/12/20 v1.0.[CTAN:macros/latex/contrib/bigfoot/perpage.dtx](#)
- [6] Package `titleref`, Donald Arsenau, 2001/04/05 v3.1.[CTAN:macros/latex/contrib/misc/titleref.sty](#)
- [7] Package `totpages`, Wilhelm Müller, 1999/07/14 v1.00.[CTAN:macros/latex/contrib/totpages/](#)
- [8] Package `xr`, David Carlisle, 1994/05/28 v5.02.[CTAN:macros/latex/required/tools/xr.pdf](#)
- [9] Package `xr-hyper`, David Carlisle, 2000/03/22 v6.00beta4.[CTAN:macros/latex/contrib/hyperref/xr-hyper.sty](#)

9 History

[2006/02/20 v1.0]

- First version.

[2006/05/03 v1.1]

- Module `perpage` added.
- Module redesign as packages.

[2006/05/25 v1.2]

- Module `dotfillmin` added.
- Module base: macros `\zref@require@unique` and `\thezref@unique` added (used by modules `titleref` and `dotfillmin`).

[2006/09/08 v1.3]

- Typo fixes and English cleanup by Per Starback.

[2007/01/23 v1.4]

- Typo in macro name fixed in documentation.

[2007/02/18 v1.5]

- `\zref@getcurrent` added (suggestion of Igor Akkerman).
- Modul `savepos` also supports Xe^TE_X.

[2007/04/06 v1.6]

- Fix in modul `abspage` and `base`: Now counter `abspage` and `zref@unique` are not remembered by `\include`.
- Beamer support for module `titleref`.

[2007/04/17 v1.7]

- Package `atbegshi` replaces `everyshi`.

[2007/04/22 v1.8]

- `\zref@wrapper@babel` and `\zref@refused` are now expandable if `babel` is not used or `\if@safe@actives` is already set to true. (Feature request of Josselin Noirel)

[2007/05/02 v1.9]

- Module `titleref`: Some support for `\caption` of package `longtable`, but only if `\label` is given after `\caption`.

[2007/05/06 v2.0]

- Uses package `etexcmds` for accessing ε -`TEX`'s `\unexpanded`.

[2007/05/28 v2.1]

- Module `titleref` supports caption of package `listings`.
- Fixes in module `titleref` for support of packages `titlesec` and `longtable`.

10 Index

Numbers written in italic refer to the page where the corresponding entry is described; numbers underlined refer to the code line of the definition; numbers in roman refer to the code lines where the entry is used.

Symbols	
<code>\@ReturnAfterFi</code>	1000, 1005
<code>\@addtoreset</code>	475, 535
<code>\@auxout</code>	350
<code>\@bsphack</code>	306, 316, 1125
<code>\@caption</code>	750
<code>\@car</code>	904
<code>\@cdr</code>	905
<code>\@chapter</code>	762
<code>\@currentHref</code>	1084
<code>\@currentlabel</code>	494
<code>\@ehc</code>	209, 223, 270
<code>\@empty</code>	152, 203, 278, 354, 421, 498, 675, 679, 718, 722, 830, 868, 894, 902, 946, 1012
<code>\@esphack</code>	313, 333, 1130
<code>\@firstofone</code>	165, 443, 445, 448
<code>\@firstoftwo</code>	214, 241, 261, 382, 424, 456
<code>\@for</code>	320
<code>\@gobble</code>	161, 507, 508, 697, 698, 699, 702, 744
<code>\@gobbletwo</code>	475, 535, 700, 701
<code>\@ifclassloaded</code>	791
<code>\@ifdefinable</code>	202
<code>\@ifnextchar</code>	285, 617
<code>\@ifpackageloaded</code>	811, 819, 827
<code>\@ifstar</code>	274, 858
<code>\@ifundefined</code>	124, 169, 473, 505, 532, 550, 567, 585, 600, 627, 673, 847, 851, 944, 966, 1082, 1084, 1093, 1095, 1144
<code>\@input</code>	986
<code>\@inputcheck</code>	879, 880, 892, 910, 912, 935
<code>\@latex@warning</code>	393
<code>\@mkboth</code>	701
<code>\@namedef</code>	288
<code>\@ne</code>	640, 1163
<code>\@newl@bel</code>	198
<code>\@nil</code>	718, 722, 904, 905, 996, 1006
<code>\@part</code>	756
<code>\@schapter</code>	780
<code>\@secondoftwo</code>	216, 243, 263, 384, 409, 422, 450, 454
<code>\@sect</code>	768

\@spart	774	\end	62, 91, 115, 117
\@ssect	786	\endcsname	160, 163,
\@testopt	860, 863, 871	164, 203, 213, 227, 254, 260,	
\@tfor	233, 355	289, 290, 294, 297, 300, 310,	
\@undefined	665, 995	357, 359, 364, 365, 381, 401,	
\@unexpandable@protect	703	412, 413, 415, 434, 435, 436,	
\\"	85, 87, 89, 90, 102, 105,	447, 460, 611, 612, 628, 630,	
	970, 998, 1024, 1033, 1040, 1049	633, 634, 635, 646, 650, 654,	
		655, 657, 659, 660, 665, 724,	
		727, 856, 955, 968, 977, 1062, 1108	
A			
\AddLineBeginAux	194	\endinput	124, 177, 191, 505,
\advance	573, 640, 1163	532, 550, 567, 585, 600, 673,	
\anchor	1038	847, 1082, 1093, 1101, 1115, 1144	
\AtBeginDocument	553, 568, 591, 748	\etex@unexpanded	441, 931
\AtBeginShipout	539		
\AtEndDocument	569		
\AtEndOfPackage	127		
B			
\beamer@section	793		
\beamer@subsection	799		
\beamer@subsubsection	805		
\begin	34, 40, 88, 104		
\bfseries	487		
C			
\c@abspage	542, 646, 651		
\c@page	573, 602, 644		
\c@zpage	644, 648		
\c@zref@unique	479, 640, 1163, 1165		
\chapter	16		
\ChapterPages	25, 45		
\ChapterStart	12, 67, 82, 98		
\ChapterStop	19, 80, 97, 116		
\cleaders	1185		
\cleardoublepage	13, 20		
\clearpage	571		
\closein	892		
\csname	160, 163, 164, 203, 213,		
	227, 254, 260, 289, 290, 294,		
	297, 300, 310, 357, 359, 364,		
	365, 381, 401, 412, 413, 415,		
	434, 435, 436, 460, 612, 628,		
	630, 633, 635, 646, 650, 654,		
	655, 657, 659, 660, 665, 724,		
	727, 856, 955, 968, 977, 1062, 1108		
\current@chapid	14, 22		
D			
\DeclareOption	126		
\default	1017, 1052		
\define@key	723, 726,		
	729, 732, 1070, 1148, 1151, 1154		
\detokenize	713		
\dftest	99, 106, 107,		
	108, 109, 110, 111, 112, 113, 114		
\dimen@	1168, 1173, 1185		
\dimexpr	85, 87, 1173		
\do	233, 320, 355		
\documentclass	2, 186		
\dotfill	101, 105		
E			
\emph	82		
F			
\filename@area	932		
\filename@parse	870		
\frontmatter	37		
G			
\g@addto@macro	254, 633, 976, 1017,		
	1020, 1029, 1038, 1045, 1051, 1062		
\G@refundefinedtrue	392		
\gdef	294, 628, 630		
\glossary	699		
H			
\hb@xt@	1185		
\hfill	1174, 1185		
\hss	1185		
I			
\if@filesw	345, 570, 1126		
\if@safe@actives	453		
\ifcase	48		
\ifcsname	447, 611, 634		
\ifeof	880, 912, 935		
\ifetex@unexpanded	181		
\ifnum	1110, 1172		
\ifodd	57		
\ifpdf	1105		
\ifx	160, 213, 235, 260, 356,		
	381, 420, 507, 654, 830, 902,		
	921, 925, 929, 946, 970, 995,		
	998, 1024, 1033, 1040, 1049, 1108		
\ifZREF@found	157, 240, 1015, 1022		
\ifZREF@immediate	335, 347, 351, 357		
\ifzref@titleref@expand	678, 695		
\ifzref@titleref@stripperiod	691, 715		
\ifZREF@xr@zreflabel	853, 887, 920		
\immediate	340		
\index	698		
\item	41, 44, 46, 54, 58, 60		
K			
\kern	1182		
L			
\l	318		
\label	507, 697, 744		
\leavevmode	1162		
\lst@Caption	833		
\lst@Label	830		
\lst@MakeCaption	829		

\LT@c@ption	821	\reset@font	487
M			
\m@ne	573	\section	69, 77
\mainmatter	66	\setcounter	538
\makeatletter	8, 35, 857	\setkeys	736, 1074, 1160
\makeatother	33	\setlength	1168
\makebox	101, 102	\space	394, 897, 898, 1097, 1112
\markboth	700	\stepcounter	540, 609, 610
\markright	702		
\MessageBreak		T	
...	184, 882, 948, 989, 1097, 1112	\tableofcontents	64
N			
\NeedsTeXFormat		\the	85,
...	120, 146, 501, 528, 546, 563,	87, 327, 332, 363, 377, 542, 688,	
	581, 596, 669, 843, 1078, 1089, 1140	932, 942, 951, 964, 992, 1120, 1121	
\newcommand		\theotype	977
...	12, 19, 25, 99, 506, 513, 522,	\thepage	348, 352, 394, 495, 645
	525, 588, 616, 664, 735, 738,	\thezpage	10, 645, 649
	854, 1073, 1132, 1135, 1160, 1161	\thezref@unique	8, 478, 642, 643, 648,
\newcounter	476, 536, 607	649, 651, 1167, 1169, 1172, 1180	
\newif	157, 335, 678, 691, 853	\title	1029, 1053
\newlabel	962, 972, 985	\toks@	319, 326, 327, 332, 361,
\newpage	75	363, 376, 377, 682, 688, 919, 932	
\nfss@text	487	\TR@TitleReference	1014, 1048
\number	28,	\ttl@sect@i	813
43, 479, 602, 622, 646, 651, 1165			
\numexpr	28,	U	
43, 48, 622, 942, 951, 964, 992, 1172		\unexpanded	184, 189
O			
\on@line	152, 894	\url	1045, 1064
\openin	879	\usepackage	4, 6
P			
\PackageError	153, 207, 221, 268	V	
\PackageInfo	204, 283, 886, 895	\verb	105
\PackageWarning	250, 322, 881		
\PackageWarningNoLine	947, 988	W	
\page	1020	\write	339, 340
\pdflastxpos	1120		
\pdflastypos	1121	X	
\pdfsavepos	1097, 1112, 1127, 1166, 1179	\x	233, 234, 235, 320,
\pdftexversion	1110	321, 323, 327, 461, 463, 621,	
\ProcessOptions	143	624, 705, 710, 918, 921, 925,	
\protect	392, 703	929, 943, 945, 953, 955, 965, 969	
\protected@write	350	\XR@ext	851
\providecommand			
...	195, 850, 1157, 1158, 1159	Y	
\ProvidesPackage		\y	232, 235
...	121, 147, 502, 529, 547, 564,		
	582, 597, 670, 844, 1079, 1090, 1141	Z	
R			
\read	910	\z@	617, 1182
\refstepcounter	555	\zdotfill	11, 102, 105, 1161
\renewcommand	478	\zdotfillsetup	11, 1160
\RequirePackage	123,	\zexternaldocument	12, 854
128, 180, 185, 193, 504, 531,	\zlabel	8, 17, 38, 70, 78, 506	
533, 549, 566, 584, 586, 587,	\zmakeperpage	9, 616	
599, 601, 672, 674, 846, 848,	\zpageref	9, 59, 522	
1081, 1092, 1104, 1143, 1145, 1147	\zposx	11, 85, 1132, 1172	
		\zposy	11, 87, 1132
		\zref	8, 45, 47, 56, 61, 71, 513, 523
		\ZREF@@newprop	290, 293
		\ZREF@@makeperpage	617, 622, 626
		\ZREF@@newprop	285, 287
		\ZREF@@perpage@step	631, 639

\zref@addprop
 4, 10, 246, 496, 497, 543, 552,
 604, 605, 606, 677, 1086, 1122, 1123
\ZREF@addtoks 375
\ZREF@baseok 498
\zref@default 7, 285, 484, 486
\ZREF@df@dot 1155, 1159, 1185
\ZREF@df@min 1152, 1157, 1173
\ZREF@df@unit 1149, 1158, 1168
\ZREF@dotfill 1170, 1176, 1184
\ZREF@ErrorNoLine
 150, 170, 183, 1096, 1111
\ZREF@extract 399, 404
\zref@extract 6, 29, 30, 43, 72,
 398, 520, 648, 649, 745, 1133, 1136
\zref@extractdefault
 6, 49, 50, 405, 428, 589, 651
\ZREF@foundfalse 231, 1013
\ZREF@foundtrue 236, 1055
\zref@getcurrent 5, 299
\zref@iflistcontainsprop 5
\zref@iflistundefined 5, 201, 212, 220
\zref@ifpropundefined 5, 259, 267,
 321, 973, 1007, 1026, 1035, 1042
\ZREF@ifrefcontainsprop 411, 419
\zref@ifrefcontainsprop
 6, 407, 1059, 1060
\zref@ifrefundefined
 6, 380, 391, 408, 429, 643, 1169
\ZREF@immediatetrue 338
\ZREF@label 308, 332, 344
\zref@label 5, 302, 510, 574
\zref@labelbylist 6, 303, 305, 642, 1128
\zref@labelbyprops
 6, 22, 315, 1167, 1180
\ZREF@listcontainsprop 227, 229
\zref@listcontainsprop 226, 249
\zref@listexists 5, 219, 247, 307
\ZREF@mainlist 303, 490,
 493, 496, 497, 543, 552, 677, 1086
\ZREF@makeperpage@opt 617, 619
\ZREF@name
 149, 153, 207, 221, 250, 268, 322
\zref@newlabel 6, 195, 197, 370, 940, 984
\zref@newlist 4, 200, 493, 603, 1119
\ZREF@newprop 276, 279, 282
\zref@newprop 5, 9, 273, 494, 495, 542,
 551, 602, 676, 849, 974, 1008,
 1027, 1036, 1043, 1083, 1120, 1121
\ZREF@nil 294, 421, 436, 911,
 917, 922, 926, 940, 953, 962,
 969, 994, 1001, 1011, 1014, 1048
\ZREF@NOVALUE 427
\ZREF@novalue 420, 421, 427
\ZREF@org@@caption 752
\ZREF@org@@chapter 764
\ZREF@org@@part 758
\ZREF@org@@schapter 782
\ZREF@org@@sect 770
\ZREF@org@@spart 776
\ZREF@org@@sect 788
\ZREF@org@beamer@section 795
\ZREF@org@beamer@subsection 801
\ZREF@org@beamer@subsubsection 807
\ZREF@org@lst@MakeCaption 836
\ZREF@org@LT@c@option 822
\ZREF@org@refstepcounter 557
\ZREF@org@stepcounter 609, 614
\ZREF@org@thepage 348, 352
\ZREF@org@ttl@sect@i 815
\ZREF@org@write 339, 340
\ZREF@P 284, 288, 289, 290,
 291, 294, 355, 357, 359, 364, 365
\ZREF@patch 158, 554,
 749, 755, 761, 767, 773, 779,
 785, 792, 798, 804, 812, 820, 828
\zref@propexists 5, 248, 266, 514
\ZREF@refused 388, 390
\zref@refused 6, 387, 519, 525, 592, 743
\zref@require@unique 8, 472, 608, 1146
\zref@setcurrent 5, 15, 291, 296, 556
\zref@setdefault 7, 483, 486
\zref@setmainlist 7, 489
\ZREF@stripperiod 717, 722
\ZREF@temp 125, 132, 133, 134,
 135, 136, 137, 138, 139, 140,
 141, 142, 354, 361, 362, 370, 1165
\ZREF@titleref 739, 741
\zref@titleref@cleanup 680, 730
\zref@titleref@current
 675, 676, 694,
 706, 707, 712, 713, 716, 717, 733
\ZREF@titleref@hook 679, 683, 687, 704
\zref@titleref@setcurrent 693,
 751, 757, 763, 769, 775, 781,
 787, 794, 800, 806, 814, 823, 832
\zref@titleref@stripperiodtrue 692
\ZREF@unexpanded 430, 432, 441, 443, 445
\ZREF@UpdateTeX 156, 1099, 1114
\ZREF@wrapper@babel 463, 469
\zref@wrapper@babel
 7, 72, 388, 446, 510, 515, 739
\zref@wrapper@immediate 7, 21, 336, 574
\zref@wrapper@unexpanded 7, 440
\ZREF@X 275, 278, 289
\ZREF@xr@@input 929, 986
\ZREF@xr@checkfile 875, 878, 906
\ZREF@xr@checkkey 996, 1006
\ZREF@xr@checklist 953, 994
\zref@xr@ext 12, 850, 871, 1071
\ZREF@xr@externaldocument
 860, 863, 866
\ZREF@xr@file 869,
 879, 882, 887, 896, 904, 949, 990
\ZREF@xr@filelist
 868, 902, 904, 905, 930, 931
\ZREF@xr@found 889, 897, 942, 964
\ZREF@xr@graburl 871, 873
\ZREF@xr@ignored 890, 898, 951, 992
\ZREF@xr@ignorewarning 959, 981, 987
\ZREF@xr@online 910, 911, 922, 926
\ZREF@xr@list 945, 946
\ZREF@xr@newlabel 925, 985

\ZREF@xr@prefix \ZREF@xr@urlcheck 957, 979, 1058
 . 867, 941, 957, 959, 963, 979, 981 \ZREF@xr@zref@newlabel 921, 984
\ZREF@xr@procesfile 914 \ZREF@xr@zreflabelfalse 859
\ZREF@xr@process@label 926, 962 \ZREF@xr@zreflabeltrue 862
\ZREF@xr@process@zreflabel . 922, 940 \ZREF@zref 515, 518
\ZREF@xr@processfile ... 878, 909, 937 \zrefused 9, 26, 27, 93, 94, 95, 525
\ZREF@xr@processline 911, 917 \zsavepos 11, 89, 90, 1124
\ZREF@xr@refname \ztitleref 10, 738
 . 941, 944, 955, 963, 966, 968, 977 \ztitlerefsetup 10, 723
\ZREF@xr@scanparams 967, 1011 \ztotpages 9, 57, 588
\ZREF@xr@scantitleref ... 1014, 1048 \zunmakeperpage 10, 664
\ZREF@xr@url 874, 1064 \zxrsetup 12, 1070