

The `showexpl` package*

Rolf Niepraschk (`Rolf.Niepraschk@gmx.de`)

2020/10/08

1 Introduction

The documentation of a L^AT_EX package is by far more readable if there are examples of the commands' and environments' usage. The best way to do that is to give a comparison of the L^AT_EX code and the formatted output. `showexpl` is a package for doing that comparison, it is based on the package `listings` which provides a good typesetted source code with emphasised keywords and so on.

2 Usage

You can use `showexpl` like every other package by putting the line

```
\usepackage{showexpl}
```

in your source code. `showexpl` doesn't know any options by itself, but all options for the underlying packages (`listings` and `graphicx`) will be passed to the respective packages.

`showexpl` provides one command and one environment:

- `\LTXinputExample` and
- `LTXexample`

`\LTXinputExample` The syntax of `\LTXinputExample` is given by

```
\LTXinputExample[<key val list>]{<file>}
```

`LTXexample` The syntax of the environment `LTXexample` is given by

```
\begin{LTXexample}[<key val list>]... \end{LTXexample}
```

The set of options represented by `<key val list>` is the same for both the command and the environment, the options are described in the following:

attachfile Boolean valued key, default value: false. If set to true the sourcecode will be attached to the `.pdf` file—presumed that the document is processed by `pdflatex`.

codefile Name of the (temporary) file that contains the code which will be formatted as source code. The default value is `\jobname.tmp`.

*This document corresponds to `showexpl` v0.3r, dated 2020/10/08.

explpreset A $\langle key\ val\ list \rangle$ which serves for presetting the properties of the formatting of the source code, for values see the documentation of the `listings` package. The default value is

graphic Name of a (graphic) file. This file—if present—will be included and displayed instead of the formatted code. The default value is empty.

hsep Defines the horizontal distance between the source code and the formatted text.

justification Defines the justification of the formatted text: reasonable values are `\raggedleft`, `\raggedright`, `\centering`. The default value is `\raggedright`.

overhang A *dimen*-value that defines the amount by which the formatted text and the source code can overlap the print space. The default value is 0 pt.

pos: Defines the relative position of the formatted text relating to the source code. Allowed values are `t`, `b`, `l`, `r`, `o`, and `i` for top, bottom, left, right, outer, and inner. The last values give sense only for two-sided printing, where there are outer and inner margins of a page. The default value is `l`.

preset Any TeX code executed before the sample code but not visible in the `listings` area.

rangeaccept Boolean valued key, default value is false. If set to true, one can define ranges of lines that will be excerpted from the source code.

rframe Defines the form of the frame around the formatted text. With a non-empty value (e.g. “single”) a simple frame will be drawn. In the future more kinds of frames will be supported. The default value is empty (no frame).

varwidth Boolean valued key, default value is false. If set to true, the formatted text is set with its “natural” width instead of a fixed width as given by the value of the option `width`.

vsep Defines the vertical distance between the source code and the formatted text.

wide Boolean valued key, default value is false. If set to true, the source code and the formatted text overlap the print space and the margin area.

width A $\langle dimen \rangle$ value that defines the width of the formatted text. The default value depends of the relative positions of the source code and the formatted text.

scaled Without a value the formatted text will be scaled to fit the given width of the result area. With a number as value the formatted text will be scaled by this number.

In addition to these options the kind of the result box (default: `\fbox`) can be changed. For example:

```
\renewcommand{\ResultBox}{\fcolorbox{green}{lightgray}}
\setlength{\ResultBoxSep}{5mm}%
\setlength{\ResultBoxRule}{2mm}%
```

3 Implementation

```
1 \DeclareOption{final}{%
2   \PassOptionsToPackage{\CurrentOption}{graphicx}%
3   \PassOptionsToPackage{\CurrentOption}{listings}%
4 }%
5 \DeclareOption{draft}{%
6   \PassOptionsToPackage{\CurrentOption}{graphicx}%
7   \PassOptionsToPackage{\CurrentOption}{listings}%
8 }%
9 \DeclareOption{attachfiles}{%
10  \AtBeginDocument{\IfFileExists{attachfile.sty}{%
11    \RequirePackage{attachfile}}{\def\SX@attachfile{}}}}
12 }%
13 \DeclareOption*{\PassOptionsToPackage{\CurrentOption}{listings}}
14 \ProcessOptions\relax
15 \RequirePackage{refcount,listings,graphicx,varwidth,floor}
```

We must activate code from package `listings` for writing files.

\SX@defaultWD Parameter #2 is a length or a number. Parameter #1 is a macro. After a call of \SX@defaultWD this macro contains the value of the length or the value of the number multiplied by \linewidth.

```
17 \newcommand*\SX@defaultWD[2]{%
18   \afterassignment\SX@def@WD\dimen@#2\linewidth\relax{#1}}
19 \newcommand*\SX@def@WD{%
20 \def\SX@def@WD#1\relax#2{\edef#2{\the\dimen@}}}
```

Additional keys.

```
21 \lst@Key{pos}\relax{\def\SX@pos{#1}}
22 \lst@Key{width}\relax{\def\SX@width{#1}}
23 \lst@Key{hsep}\relax{\tempdima=#1\relax\edef\SX@hsep{\the\tempdima}}
24 \lst@Key{vsep}\relax{\tempdima=#1\relax\edef\SX@vsep{\the\tempdima}}
25 \lst@Key{overhang}\relax{\def\SX@overhang{#1}}
26 \lst@Key{wide}f[t]{\lstKV@SetIf{#1}\if@SX@wide}
27 \lst@Key{rframe}\relax{\def\SX@rframe{#1}}
28 \lst@Key{preset}\relax{\def\SX@preset{#1}}
29 \newcommand*\SX@scaled{%
30 \lst@Key{scaled}{?}{!}{\def\SX@scaled{#1}}}

31 \lst@Key{explpreset}\relax{\def\SX@explpreset{#1}}
32 \lst@Key{codefile}\relax{\def\SX@codefile{#1}}
33 \newif\if@SX@rangeaccept \SX@rangeacceptfalse
34 \newif\if@SX@varwidth \SX@varwidthfalse
35 \newif\if@SX@wide \SX@widefalse
36 \newif\if@SX@attachfile \SX@attachfilefalse

37 \lst@Key{rangeaccept}f[t]{\lstKV@SetIf{#1}\if@SX@rangeaccept}

38 \lst@Key{varwidth}f[t]{\lstKV@SetIf{#1}\if@SX@varwidth}
39 \lst@Key{justification}\relax{\def\SX@justification{#1}}
40 \lst@Key{attachfile}f[t]{\lstKV@SetIf{#1}\if@SX@attachfile}
41 \newcommand*\SX@graphicname{}%
42 \newcommand*\SX@graphicparam{}%
```

```

43 \lst@Key{graphic}{[]}{%
44   \lstKV@OptArg[width=\linewidth]{#1}{%
45     \edef\SX@graphicparam{##1}\edef\SX@graphicname{##2}%
46   }%
47 }%
48 \newbox\SX@ResBox
49 \newcommand\ResultBox{} \let\ResultBox=\fbox
50 \newdimen\ResultBoxSep \ResultBoxSep=\fboxsep
51 \newdimen\ResultBoxRule \ResultBoxRule=\fboxrule
52 \newcommand*\SX@pos{}%
53 \newcommand*\SX@width{}%
54 \newcommand*\SX@hsep{}%
55 \newcommand*\SX@vsep{}%
56 \newcommand*\SX@overhang{}%
57 \newcommand*\SX@rframe{}%
58 \newcommand\SX@preset{}%
59 \newcommand*\SX@explpreset{}%

60 \newcommand*\SX@explpreset{}%
61 \newcommand*\SX@codefile{} \edef\SX@codefile{\jobname.tmp}%
62 \newcommand*\SX@justification{\raggedright}

```

\SX@preset Contains some redefinitions of L^AT_EX macros and environments to do nothing. **\SX@preset** will be called just before typesetting the result of the example code. More can be added with the user key “**preset=...**”.

```

63 \newcommand*\SX@preset{%
64   \renewcommand\documentclass[2][]{\SX@eat@version}%
65   \renewcommand\usepackage[2][]{\SX@eat@version}%
66   \renewenvironment{document}{}{}%
67   \renewcommand\cite[1][]{\relax}%
68   \let\tableofcontents\relax \let\listoffigures\relax
69   \let\listoftables\relax \let\printindex\relax
70   \let\listfiles\relax \let\nofiles\relax
71   \let\index\gobble \let\label\gobble
72   \let\refstepcounter\stepcounter
73   \let\bibliography\gobble
74   \let\pagestyle\gobble \let>thispagestyle\gobble
75   %\let\immediate\relax \let\write\gobbletwo
76   %\let\closeout\gobble \let\@input\gobble
77   \renewcommand\marginpar[2][]{\relax}%
78   \renewcommand\footnote[2][]{\relax}%
79   \let\@footnotetext\gobble
80   %%\abovedisplayskip=\z@
81   %%\abovedisplayshortskip=\z@
82 }%
83 \newcommand*\SX@eat@version[1][]{}

```

\isSX@odd Parameter #1 is executed on odd pages, parameter #2 on even pages.

```

84 \newif\ifSX@wasodd
85 \if@twoside
86   \newcommand*\isSX@odd{%
87     \begingroup
88       \ifodd\getpagerefnumber{\SX@IDENT}%
89         \aftergroup\SX@wasoddtrue

```

```

90      \else
91          \aftergroup\SX@wasoddfalse
92      \fi
93  \endgroup
94  \ifSX@wasodd
95      \expandafter\@firstoftwo
96  \else
97      \expandafter\@secondoftwo
98  \fi
99 }
100 \else
101   \SX@wasoddtrue
102   \newcommand*\isSX@odd[2]{#1}
103 \fi

```

The call of `\isSX@odd` sets also `\ifSX@wasodd` to true or false. If it's clear that no page break occurs, `\ifSX@wasodd` can be used.

```

104 \newcounter{ltxexample}
105 \newcommand*\{SX@IDENT}{SX@number\value{ltxexample}}

```

`\SX@attachfile`

```

106 \newcommand*\SX@attachfile{%
107   \if@SX@attachfile
108     \attachfile[mimetype=text/plain,subject={example \theltxexample}]%
109     {\SX@codefile}{}%
110   \fi
111 }

```

`\SX@put@t/b/l/r/o/i` Six macros for positioning #2 (result) and #3 (code). The result can be `above`, `below`, `left` or `right` of the code area or on the `outer` or `inner` side. Parameter #1 is the width of the result.

```

112 \newcommand*\SX@put@t[3]{%
113   \SX@ResultArea{\linewidth}{#2}\endgraf\pagebreak[2]%
114   \tempdima=\dimexpr\SX@vsep\vskip\tempdima
115   \SX@CodeArea{\linewidth}{#3}%
116 }
117 \newcommand*\SX@put@b[3]{%
118   \SX@CodeArea{\linewidth}{#3}\endgraf\pagebreak[2]%
119   \tempdima=\dimexpr\SX@vsep\vskip\tempdima
120   \SX@ResultArea{\linewidth}{#2}%
121 }
122 \newcommand*\SX@put@l[3]{%
123   \tempdimc=\dimexpr\linewidth-#1-\SX@hsep %
124   \SX@ResultArea{#1}{#2}\hfill\SX@CodeArea{\tempdimc}{#3}%
125 }
126 \newcommand*\SX@put@r[3]{%
127   \tempdimc=\dimexpr\linewidth-#1-\SX@hsep %
128   \SX@CodeArea{\tempdimc}{#3}\hfill\SX@ResultArea{#1}{#2}%
129 }
130 \newcommand*\SX@put@o[3]{%
131   \nameuse{\SX@put@}{\ifSX@wasodd r\else l\fi}{#1}{#2}{#3}%
132 }
133 \newcommand*\SX@put@i[3]{%
134   \nameuse{\SX@put@}{\ifSX@wasodd l\else r\fi}{#1}{#2}{#3}%

```

```

135 }
136 \newcommand{\SX@ResultArea}[2]{%
137   \SX@justification\tempdima=\dimexpr #1 %
138   \parbox{\tempdima}{#2}%
139 }
140 \newcommand{\SX@CodeArea}[2]{%
141   \tempdima=\dimexpr #1 %
142   \sbox{\tempboxa}{\parbox{\tempdima}{#2}}%
143   \tempdima=\dp\tempboxa\usebox{\tempboxa}
144   \rlap{\raisebox{-\tempdima}[0pt][0pt]{\SX@attachfile}}%
145 }
146 \newcommand*\SX@KillAboveCaptionskip{%
147   \ifx\lst@caption\empty\else
148     \lst@ifsubstring t\lst@captionpos
149       {\vskip-\abovecaptionskip}{}%
150   \fi
151 }
152 \newcommand*\SX@KillBelowCaptionskip{%
153   \ifx\lst@caption\empty\else
154     \lst@ifsubstring b\lst@captionpos
155       {\vskip-\belowcaptionskip}{}%
156   \fi
157 }

```

LTXexample

```

158 \lstnewenvironment{LTXexample}[1][]{%
159   \tempokena{#1}%
160   \begingroup
    For "codefile=..."/"graphic=..." if \theltxexample or \thelstlisting is part of
    the filename.
161   \advance\c@ltxexample@ne \advance\c@lstlisting@ne
162   \expandafter\lstset\expandafter{\SX@explpreset,\#1}%
163   \edef\x{\endgroup
164     \def\noexpand\SX@codefile{\SX@codefile}%
165     \def\noexpand\SX@graphicname{\SX@graphicname}%
166     \def\noexpand\SX@graphicparam{\SX@graphicparam}}%
167   \x
168   \xdef\SX@@explpreset{\the\tempokena,codefile=\SX@codefile,%
169     graphic=[\SX@graphicparam]{\SX@graphicname}}%
170   \setbox\tempboxa=\hbox\bgroup
171   \lst@BeginWriteFile{\SX@codefile}%
172 }
173 {%
174   \lst@EndWriteFile\egroup
175   \SX@put@code@result
176 }

```

\SX@put@code@result

```

177 \newcommand*\SX@put@code@result{%
178   \begingroup
179     \expandafter\lstset\expandafter{\SX@explpreset}%
180     \expandafter\lstset\expandafter{\SX@@explpreset}%

```

Use listings floating procedure if necessary.

```
181      \ifx\lst@float\relax\else
182          \edef\@tempa{\noexpand\lst@beginfloat{lstlisting}[\lst@float]}
183          \expandafter\@tempa
184      \fi
185      \ifx\lst@caption\empty
186          \lstset{nolol=true}%
187      \fi
188      \if@SX@wide\def\SX@overhang{\marginparwidth+\marginparsep}\fi
189      \trivlist\item\relax
190          \stepcounter{ltxexample}\label{\SX@IDENT}%

```

Make $\SX@width$ a real dimension if the unit is missing.

```
191      \SX@defaultWD\SX@width{\SX@width}%

```

Set the default width if necessary.

```
192      \ifdim\SX@width<\z@
193          \tempswatrue
194          \def\@tempa{t}%
195          \ifx\@tempa\SX@pos\tempswafalse\fi
196          \def\@tempa{b}%
197          \ifx\@tempa\SX@pos\tempswafalse\fi
198          \tempdima=\dimexpr\linewidth+\SX@overhang %
199          \if@tempswa\tempdima=.5\tempdima\fi%
200          \edef\SX@width{\the\tempdima}%
201      \fi

```

Correct $\SX@width$ if a frame is requested.

```
202      \ifx\SX@rframe\empty
203          \long\def\SX@frame##1##1}%
204      \else
205          \let\SX@frame\ResultBox
206          \tempdima=\dimexpr\SX@width-2\ResultBoxSep-2\ResultBoxRule %
207          \edef\SX@width{\the\tempdima}%
208      \fi
209      \isSX@odd{\def\@tempa{1}}{\def\@tempa{r}}%
210      \makebox[\linewidth]{\@tempa}%
211          \parbox{\dimexpr\linewidth+\SX@overhang}{%

```

$\SX@codefile$ ($\jobname.\tmp$) is not necessary for the filelist.

```
212          \let\@addtofilelist@gobble
213          \let\lst@ifdisplaystyle\iftrue
214          \SX@KillAboveCaptionskip\lst@MakeCaption{t}%

```

Use the “natural” width of the result code if “varwidth” is true. .

```
215          \setbox\SX@ResBox\hbox{%
216              \fboxsep=\ResultBoxSep
217              \fboxrule=\ResultBoxRule
218              \SX@frame{%
219                  \nameuse{\if@SX@varwidth varwidth\else minipage\fi}%
220                  \SX@width\relax
221                  \begin{group}
222                      \SX@resultInput
223                  \end{group}
224                  \nameuse{\end\if@SX@varwidth varwidth\else minipage\fi}%
225              \edef\SX@width{\the\wd\SX@ResBox}%

```

```

226          \@ifundefined{SX@put@\SX@pos}%
227              {\@latex@error{Parameter `'\SX@pos' undefined}\@ehd}%
228              {\@nameuse{SX@put@\SX@pos}%
229                  {\SX@width}{\box\SX@ResBox}{\SX@codeInput}}%
230                  \lst@MakeCaption{b}\SX@KillBelowCaptionskip
231          }%
232      }%
233  \endtrivlist
234  \ifx\lst@float\relax\else\expandafter\lst@endfloat\fi
235  \gdef\SX@explpreset{}%
236  \endgroup
237 }

238 \newcommand{\SX@SkipToFirst}{%
239   \ifeof\@inputcheck\else
240     \ifnum \lst@lineno=\lst@firstline\else
241       \readline\@inputcheck to\SX@tempa
242       \typeout{IGNORE (\the\lst@lineno)}%
243       \global\advance\lst@lineno\@ne
244       \SX@SkipToFirst
245     \fi
246   \fi
247 }
248 \newcommand{\SX@ProcessResult}{%
249   \ifeof\@inputcheck
250     \let\SX@tempb\relax
251   \else
252     \let\SX@tempb\SX@ProcessResult
253     \ifnum \lst@lineno>\lst@lastline\relax
254       \ifx\lst@linerange\@empty
255         \let\SX@tempb\relax
256       \else
257         \lst@GetLineInterval
258         \SX@SkipToFirst
259       \fi
260     \else
261       \readline\@inputcheck to\SX@tempa
262       \typeout{READ (\the\lst@lineno)}%
263       \expandafter\g@addto@macro
264         \expandafter\SX@lines\expandafter{\SX@tempa^J}%
265       \global\advance\lst@lineno\@ne
266     \fi
267   \fi
268   \SX@tempb
269 }

\SX@input
270 \newcommand{\SX@input[1]}{%
271   \begingroup
272   \IfFileExists{#1}{}{%
273   {%
274     \filename@parse{#1}%
275     \ifx\filename@ext\relax \def\filename@ext{tex}\fi
276     \@latexerr{File

```

```

277   '\filename@area\filename@base.\filename@ext' not found.^^J^^J}\@ehd%
278 }%
279 \openin\@inputcheck#1
280 \lsthk@PreSet\let\lst@linerange\@empty\global\lst@lineno\@ne
281 \expandafter\lstset\expandafter{\SX@explpreset}%
282 \ifx\lst@linerange\@empty
283   \edef\lst@linerange{\{\lst@firstline}-{\lst@lastline},}%
284 \fi
285 \lst@GetLineInterval
286 \SX@Info
287 \newlinechar='^^J\relax
288 \SX@SkipToFirst\let\SX@lines\@empty
289 \SX@ProcessResult
290 \closein\@inputcheck
291 \scantokens\expandafter{\SX@lines}%
292 \endgroup
293 }

294 \newcommand*\SX@Info{%
295   \typeout{-----}%
296   \typeout{pos=\SX@pos}%
297   \typeout{width=\SX@width}%
298   \typeout{hsep=\SX@hsep}%
299   \typeout{vsep=\SX@vsep}%
300   \typeout{overhang=\SX@overhang}%
301   \typeout{rframe=\SX@rframe}%
302   \typeout{codefile=\SX@codefile}%
303   \@ifundefined{lst@firstline}{}{%
304     {\typeout{\string\lst@firstline=\lst@firstline}}%
305   \@ifundefined{lst@lastline}{}{%
306     {\typeout{\string\lst@lastline=\lst@lastline}}%
307   \@ifundefined{lst@linerange}{}{%
308     {\typeout{\string\lst@linerange=\lst@linerange}}%
309   \typeout{\string\if@SX@wide=\if@SX@wide TRUE\else FALSE\fi}%
310   \typeout{\string\if@SX@orangeaccept=\if@SX@orangeaccept TRUE\else FALSE\fi}%
311   \typeout{\string\if@SX@varwidth=\if@SX@varwidth TRUE\else FALSE\fi}%
312   \typeout{graphicfile=\SX@graphicname, graphicparameter=[\SX@graphicparam]}%
313   \typeout{-----}%
314 }%
315 \providecommand*\MakePercentIgnore{\catcode`\%9\relax}
316 \providecommand*\MakePercentComment{\catcode`\%14\relax}

\SX@resultInput
317 \newcommand*\SX@resultInput{%
318   \ifx\SX@graphicname\@empty
319     \begingroup
320       \MakePercentComment\makeatother\catcode`\^^M=5\relax
321       \SX@Cpreset\SX@preset
322       \if@SX@orangeaccept
323         \let\SX@tempa=\SX@input
324       \else
325         \let\SX@tempa=\input
326       \fi
327       \if\SX@scaled ?%

```

```

328      \let\SX@tempb=\@firstofone
329      \else
330          \if\SX@scaled !%
331              \def\SX@tempb##1{\resizebox{\SX@width}{!}{##1}}%
332          \else
333              \def\SX@tempb##1{\scalebox{\SX@scaled}{##1}}%
334          \fi
335      \fi
336      \let\SX@lst@Init=\lst@Init

```

Prevents float environments from floating. This is not enough for floating listing environments! Why?

```

337      \def\xffloat##1[##2]{%
338          \def\@capttype{##1}%
339          \cnamedef{the\@capttype}{0}%
340          \cfloat@HH{##1}[H] }%

```

Special handling of floating listing environments.

```

341      \def\lst@Init{%
342          \let\lst@float=\relax
343          \setcounter\@capttype{-1}%
344          \SX@lst@Init
345      }

```

Typeset the Code.

```

346      \SX@tempb{\SX@tempa{\SX@codefile}}\par

```

Restore the regular numbering of floats outside of ‘LTXexample’.

```

347      \endgroup
348      \else
349          \expandafter\includegraphics\expandafter[\SX@graphicparam]%
350          {\SX@graphicname}%
351      \fi
352  }

```

\SX@codeInput

```

353 \newcommand*\SX@codeInput{%

```

Without a caption entry the command \lstinputlisting adds the filename to the “list of listings” (lol). This should be avoided.

```

354 \begingroup

```

The default parameters for all examples.

```

355 \expandafter\lstset\expandafter{\SX@explpreset}%

```

If “numbers=none” then margin dimensions should be zero.

```

356 \expandafter\lstset\expandafter{\SX@@explpreset}%
357 \ifx\lst@PlaceNumber\empty
358     \g@addto@macro\SX@@explpreset{,xleftmargin=0pt,xrightmargin=0pt}%
359 \fi
360 \SX@Info
361 \expandafter\lstinputlisting\expandafter[\SX@@explpreset,nolol=true,%
362     caption={},belowskip=\z@,aboveskip=\z@,float=false]{\SX@codefile}%
363 \endgroup
364 }%

```

```

365 \newcommand*\LTXinputExample[2][]{%
366   \g@addto@macro{\SX@@explpreset{float=false,#1,codefile=#2}}%
367   \SX@put@code@result}%

    All the default values.

368 \lstset{explpreset={numbers=left,numberstyle=\tiny,numbersep=.3em,
    Negative width means defaults.

369 xleftmargin=1em,columns=flexible,language=[LaTeX]TEX, pos=l, width=-99pt,
370 overhang=0pt,hsep=\columnsep,vsep=\bigskipamount,rframe=single}

.

371 \AtBeginDocument{%
372   \def\theHlistnumber{\thelstlisting.\arabic{lstnumber}. \lst@neglisting}%
373 }

    Changing the defaults possible in showexpl.cfg.

374 \InputIfFileExists{showexpl.cfg}{}{}
```

Change History

v0.1a	General: “hpos” and “vpos” added, “pos” removed (RN).	v0.1k	General: “rangeaccept” added (RN).	3
	Initial version		\SX@put@t/b/l/r/o/i: Change [a]bove to [t]op (RN).	5
v0.1b	\SX@put@t/b/l/r/o/i: Positioning the captions more independend of the result and code area (RN).	v0.1l	General: Some bug corrections (RN).	3
v0.1c	\SX@put@t/b/l/r/o/i: Commands \SX@KillAboveCaptionskip and \SX@KillBelowCaptionskip added (RN).	v0.1m	General: Problem related to \label/\ref solved (RN).	6
v0.1f	General: “lstpreset” added. (RN).	v0.2b	General: “varwidth” and “justification” added (RN).	3
v0.1h	General: “codefile” added. (RN).	v0.2a	“varwidth” package used (RN).	6
	“lstpreset” renamed to “explpreset” (RN).		General: Check if \SX@put@? is defined (RN).	6
	New macro \LTXinputExample (RN).	v0.3a	\SX@attachfile: Attach file functionality (with pdfTeX) added (RN).	5
	Renamed from “example” to “LTXexample” (RN).	v0.3b	General: “attachfile” added (RN).	3
v0.1i	General: Better caption positioning and correct distance between the parts (RN).	v0.3c	\SX@resultInput: Input of result code now inside a group; \makeatother added (RN).	9
v0.1j	\SX@input: For ranges of lines (RN).		\SX@resultInput: Wrong catcode for newline char corrected (RN).	9

v0.3d	\SX@resultInput: Missing \par added (RN).	9	v0.3l	General: Definition for “hyperref” (suggested by Heiko Oberdiek)	11
v0.3e	\SX@preset: More redefinitions added (RN).	4		\SX@resultInput: Code for “scaled” option (RN).	9
v0.3g	General: \SX@ProcessResult is now working correctly using \readline and \scantokens. Thanks to Ulrich Diez for help (RN).	8		General: Option “scaled” and \SX@scaled added (RN).	3
	Missing \newcommand for \SX@explpreset added (RN). . .	4	v0.3m	\SX@put@code@result: Wrong assignement for \lst@belowskip (RN).	7
v0.3h	General: New Option ‘attachfiles’ (RN).	3	v0.3n	\SX@put@code@result: Use \ResultBox	7
v0.3j	\SX@put@code@result: Setting \lst@MakeCaption to was a bad idea for hyperlinks. Group added to varwidth environment. (Suggestions by Ulrike Fischer.).	7		General: Define \ResultBox etc.	3
v0.3k	\SX@put@code@result: Setting \lst@MakeCaption to \@gobble again (prevent multiply defined labels; label key)	7		Prevent utf8 encoding errors	6
			v0.3p	\SX@preset: Remove extra treatment of ‘figure’/‘table’ (RN).	4
				\SX@put@code@result: Let’s leave \lst@MakeCaption untouched (RN).	7
				\SX@resultInput: Better handling of floats (RN).	10
				\isSX@odd: Replace \isodd with \ifodd\getpagerefnumber (remove package ‘ifthen’) (RN). . .	4
				General: Remove package ‘calc’ (RN).	3

Index

Numbers written in italic refer to the page where the corresponding entry is described; numbers underlined refer to the code line of the definition; numbers in roman refer to the code lines where the entry is used.

Symbols			
\%	314, 315	\@gobbletwo	74
\@@input	75	\@inputcheck 238, 240,	248, 260, 278, 289
\CSX@attachfilefalse	36	\@latex@error	226
\CSX@rangeacceptfalse	33	\@latexerr	275
\CSX@varwidthfalse	34	\@secondoftwo	96
\CSX@widefalse	35	\@temptokena	158, 167
\addtolist	211	\@xfloat	335, 337, 343
\ehd	226, 276	\^	286, 319
\firstfone	327		
\firstftwo	94	A	
\float@HH	337	\abovecaptionskip	148
\footnotetext	78	\abovedisplayshortskip	80
\gobble	71–73, 75, 78, 211	\abovedisplayskip	79
		\closein	289
		\closeout	75
		\columns	368
		B	
		\belowcaptionskip	154
		\bibliography	72
		\bigskipamount	368
		\box	228
		C	
		\c@lstlisting	160
		\c@ltxexample	160
		\cite	67
		\closein	289
		\closeout	75
		\columns	368

D	P
\dimexpr .. 113, 118, 122, 126, 136, 140, 197, 205, 210	\lst@firstline 239, 282, 303 \lst@float 180, 181, 233, 339 \lst@GetLineInterval 256, 284
E	
\endgraf 112, 117 environments: LTXexample ... 1, <u>157</u>	\lst@ifdisplaystyle 212 \lst@IfSubstring 147, 153 \lst@Init .. 336, 338, 344 \lst@Key 21–28, 30–32, 37–40, 43 \lst@lastline 252, 282, 305 \lst@lineno 239, 241, 242, 252, 261, 264, 279 \lst@linerange 253, 279, 281, 282, 307 \lst@MakeCaption 213, 229
F	
\fbox 49 \fboxrule 51, 216 \fboxsep 50, 215 \filename@area 276 \filename@base 276 \filename@ext . 274, 276 \filename@parse 273 \footnote 77	\lst@neglisting ... 370 \lst@PlaceNumber .. 355 \lst@RequireAspects 16 \lsthk@PreSet 279 \lstinputlisting ... 359 \lstKV@OptArg 44 \lstKV@SetIf 26, 37, 38, 40 \lstnewenvironment .. 157 \lstset 161, 178, 179, 185, 280, 353, 354, 366 LTXexample (environ- ment) 1, <u>157</u> \LTXinputExample 1, 363
G	
\g@addto@macro 262, 356, 364 \getpagerefnumber . 87	
I	
\if@SX@attachfile 36, 40, 106 \if@SX@rangeaccept 33, 37, 309, 321 \if@SX@varwidth ... 34, 38, 218, 223, 310 \if@SX@wide 26, 35, 187, 308 \if@twoside 84 \ifeof 238, 248 \IfFileExists .. 10, 271 \ifSX@wasodd 83, 93, 130, 133 \immediate 74 \includegraphics .. 347 \index 71 \isSX@odd .. <u>83</u> , 208	\lstinputlisting ... 359 \lstKV@OptArg 44 \lstKV@SetIf 26, 37, 38, 40 \lstnewenvironment .. 157 \lstset 161, 178, 179, 185, 280, 353, 354, 366 LTXexample (environ- ment) 1, <u>157</u> \LTXinputExample 1, 363
L	
\label 71, 189 \listoffigures 68 \listoftables 69 \lst@beginfloat ... 181 \lst@BeginWriteFile 170 \lst@caption 146, 152, 184 \lst@captionpos 147, 153 \lst@endfloat 233 \lst@EndWriteFile .. 173	\makeatother 319 \makebox 209 \MakePercentComment 315, 319 \MakePercentIgnore .. 314 \marginpar 76 \marginparsep 187 \marginparwidth ... 187 N
	\newbox 48 \newdimen 50, 51 \newlinechar 286 O
	\openin 278

\SX@justification	39, 62, 136	\SX@put@t/b/l/r/o/i 111	\SX@wasoddfalse	90
\SX@KillAboveCaptionskip	145, 213	\SX@ResBox	\SX@wasoddtrue	88, 100
\SX@KillBelowCaptionskip	151, 229	\SX@ResultArea 112,	\SX@width	22, 53,
\SX@lines	263, 287, 290	119, 123, 127, 135	190, 191, 199,	
\SX@list@Init	336, 340, 344	\SX@resultInput 221, 316	205, 206, 219,	
\SX@overhang	25, 56, 187, 197, 210, 299	\SX@rfframe	224, 228, 296, 330	
\SX@pos	21, 52, 194, 196, 225–227, 295	\SX@scaled	\SX@xfloat	335, 343
\SX@preset	28, 58, 320	29, 30, 326, 329, 332	\theHlistnumber	370
\SX@ProcessResult	247, 251, 288	\SX@SkipToFirst	\thelstlisting	370
\SX@put@code@result	174, 176, 365	237, 243, 257, 287	\theltexample	107
\SX@put@t	111	\SX@tempa	\thispagestyle	73
		240, 260, 263, 322, 324, 342		
		\SX@tempb	\usebox	142
		249, 251, 254, 267, 327, 330, 332, 342		
		\SX@vsep	\write	74