

# The package **nicematrix**<sup>\*</sup>

F. Pantigny  
fpantigny@wanadoo.fr

January 22, 2020

## Abstract

The LaTeX package **nicematrix** provides new environments similar to the classical environments **{array}** and **{matrix}** but with some additional features. Among these features are the possibilities to fix the width of the columns and to draw continuous ellipsis dots between the cells of the array.

## 1 Presentation

This package can be used with **xelatex**, **lualatex**, **pdflatex** but also by the classical workflow **latex-dvips-ps2pdf** (or Adobe Distiller). Two or three compilations may be necessary. This package requires and **loads** the packages **expl3**, **l3keys2e**, **xparse**, **array**, **amsmath** and **tikz**. It also loads the **Tikz** library **fit**. The final user only has to load the extension with **\usepackage{nicematrix}**.

This package provides some new tools to draw mathematical matrices. The main features are the following:

- continuous dotted lines<sup>1</sup>;
- exterior rows and columns for labels;
- a control of the width of the columns.

A command **\NiceMatrixOptions** is provided to fix the options (the scope of the options fixed by this command is the current TeX group).

### An example for the continuous dotted lines

For example, consider the following code which uses an environment **{pmatrix}** of **amsmath**.

```
$A = \begin{pmatrix}
1 & \cdots & \cdots & 1 \\
0 & \ddots & & \vdots \\
\vdots & \ddots & \ddots & \vdots \\
0 & \cdots & 0 & 1
\end{pmatrix}
```

This code composes the matrix  $A$  on the right.

$$A = \begin{pmatrix} a_{11} & a_{12} & \cdots & a_{1n} \\ a_{21} & a_{22} & \cdots & a_{2n} \\ \vdots & \vdots & \ddots & \vdots \\ a_{n1} & a_{n2} & \cdots & a_{nn} \end{pmatrix}$$

$$A = \begin{pmatrix} 1 & \cdots & \cdots & 1 \\ 0 & \ddots & & \vdots \\ \vdots & \ddots & \ddots & \vdots \\ 0 & \cdots & 0 & 1 \end{pmatrix}$$

Now, if we use the package **nicematrix** with the option **transparent**, the same code will give the result on the right.

$$A = \begin{pmatrix} 1 & \cdots & \cdots & 1 \\ 0 & \cdots & \cdots & \vdots \\ \vdots & \cdots & \cdots & \vdots \\ 0 & \cdots & 0 & 1 \end{pmatrix}$$

<sup>\*</sup>This document corresponds to the version 3.10 of **nicematrix**, at the date of 2020/01/22.

<sup>1</sup>If the class option **draft** is used, these dotted lines will not be drawn for a faster compilation.

## 2 The environments of this extension

The extension `nicematrix` defines the following new environments.

```
{NiceMatrix}   {NiceArray}   {pNiceArray}
{pNiceMatrix}  {bNiceArray}
{bNiceMatrix}  {BNiceArray}
{BNiceMatrix}  {vNiceArray}
{vNiceMatrix}  {VNiceArray}
{VNiceMatrix}  {NiceArrayWithDelims}
```

By default, the environments `{NiceMatrix}`, `{pNiceMatrix}`, `{bNiceMatrix}`, `{BNiceMatrix}`, `{vNiceMatrix}` and `{VNiceMatrix}` behave almost exactly as the corresponding environments of `amsmath`: `{matrix}`, `{pmatrix}`, `{bmatrix}`, `{Bmatrix}`, `{vmatrix}` and `{Vmatrix}`.

The environment `{NiceArray}` is similar to the environment `{array}` of the package `{array}`. However, for technical reasons, in the preamble of the environment `{NiceArray}`, the user must use the letters `L`, `C` and `R` instead of `l`, `c` and `r`. It's possible to use the constructions `w{...}{...}`, `W{...}{...}`<sup>2</sup>, `|`, `>{...}`, `<{...}`, `@{...}`, `!{...}` and `*{n}{...}` but the letters `p`, `m` and `b` should not be used. See p. 7 the section relating to `{NiceArray}`.

## 3 The continuous dotted lines

Inside the environments of the extension `nicematrix`, new commands are defined: `\Ldots`, `\Cdots`, `\Vdots`, `\Ddots`, and `\Iddots`. These commands are intended to be used in place of `\dots`, `\cdots`, `\vdots`, `\ddots` and `\iddots`.<sup>3</sup>

Each of them must be used alone in the cell of the array and it draws a dotted line between the first non-empty cells<sup>4</sup> on both sides of the current cell. Of course, for `\Ldots` and `\Cdots`, it's an horizontal line; for `\Vdots`, it's a vertical line and for `\Ddots` and `\Iddots` diagonal ones.

```
\begin{bNiceMatrix}
a_1 & \Cdots & & a_1 \\
\Vdots & a_2 & \Cdots & a_2 \\
& \Vdots & \Ddots & \\
& a_1 & a_2 & & a_n
\end{bNiceMatrix}
```

$$\begin{bmatrix} a_1 & \cdots & a_1 \\ \vdots & a_2 & \cdots & a_2 \\ \vdots & \vdots & \ddots & \vdots \\ a_1 & a_2 & \cdots & a_n \end{bmatrix}$$

In order to represent the null matrix, one can use the following codage:

```
\begin{bNiceMatrix}
0 & \Cdots & 0 \\
\Vdots & & \Vdots \\
0 & \Cdots & 0
\end{bNiceMatrix}
```

$$\begin{bmatrix} 0 & \cdots & 0 \\ \vdots & & \vdots \\ 0 & \cdots & 0 \end{bmatrix}$$

However, one may want a larger matrix. Usually, in such a case, the users of `LaTeX` add a new row and a new column. It's possible to use the same method with `nicematrix`:

```
\begin{bNiceMatrix}
0 & \Cdots & \Cdots & 0 \\
\Vdots & & & \Vdots \\
\Vdots & & & \Vdots \\
0 & \Cdots & \Cdots & 0
\end{bNiceMatrix}
```

$$\begin{bmatrix} 0 & \cdots & \cdots & 0 \\ \vdots & & & \vdots \\ \vdots & & & \vdots \\ 0 & \cdots & \cdots & 0 \end{bmatrix}$$

<sup>2</sup>However, for the columns of type `w` and `W`, the cells are composed in math mode (in the environments of `nicematrix`) whereas in `{array}` of `array`, they are composed in text mode.

<sup>3</sup>The command `\iddots`, defined in `nicematrix`, is a variant of `\ddots` with dots going forward:  $\cdots$ . If `mathdots` is loaded, the version of `mathdots` is used. It corresponds to the command `\adots` of `unicode-math`.

<sup>4</sup>The precise definition of a “non-empty cell” is given below (cf. p. 16).

In the first column of this exemple, there are two instructions `\Vdots` but only one dotted line is drawn (there is no overlapping graphic objects in the resulting PDF<sup>5</sup>).

In fact, in this example, it would be possible to draw the same matrix more easily with the following code:

```
\begin{bNiceMatrix}
0 & \Cdots & & 0 \\
\Vdots & & & \\
& & & \Vdots \\
0 & & \Cdots & 0
\end{bNiceMatrix}
```

$$\begin{bmatrix} 0 & \cdots & 0 \\ \vdots & & \vdots \\ \vdots & & \vdots \\ 0 & \cdots & 0 \end{bmatrix}$$

There are also other means to change the size of the matrix. Someone might want to use the optional argument of the command `\\"\\` for the vertical dimension and a command `\hspace*` in a cell for the horizontal dimension.<sup>6</sup>

However, a command `\hspace*` might interfer with the construction of the dotted lines. That's why the package `nicematrix` provides a command `\Hspace` which is a variant of `\hspace` transparent for the dotted lines of `nicematrix`.

```
\begin{bNiceMatrix}
0 & \Cdots & \Hspace*[1cm] & 0 \\
\Vdots & & & \Vdots \\[1cm]
0 & \Cdots & & 0
\end{bNiceMatrix}
```

$$\begin{bmatrix} 0 & \cdots & 0 \\ \vdots & & \vdots \\ 0 & \cdots & 0 \end{bmatrix}$$

### 3.1 The option `nullify-dots`

Consider the following matrix composed classically with the environment `{pmatrix}` of `amsmath`.

```
$A = \begin{pmatrix}
a_0 & b \\
a_1 & \\
a_2 & \\
a_3 & \\
a_4 & \\
a_5 & b
\end{pmatrix}
```

$$A = \begin{pmatrix} a_0 & b \\ a_1 & \\ a_2 & \\ a_3 & \\ a_4 & \\ a_5 & b \end{pmatrix}$$

If we add `\vdots` instructions in the second column, the geometry of the matrix is modified.

```
$B = \begin{pmatrix}
a_0 & b \\
a_1 & \vdots \\
a_2 & \vdots \\
a_3 & \vdots \\
a_4 & \vdots \\
a_5 & b
\end{pmatrix}
```

$$B = \begin{pmatrix} a_0 & b \\ a_1 & \vdots \\ a_2 & \vdots \\ a_3 & \vdots \\ a_4 & \vdots \\ a_5 & b \end{pmatrix}$$

---

<sup>5</sup> And it's not possible to draw a `\Ldots` and a `\Cdots` line between the same cells.

<sup>6</sup> In `nicematrix`, one should use `\hspace*` and not `\hspace` for such an usage because `nicematrix` loads `array`. One may also remark that it's possible to fix the width of a column by using the environment `{NiceArray}` (or one of its variants) with a column of type `w` or `W`: see p. 10

By default, with `nicematrix`, if we replace `{pmatrix}` by `{pNiceMatrix}` and `\vdots` by `\Vdots`, the geometry of the matrix is not changed.

```
$C = \begin{pNiceMatrix}
a_0 & b \\
a_1 & \Vdots \\
a_2 & \Vdots \\
a_3 & \Vdots \\
a_4 & \Vdots \\
a_5 & b
\end{pNiceMatrix}$
```

$$C = \begin{pmatrix} a_0 & b \\ a_1 & \vdots \\ a_2 & \vdots \\ a_3 & \vdots \\ a_4 & \vdots \\ a_5 & b \end{pmatrix}$$

However, one may prefer the geometry of the first matrix  $A$  and would like to have such a geometry with a dotted line in the second column. It's possible by using the option `nullify-dots` (and only one instruction `\Vdots` is necessary).

```
$D = \begin{pNiceMatrix}[nullify-dots]
a_0 & b \\
a_1 & \Vdots \\
a_2 & \\
a_3 & \\
a_4 & \\
a_5 & b
\end{pNiceMatrix}$
```

$$D = \begin{pmatrix} a_0 & b \\ a_1 & \vdots \\ a_2 & \vdots \\ a_3 & \vdots \\ a_4 & \vdots \\ a_5 & b \end{pmatrix}$$

The option `nullify-dots` smashes the instructions `\Ldots` (and the variants) vertically but also horizontally.

**There must be no space before the opening bracket (`[`) of the options of the environment.**

## 3.2 The command `\Hdotsfor`

Some people commonly use the command `\hdotsfor` of `amsmath` in order to draw horizontal dotted lines in a matrix. In the environments of `nicematrix`, one should use instead `\Hdotsfor` in order to draw dotted lines similar to the other dotted lines drawn by the package `nicematrix`.

As with the other commands of `nicematrix` (like `\Cdots`, `\Ldots`, `\Vdots`, etc.), the dotted line drawn with `\Hdotsfor` extends until the contents of the cells on both sides.

```
$\begin{pNiceMatrix}
1 & 2 & 3 & 4 & 5 \\
1 & \Hdotsfor{3} & 5 \\
1 & 2 & 3 & 4 & 5 \\
1 & 2 & 3 & 4 & 5
\end{pNiceMatrix}$
```

$$\begin{pmatrix} 1 & 2 & 3 & 4 & 5 \\ 1 & \cdots & & & 5 \\ 1 & 2 & 3 & 4 & 5 \\ 1 & 2 & 3 & 4 & 5 \end{pmatrix}$$

However, if these cells are empty, the dotted line extends only in the cells specified by the argument of `\Hdotsfor` (by design).

```
$\begin{pNiceMatrix}
1 & 2 & 3 & 4 & 5 \\
& \Hdotsfor{3} \\
1 & 2 & 3 & 4 & 5 \\
1 & 2 & 3 & 4 & 5
\end{pNiceMatrix}$
```

$$\begin{pmatrix} 1 & 2 & 3 & 4 & 5 \\ & \cdots & & & \\ 1 & 2 & 3 & 4 & 5 \\ 1 & 2 & 3 & 4 & 5 \end{pmatrix}$$

The command `\hdotsfor` of `amsmath` takes an optional argument (between square brackets) which is used for fine tuning of the space between two consecutive dots. For homogeneity, `\Hdotsfor` has also an optional argument but this argument is discarded silently.

Remark: Unlike the command `\hdotsfor` of `amsmath`, the command `\Hdotsfor` may be used when the extension `colortbl` is loaded (but you might have problem if you use `\rowcolor` on the same row as `\Hdotsfor`).

### 3.3 How to generate the continuous dotted lines transparently

The package `nicematrix` provides an option called `transparent` for using existing code transparently in the environments of the `amsmath` : `{matrix}`, `{pmatrix}`, `{bmatrix}`, etc. In fact, this option is an alias for the conjunction of two options: `renew-dots` and `renew-matrix`.<sup>7</sup>

- The option `renew-dots`

With this option, the commands `\ldots`, `\cdots`, `\vdots`, `\ddots`, `\iddots`<sup>3</sup> and `\hdotsfor` are redefined within the environments provided by `nicematrix` and behave like `\Ldots`, `\Cdots`, `\Vdots`, `\Ddots`, `\Iddots` and `\Hdotsfor`; the command `\dots` (“automatic dots” of `amsmath`) is also redefined to behave like `\Ldots`.

- The option `renew-matrix`

With this option, the environment `{matrix}` is redefined and behave like `{NiceMatrix}`, and so on for the five variants.

Therefore, with the option `transparent`, a classical code gives directly the ouput of `nicematrix`.

```
\NiceMatrixOptions{transparent}
\begin{pmatrix}
1 & \cdots & \cdots & 1 \\
0 & \ddots & \vdots & \vdots \\
\vdots & \ddots & \ddots & \vdots \\
0 & \cdots & 0 & 1
\end{pmatrix}
```

$$\begin{pmatrix} 1 & \cdots & \cdots & 1 \\ 0 & \ddots & \vdots & \vdots \\ \vdots & \ddots & \ddots & \vdots \\ 0 & \cdots & 0 & 1 \end{pmatrix}$$

### 3.4 Fine tuning of the dotted lines

The distance between a node and the end of a dotted line is set by `dotted-lines-margin`. The initial value of this key is 0.3 em (it's recommended to use a unit dependant of the current font). For an example, cf. p. 18.

## 4 The Tikz nodes created by `nicematrix`

The package `nicematrix` creates a Tikz node for each cell of the considered array. These nodes are used to draw the dotted lines between the cells of the matrix. However, the user may wish to use directly these nodes. It's possible. First, the user have to give a name to the array (with the key called `name`). Then, the nodes are accessible through the names “`name-i-j`” where `name` is the name given to the array and `i` and `j` the numbers of the row and the column of the considered cell.

```
$\begin{pNiceMatrix}[name=mymatrix]
1 & 2 & 3 \\
4 & 5 & 6 \\
7 & 8 & 9
\end{pNiceMatrix}$
\tikz[remember picture,overlay]
\draw (mymatrix-2-2) circle (2mm) ;
```

$$\begin{pmatrix} 1 & 2 & 3 \\ 4 & 5 & 6 \\ 7 & 8 & 9 \end{pmatrix}$$

Don't forget the options `remember picture` and `overlay`.

In the following example, we have underlined all the nodes of the matrix.

$$\begin{pmatrix} a & a+b & a+b+c \\ a & a & a+b \\ a & a & a \end{pmatrix}$$

---

<sup>7</sup>The options `renew-dots`, `renew-matrix` and `transparent` can be fixed with the command `\NiceMatrixOptions` like the other options. However, they can also be fixed as options of the command `\usepackage` (it's an exception for these three specific options.)

In fact, the package `nicematrix` can create “extra nodes”: the “medium nodes” and the “large nodes”. The first ones are created with the option `create-medium-nodes` and the second ones with the option `create-large-nodes`.<sup>8</sup>

The names of the “medium nodes” are constructed by adding the suffix “`-medium`” to the names of the “normal nodes”. In the following example, we have underlined the “medium nodes”. We consider that this example is self-explanatory.

$$\begin{pmatrix} a & \underline{a+b} & \underline{a+b+c} \\ \underline{a} & \underline{a} & \underline{a+b} \\ a & \underline{a} & \underline{a} \end{pmatrix}$$

The names of the “large nodes” are constructed by adding the suffix “`-large`” to the names of the “normal nodes”. In the following example, we have underlined the “large nodes”. We consider that this example is self-explanatory.<sup>9</sup>

$$\begin{pmatrix} a & \underline{a+b} & \underline{a+b+c} \\ \underline{a} & \underline{a} & \underline{a+b} \\ a & \underline{a} & \underline{a} \end{pmatrix}$$

The “large nodes” of the first column and last column may appear too small for some usage. That’s why it’s possible to use the options `left-margin` and `right-margin` to add space on both sides of the array and also space in the “large nodes” of the first column and last column. In the following example, we have used the options `left-margin` and `right-margin`.<sup>10</sup>

$$\begin{pmatrix} a & \underline{a+b} & \underline{a+b+c} \\ \underline{a} & \underline{a} & \underline{a+b} \\ a & \underline{a} & \underline{a} \end{pmatrix}$$

It’s also possible to add more space on both side of the array with the options `extra-left-margin` and `extra-right-margin`. These margins are not incorporated in the “large nodes”. It’s possible to fix both values with the option `extra-margin` and, in the following example, we use `extra-margin` with the value 3 pt.

$$\begin{pmatrix} a & \underline{a+b} & \underline{a+b+c} \\ \underline{a} & \underline{a} & \underline{a+b} \\ a & \underline{a} & \underline{a} \end{pmatrix}$$

In this case, if we want a control over the height of the rows, we can add a `\strut` in each row of the array.

$$\begin{pmatrix} a & \underline{a+b} & \underline{a+b+c} \\ \underline{a} & \underline{a} & \underline{a+b} \\ a & \underline{a} & \underline{a} \end{pmatrix}$$

We explain below how to fill the nodes created by `nicematrix` (cf. p. 20).

---

<sup>8</sup>There is also an option `create-extra-nodes` which is an alias for the conjunction of `create-medium-nodes` and `create-large-nodes`.

<sup>9</sup>There is no “large nodes” created in the exterior rows and columns (for these rows and columns, cf. p. 8).

<sup>10</sup>The options `left-margin` and `right-margin` take dimensions as values but, if no value is given, the default value is used, which is `\arraycolsep` (by default: 5 pt). There is also an option `margin` to fix both `left-margin` and `right-margin` to the same value.

## 5 The code-after

The option `code-after` may be used to give some code that will be executed after the construction of the matrix (and, hence, after the construction of all the Tikz nodes).

In the `code-after`, the Tikz nodes should be accessed by a name of the form  $i-j$  (without the prefix of the name of the environment).

Moreover, a special command, called `\line` is available to draw directly dotted lines between nodes.

```
$\begin{pNiceMatrix}[code-after = \line{1-1}{3-3}]
0 & 0 & 0 \\
0 & & 0 \\
0 & 0 & 0
\end{pNiceMatrix}$
```

$$\begin{pmatrix} 0 & 0 & 0 \\ 0 & \ddots & 0 \\ 0 & 0 & 0 \end{pmatrix}$$

## 6 The environment `{NiceArray}`

The environment `{NiceArray}` is similar to the environment `{array}`. As for `{array}`, the mandatory argument is the preamble of the array. However, for technical reasons, in this preamble, the user must use the letters L, C and R<sup>11</sup> instead of l, c and r. It's possible to use the constructions `w{...}{...}`, `W{...}{...}`, `|,`, `>{...}`, `<{...}`, `@{...}`, `!{...}` and `*{n}{...}` but the letters p, m and b should not be used.<sup>12</sup>

The environment `{NiceArray}` accepts the classical options t, c and b of `{array}` but also other options defined by `nicematrix` (`renew-dots`, `columns-width`, etc.).

An example with a linear system (we need `{NiceArray}` for the vertical rule):

```
$\left[\begin{array}{cccc|c}
& ? & \cdots & ? & ? \\
a_1 & & & & \\
0 & & & \ddots & \\
\vdots & & \ddots & \ddots & \\
0 & & \cdots & 0 & a_n
\end{array}\right]$
```

$$\left[ \begin{array}{ccccc} a_1 & ? & \cdots & \cdots & ? \\ 0 & \ddots & \ddots & \ddots & \vdots \\ \vdots & \ddots & \ddots & \ddots & ? \\ 0 & \cdots & 0 & a_n & ? \end{array} \right]$$

In fact, there is also variants for the environment `{NiceArray}`: `{pNiceArray}`, `{bNiceArray}`, `{BNiceArray}`, `{vNiceArray}` and `{VNiceArray}`.

In the following example, we use an environment `{pNiceArray}` (we don't use `{pNiceMatrix}` because we want to use the types L and R — in `{pNiceMatrix}`, all the columns are of type C).

```
$\begin{pNiceArray}{LCR}
a_{11} & \cdots & a_{1n} \\
a_{21} & & a_{2n} \\
\vdots & & \vdots \\
a_{n-1,1} & \cdots & a_{n-1,n}
\end{pNiceArray}$
```

$$\begin{pmatrix} a_{11} & \cdots & a_{1n} \\ a_{21} & & a_{2n} \\ \vdots & & \vdots \\ a_{n-1,1} & \cdots & a_{n-1,n} \end{pmatrix}$$

In fact, the environment `{pNiceArray}` and its variants are based upon a more general environment, called `{NiceArrayWithDelims}`. The first two mandatory arguments of this environment are the left and right delimiters used in the construction of the matrix. It's possible to use `{NiceArrayWithDelims}` if we want to use atypical delimiters.

<sup>11</sup>The column types L, C and R are defined locally inside `{NiceArray}` with `\newcolumntype` of `array`. This definition overrides an eventual previous definition. In fact, the column types w and W are also redefined.

<sup>12</sup>In a command `\multicolumn`, one should also use the letters L, C, R.

```
$\begin{NiceArrayWithDelims}
{\downarrow}{\downarrow}{CCC}
1 & 2 & 3 \\
4 & 5 & 6 \\
7 & 8 & 9 \\
\end{NiceArrayWithDelims}$
```

$$\begin{array}{|ccc|} \hline 1 & 2 & 3 \\ \hline 4 & 5 & 6 \\ \hline 7 & 8 & 9 \\ \hline \end{array}$$

## 7 The exterior rows and columns

The options `first-row`, `last-row`, `first-col` and `last-col` allow the composition of exterior rows and columns in the environments of `nicematrix`.

A potential first row has the number 0 (and not 1). Idem for the potential first column. In general cases, one must specify the number of the last row and the number of the last column as values of `last-row` and `last-col`.

```
$\begin{pNiceMatrix}[\mathbf{first-row},\mathbf{last-row}=5,\mathbf{first-col},\mathbf{last-col}=5]
& C_1 & C_2 & C_3 & C_4 & \\
L_1 & a_{11} & a_{12} & a_{13} & a_{14} & L_1 \\
L_2 & a_{21} & a_{22} & a_{23} & a_{24} & L_2 \\
L_3 & a_{31} & a_{32} & a_{33} & a_{34} & L_3 \\
L_4 & a_{41} & a_{42} & a_{43} & a_{44} & L_4 \\
& C_1 & C_2 & C_3 & C_4 &
\end{pNiceMatrix}$
```

$$\begin{matrix} & C_1 & C_2 & C_3 & C_4 \\ L_1 & \left( \begin{matrix} a_{11} & a_{12} & a_{13} & a_{14} \end{matrix} \right) & L_1 \\ L_2 & \left( \begin{matrix} a_{21} & a_{22} & a_{23} & a_{24} \end{matrix} \right) & L_2 \\ L_3 & \left( \begin{matrix} a_{31} & a_{32} & a_{33} & a_{34} \end{matrix} \right) & L_3 \\ L_4 & \left( \begin{matrix} a_{41} & a_{42} & a_{43} & a_{44} \end{matrix} \right) & L_4 \\ & C_1 & C_2 & C_3 & C_4 \end{matrix}$$

We have several remarks to do.

- For the environments with an explicit preamble (i.e. `{NiceArray}` and its variants), no letter must be given in that preamble for the potential first column and the potential last column: the first column will be automatically (and necessarily) of type `R` and the last column will be automatically of type `L`.
- In an environment with an explicit preamble, the option `last-col` must be used *without* value: the number of columns will be automatically computed from the preamble of the array.
- For the potential last row, the option `last-row` may, in fact, be used without value. In this case, `nicematrix` computes, during the first compilation, the number of rows of the array and writes that information in the `.aux` file for the second run. In the following example, the option `last-row` will be used without value.

It's possible to control the appearance of these rows and columns with options `code-for-first-row`, `code-for-last-row`, `code-for-first-col` and `code-for-last-col`. These options specify tokens that will be inserted before each cell of the corresponding row or column.

```
\NiceMatrixOptions{code-for-first-row = \color{red},
                  code-for-first-col = \color{blue},
                  code-for-last-row = \color{green},
                  code-for-last-col = \color{magenta}}
$\begin{pNiceArray}{CC|CC}[\mathbf{first-row},\mathbf{last-row},\mathbf{first-col},\mathbf{last-col}]
```

```

    & C_1      & C_2      & C_3      & C_4      &      \\
L_1 & a_{11} & a_{12} & a_{13} & a_{14} & L_1 \\
L_2 & a_{21} & a_{22} & a_{23} & a_{24} & L_2 \\
\hline
L_3 & a_{31} & a_{32} & a_{33} & a_{34} & L_3 \\
L_4 & a_{41} & a_{42} & a_{43} & a_{44} & L_4 \\
    & C_1      & C_2      & C_3      & C_4      &
\end{pNiceArray}

```

$$\begin{array}{cccc|cc} & \color{red}C_1&\color{red}C_2&\color{red}C_3&\color{red}C_4& \\ \color{blue}L_1&\left( \begin{array}{cc|cc} a_{11}&a_{12}&a_{13}&a_{14} \\ a_{21}&a_{22}&a_{23}&a_{24} \end{array} \right) & \color{red}L_1 \\ \color{blue}L_2&&&&& \color{red}L_2 \\ \color{blue}L_3&&&&& \color{red}L_3 \\ \color{blue}L_4&\left( \begin{array}{cc|cc} a_{31}&a_{32}&a_{33}&a_{34} \\ a_{41}&a_{42}&a_{43}&a_{44} \end{array} \right) & \color{red}L_4 \\ & \color{green}C_1&\color{green}C_2&\color{green}C_3&\color{green}C_4& \end{array}$$

*Remarks*

- As shown in the previous example, an horizontal rule (drawn by `\hline`) doesn't extend in the exterior columns and a vertical rule (specified by a “|” in the preamble of the array) doesn't extend in the exterior rows.<sup>13</sup>
- If one wishes to define new specifiers for columns in order to draw vertical rules (for example thicker than the standard rules), he should consider the command `\OnlyMainNiceMatrix` described on page 14.
- Logically, the potential option `columns-width` (described p. 10) doesn't apply to the “first column” and “last column”.
  - For technical reasons, it's not possible to use the option of the command `\hline` after the “first row” or before the “last row” (the placement of the delimiters would be wrong).

## 8 The dotted lines to separate rows or columns

In the environments of the extension `nicematrix`, it's possible to use the command `\hdottedline` (provided by `nicematrix`) which is a counterpart of the classical commands `\hline` and `\hdashline` (the latter is a command of `arydshln`).

```

\begin{pNiceMatrix}
1 & 2 & 3 & 4 & 5 \\
\hdottedline
6 & 7 & 8 & 9 & 10 \\
11 & 12 & 13 & 14 & 15
\end{pNiceMatrix}

```

$$\left( \begin{array}{ccccc} 1 & 2 & 3 & 4 & 5 \\ \cdots & \cdots & \cdots & \cdots & \cdots \\ 6 & 7 & 8 & 9 & 10 \\ 11 & 12 & 13 & 14 & 15 \end{array} \right)$$

In the environments with an explicit preamble (like `{NiceArray}`, etc.), it's possible to draw a vertical dotted line with the specifier “:”.

```

\left(\begin{NiceArray}{CCCC:C}
1 & 2 & 3 & 4 & 5 \\
6 & 7 & 8 & 9 & 10 \\
11 & 12 & 13 & 14 & 15
\end{NiceArray}\right)

```

$$\left( \begin{array}{ccccc} 1 & 2 & 3 & 4 & :5 \\ 6 & 7 & 8 & 9 & :10 \\ 11 & 12 & 13 & 14 & :15 \end{array} \right)$$

These dotted lines do *not* extend in the potential exterior rows and columns.

---

<sup>13</sup>The latter is not true when the extension `arydshln` is loaded besides `nicematrix`. In fact, `nicematrix` and `arydshln` are not totally compatible because `arydshln` redefines many internals of `array`. On another hand, if one really wants a vertical rule running in the first and in the last row, he should use `!{\vline}` instead of `|` in the preamble of the array.

```
$\begin{pNiceArray}{CCC:C}
    first-row, last-col,
    code-for-first-row = \color{blue}\scriptstyle,
    code-for-last-col = \color{blue}\scriptstyle ]
C_1 & C_2 & C_3 & C_4 \\
1 & 2 & 3 : 4 \\[L_1]
5 & 6 & 7 : 8 \\[L_2]
9 & 10 & 11 : 12 \\[L_3]
13 & 14 & 15 : 16 \\[L_4]
\hdottedline
13 & 14 & 15 & 16 & L_4
\end{pNiceArray}$
```

It's possible to change in `nicematrix` the letter used to specify a vertical dotted line with the option `letter-for-dotted-lines` available in `\NiceMatrixOptions`. For example, in this document, we have loaded the extension `arydshln` which uses the letter “`:`” to specify a vertical dashed line. Thus, by using `letter-for-dotted-lines`, we can use the vertical lines of both `arydshln` and `nicematrix`.

```
\NiceMatrixOptions{letter-for-dotted-lines = V}
\left(\begin{array}{|CC:CVC}
1 & 2 & 3 : 4 \\
5 & 6 & 7 : 8 \\
9 & 10 & 11 : 12 \\
\end{array}\right)
```

## 9 The width of the columns

In the environments with an explicit preamble (like `{NiceArray}`, `{pNiceArray}`, etc.), it's possible to fix the width of a given column with the standard letters `w` and `W` of the package `array`.

```
$\left(\begin{array}{wc{1cm}CC}
1 & 12 & -123 \\
12 & 0 & 0 \\
4 & 1 & 2 \\
\end{array}\right)$
```

In the environments of `nicematrix`, it's also possible to fix the width of all the columns of a matrix directly with the option `columns-width`.

```
$\begin{pNiceMatrix}[\text{columns-width} = 1cm]
1 & 12 & -123 \\
12 & 0 & 0 \\
4 & 1 & 2
\end{pNiceMatrix}$
```

Note that the space inserted between two columns (equal to `2 \arraycolsep`) is not suppressed (of course, it's possible to suppress this space by setting `\arraycolsep` equal to `0 pt`).

It's possible to give the special value `auto` to the option `columns-width`: all the columns of the array will have a width equal to the widest cell of the array.<sup>14</sup>

```
$\begin{pNiceMatrix}[\text{columns-width} = \text{auto}]
1 & 12 & -123 \\
12 & 0 & 0 \\
4 & 1 & 2
\end{pNiceMatrix}$
```

---

<sup>14</sup>The result is achieved with only one compilation (but Tikz will have written informations in the `.aux` file and a message requiring a second compilation will appear).

Without surprise, it's possible to fix the width of the columns of all the matrices of a current scope with the command `\NiceMatrixOptions`.

```
\NiceMatrixOptions{columns-width=10mm}
$\begin{pNiceMatrix}
a & b \\ c & d \\
\end{pNiceMatrix}
=
\begin{pNiceMatrix}
1 & 1245 \\ 345 & 2 \\
\end{pNiceMatrix}$
```

$$\begin{pmatrix} a & b \\ c & d \end{pmatrix} = \begin{pmatrix} 1 & 1245 \\ 345 & 2 \end{pmatrix}$$

But it's also possible to fix a zone where all the matrices will have their columns of the same width, equal to the widest cell of all the matrices. This construction uses the environment `{NiceMatrixBlock}` with the option `auto-columns-width`.<sup>15</sup>

```
\begin{NiceMatrixBlock}[auto-columns-width]
$\begin{pNiceMatrix}
a & b \\ c & d \\
\end{pNiceMatrix}
=
\begin{pNiceMatrix}
1 & 1245 \\ 345 & 2 \\
\end{pNiceMatrix}$
```

$$\begin{pmatrix} a & b \\ c & d \end{pmatrix} = \begin{pmatrix} 1 & 1245 \\ 345 & 2 \end{pmatrix}$$

**Several compilations may be necessary to achieve the job.**

## 10 Block matrices

This section has no direct link with the previous one where an environment `{NiceMatrixBlock}` was introduced.

In the environments of `nicematrix`, it's possible to use the command `\Block` in order to place an element in the center of a rectangle of merged cells of the array.

The command `\Block` must be used in the upper leftmost cell of the array with two arguments. The first argument is the size of the block with the syntax  $i-j$  where  $i$  is the number of rows of the block and  $j$  its number of columns. The second argument is the content of the block (composed in math mode).

```
\arrayrulecolor{cyan}
$\begin{bNiceArray}{CCC|C}[margin]
\Block{3-3}{A} & & & 0 \\
& \hspace*{1cm} & \Vdots & \\
& & 0 & \\
\hline
0 & \cdots & 0 & 0
\end{bNiceArray}$
\arrayrulecolor{black}
```

$$\left[ \begin{array}{ccc|c} & & & 0 \\ A & & & \vdots \\ & & & 0 \\ \hline 0 & \cdots & 0 & 0 \end{array} \right]$$

One may wish to raise the size of the “ $A$ ” placed in the block of the previous example. Since this element is composed in math mode, it's not possible to use directly a command like `\large`, `\Large` and `\LARGE`. That's why the command `\Block` provides an option between angle brackets to specify some TeX code which will be inserted before the beginning of the math mode.

---

<sup>15</sup>At this time, this is the only usage of the environment `{NiceMatrixBlock}` but it may have other usages in the future.

```
\arrayrulecolor{cyan}
$\begin{bNiceArray}{CCC|C}[margin]
\Block{3-3}<\Large>\{A} & & & 0 \\
& \hspace{1cm} & & \Vdots \\
& & & 0 \\
\hline
0 & \cdots & 0 & 0
\end{bNiceArray}$
\arrayrulecolor{black}
```

$$\left[ \begin{array}{ccc|c} & & & 0 \\ & A & & \vdots \\ & & & 0 \\ \hline 0 & \cdots & 0 & 0 \end{array} \right]$$

For technical reasons, you can't write `\Block{i-j}{<>}`. But you can write `\Block{i-j}{<>}` with the expected result.

## 11 Advanced features

### 11.1 The option `small`

With the option `small`, the environments of the extension `nicematrix` are composed in a way similar to the environment `{smallmatrix}` of the extension `amsmath` (and the environments `{psmallmatrix}`, `{bsmallmatrix}`, etc. of the extension `mathtools`).

```
$\begin{bNiceArray}{CCCC|C}[small,
    last-col,
    code-for-last-col = \scriptscriptstyle,
    columns-width = 3mm ]
1 & -2 & 3 & 4 & 5 \\
0 & 3 & 2 & 1 & 2 & \gets 2 L_1 - L_2 \\
0 & 1 & 2 & 3 & L_3 & \gets L_1 + L_3 \\
\end{bNiceArray}$
```

$$\left[ \begin{array}{ccccc|c} 1 & -2 & 3 & 4 & 5 \\ 0 & 3 & 2 & 1 & 2 & \scriptstyle L_2 \leftarrow 2L_1 - L_2 \\ 0 & 1 & 1 & 2 & 3 & \scriptstyle L_3 \leftarrow L_1 + L_3 \end{array} \right]$$

One should note that the environment `{NiceMatrix}` with the option `small` is not composed *exactly* as the environment `{smallmatrix}`. Indeed, all the environments of `nicematrix` are constructed upon `{array}` (of the extension `array`) whereas the environment `{smallmatrix}` is constructed directly with an `\halign` of TeX.

In fact, the option `small` corresponds to the following tuning:

- the cells of the array are composed with `\scriptstyle`;
- `\arraystretch` is set to 0.47;
- `\arraycolsep` is set to 1.45 pt;
- the characteristics of the dotted lines are also modified.

### 11.2 The counters `iRow` and `jCol`

In the cells of the array, it's possible to use the LaTeX counters `iRow` and `jCol` which represent the number of the current row and the number of the current col<sup>16</sup>. Of course, the user must not change the value of these counters which are used internally by `nicematrix`.

---

<sup>16</sup>We recall that the first row (if it exists) has the number 0 and that the first col (if it exists) has also the number 0.

```
$\begin{pNiceMatrix} % don't forget the %
[first-row,
 first-col,
 code-for-first-row = \mathbf{\alpha{jCol}} ,
 code-for-first-col = \mathbf{\arabic{iRow}} ]
& & & \\
& 1 & 2 & 3 & 4 \\
& 5 & 6 & 7 & 8 \\
& 9 & 10 & 11 & 12
\end{pNiceMatrix}$
```

$$\begin{array}{cccc} \mathbf{a} & \mathbf{b} & \mathbf{c} & \mathbf{d} \\ \mathbf{1} & 1 & 2 & 3 \\ \mathbf{2} & 5 & 6 & 7 \\ \mathbf{3} & 9 & 10 & 11 & 12 \end{array}$$

If LaTeX counters called `iRow` and `jCol` are defined in the document by extensions other than `nicematrix` (or by the user), they are shadowed in the environments of `nicematrix`.

The extension `nicematrix` also provides commands in order to compose automatically matrices from a general pattern. These commands are `\pAutoNiceMatrix`, `\bAutoNiceMatrix`, `\vAutoNiceMatrix`, `\VAutoNiceMatrix` and `\BAutoNiceMatrix`.

These commands take two mandatory arguments. The first is the format of the matrix, with the syntax  $n-p$  where  $n$  is the number of rows and  $p$  the number of columns. The second argument is the pattern (it's a list of tokens which are inserted in each cell of the constructed matrix, excepted in the cells of the eventual exterior rows and columns).

```
$C = \pAutoNiceMatrix{3-3}{C_{\arabic{iRow},\arabic{jCol}}}$
```

$$C = \begin{pmatrix} C_{1,1} & C_{1,2} & C_{1,3} \\ C_{2,1} & C_{2,2} & C_{2,3} \\ C_{3,1} & C_{3,2} & C_{3,3} \end{pmatrix}$$

### 11.3 The option `hlines`

You can add horizontal rules between rows in the environments of `nicematrix` with the usual command `\hline`. But, by convenience, the extension `nicematrix` also provides the option `hlines`. With this option, all the horizontal rules will be drawn (excepted, of course, the rule before the potential “first row” and the rule after the potential “last row”).

```
$\begin{NiceArray}{|*{4}{|c|}}[hlines,first-row,first-col]
& e & a & b & c \\
e & e & a & b & c \\
a & a & e & c & b \\
b & b & c & e & a \\
c & c & b & a & e
\end{NiceArray}$
```

$e$	$a$	$b$	$c$
$a$	$e$	$c$	$b$
$b$	$b$	$e$	$a$
$c$	$c$	$a$	$e$

### 11.4 The option `light-syntax`

The option `light-syntax`<sup>17</sup> allow the user to compose the arrays with a lighter syntax, which gives a more readable TeX source.

When this option is used, one should use the semicolon for the end of a row and a space to separate the columns. However, as usual in the TeX world, the spaces after a control sequence are discarded and the elements between curly braces are considered as a whole.

The following example has been composed with XeLaTeX with `unicode-math`, which allows the use of greek letters directly in the TeX source.

```
$\begin{bNiceMatrix} [light-syntax,first-row,first-col]
{} \alpha & \beta & ; \\
\alpha & 2\cos \alpha & \{\cos \alpha + \cos \beta\} ; \\
\beta & \cos \alpha + \cos \beta & \{ 2 \cos \beta \}
\end{bNiceMatrix}$
```

$$\begin{array}{ccc} \alpha & & \beta \\ \alpha & 2 \cos \alpha & \cos \alpha + \cos \beta \\ \beta & \cos \alpha + \cos \beta & 2 \cos \beta \end{array}$$


---

<sup>17</sup>This option is inspired by the extension `spalign` of Joseph Rabinoff.

It's possible to change the character used to mark the end of rows with the option `end-of-row`. As said before, the initial value is a semicolon.

## 11.5 Utilisation of the column type S of siunitx

If the package `siunitx` is loaded (before or after `nicematrix`), it's possible to use the `S` column type of `siunitx` in the environments of `nicematrix`. The implementation doesn't use explicitly any private macro of `siunitx`.

```
$\begin{pNiceArray}{SCWc{1cm}C}[nullify-dots,first-row]
{C_1} & \cdots & C_n \\
2.3 & 0 & 0 \\
12.4 & \vdots & \vdots \\
1.45 & \vdots & \vdots \\
7.2 & 0 & 0
\end{pNiceArray}
```

$$\left( \begin{array}{ccc|c} C_1 & \cdots & C_n \\ 2.3 & 0 & 0 \\ 12.4 & \vdots & \vdots \\ 1.45 & \vdots & \vdots \\ 7.2 & 0 & 0 \end{array} \right)$$

On the other hand, the `d` columns of the package `dcolumn` are not supported by `nicematrix`.

## 12 Technical remarks

### 12.1 Definition of new column types

The extension `nicematrix` provides the command `\OnlyMainNiceMatrix` which is meant to be used in definitions of new column types. Its argument is evaluated if and only if we are in the main part of the array, that is to say not in an eventual exterior row.

For example, one may wish to define a new column type `?` in order to draw a thick rule of width 1 pt. The following definition will do the job:

```
\newcolumntype{?}{!{\OnlyMainNiceMatrix{\vrule width 1 pt}}}
```

The thick vertical rule won't extend in the exterior rows:

```
$\begin{pNiceArray}{CC?CC}[first-row,last-row]
C_1 & C_2 & C_3 & C_4 \\
a & b & c & d \\
e & f & g & h \\
C_1 & C_2 & C_3 & C_4
\end{pNiceArray}
```

$$\left( \begin{array}{cc|cc} C_1 & C_2 & C_3 & C_4 \\ a & b & c & d \\ e & f & g & h \\ C_1 & C_2 & C_3 & C_4 \end{array} \right)$$

The specifier `?` may be used in a standard environment `{array}` (of the package `array`) and, in this case, the command `\OnlyMainNiceMatrix` is no-op.

### 12.2 Intersections of dotted lines

Since the version 3.1 of `nicematrix`, the dotted lines created by `\cdots`, `\ldots`, `\vdots`, etc. can't intersect.<sup>18</sup>

That means that a dotted line created by one these commands automatically stops when it arrives on a dotted line already drawn. Therefore, the order in which dotted lines are drawn is important. Here's that order (by design) : `\hdotsfor`, `\vdots`, `\ddots`, `\iddots`, `\cdots` and `\ldots`.

With this structure, it's possible to draw the following matrix.

---

<sup>18</sup>On the contrary, dotted lines created by `\hdottedline`, the letter ":" in the preamble of the array and the command `\line` in the `code-after` can have intersections with other dotted lines.

```
$\begin{pNiceMatrix} [nullify-dots]
1 & 2 & 3 & \Cdots & n \\
1 & 2 & 3 & \Cdots & n \\
\Vdots & \Cdots & & \Hspace*{15mm} & \Vdots \\
& \Cdots & & & \\
& \Cdots & & & \\
& \Cdots & & & \\
\end{pNiceMatrix}$
```

$$\begin{pmatrix} 1 & 2 & 3 & \cdots & n \\ 1 & 2 & 3 & \cdots & n \\ \vdots & \ddots & \ddots & \ddots & \vdots \\ \vdots & \ddots & \ddots & \ddots & \vdots \\ \vdots & \ddots & \ddots & \ddots & \vdots \end{pmatrix}$$

### 12.3 The names of the Tikz nodes created by nicematrix

We have said that, when a name is given to an environment of `nicematrix`, it's possible to access the Tikz nodes through this name (cf. p. 5).

That's the recommended way to access these nodes. However, we describe now the internal names of these nodes.

The environments created by `nicematrix` are numbered by an internal global counter. The command `\NiceMatrixLastEnv` provides the number of the last environment of `nicematrix` (for LaTeX, it's a “fully expandable” command and not a counter).

For the environment of number  $n$ , the node in row  $i$  and column  $j$  has the name `nm-n-i-j`. The `medium` and `large` have the same name, suffixed by `-medium` and `-large`.

### 12.4 Diagonal lines

By default, all the diagonal lines<sup>19</sup> of a same array are “parallelized”. That means that the first diagonal line is drawn and, then, the other lines are drawn parallel to the first one (by rotation around the left-most extremity of the line). That's why the position of the instructions `\Ddots` in the array can have a marked effect on the final result.

In the following examples, the first `\Ddots` instruction is written in color:

Example with parallelization (default):

```
$A = \begin{pNiceMatrix}
1 & \Cdots & & 1 & \\
a+b & \textcolor{blue}{\Ddots} & & \Vdots & \\
\Vdots & \Ddots & & & \\
a+b & \Cdots & a+b & & 1
\end{pNiceMatrix}$
```

$$A = \begin{pmatrix} 1 & \cdots & \cdots & \cdots & 1 \\ a+b & \cdots & \cdots & \cdots & \vdots \\ \vdots & \ddots & \ddots & \ddots & \vdots \\ a+b & \cdots & a+b & \cdots & 1 \end{pmatrix}$$

```
$A = \begin{pNiceMatrix}
1 & \Cdots & & 1 & \\
a+b & & & \Vdots & \\
\Vdots & \textcolor{blue}{\Ddots} & \Ddots & & \\
a+b & \Cdots & a+b & & 1
\end{pNiceMatrix}$
```

$$A = \begin{pmatrix} 1 & \cdots & \cdots & \cdots & 1 \\ a+b & \cdots & \cdots & \cdots & \vdots \\ \vdots & \ddots & \ddots & \ddots & \vdots \\ a+b & \cdots & a+b & \cdots & 1 \end{pmatrix}$$

It's possible to turn off the parallelization with the option `parallelize-diags` set to `false`:

The same example without parallelization:

$$A = \begin{pmatrix} 1 & \cdots & \cdots & \cdots & 1 \\ a+b & \cdots & \cdots & \cdots & \vdots \\ \vdots & \ddots & \ddots & \ddots & \vdots \\ a+b & \cdots & a+b & \cdots & 1 \end{pmatrix}$$

---

<sup>19</sup>We speak of the lines created by `\Ddots` and not the lines created by a command `\line` in `code-after`.

## 12.5 The “empty” cells

An instruction like `\Ldots`, `\Cdots`, etc. tries to determine the first non-empty cells on both sides. However, an empty cell is not necessarily a cell with no TeX content (that is to say a cell with no token between the two ampersands &). Indeed, a cell with contents `\hspace*{1cm}` may be considered as empty.

For `nicematrix`, the precise rules are as follow.

- An implicit cell is empty. For example, in the following matrix:

```
\begin{pmatrix}
a & b \\
c \\
\end{pmatrix}
```

the last cell (second row and second column) is empty.

- Each cell whose TeX output has a width less than 0.5 pt is empty.
- A cell which contains a command `\Ldots`, `\Cdots`, `\Vdots`, `\Ddots` or `\Iddots` is empty. We recall that these commands should be used alone in a cell.
- A cell with a command `\Hspace` (or `\Hspace*`) is empty. This command `\Hspace` is a command defined by the package `nicematrix` with the same meaning as `\hspace` except that the cell where it is used is considered as empty. This command can be used to fix the width of some columns of the matrix without interfering with `nicematrix`.

## 12.6 The option `exterior-arraycolsep`

The environment `{array}` inserts an horizontal space equal to `\arraycolsep` before and after each column. In particular, there is a space equal to `\arraycolsep` before and after the array. This feature of the environment `{array}` was probably not a good idea<sup>20</sup>. The environment `{matrix}` of `amsmath` and its variants (`{pmatrix}`, `{vmatrix}`, etc.) of `amsmath` prefer to delete these spaces with explicit instructions `\hskip -\arraycolsep`. The extension `nicematrix` does the same in all its environments, `{NiceArray}` included. However, if the user wants the environment `{NiceArray}` behaving by default like the environment `{array}` of `array` (for example, when adapting an existing document) it's possible to control this behaviour with the option `exterior-arraycolsep`, set by the command `\NiceMatrixOptions`. With this option, exterior spaces of length `\arraycolsep` will be inserted in the environments `{NiceArray}` (the other environments of `nicematrix` are not affected).

## 12.7 The class option `draft`

The package `nicematrix` is rather slow when drawing the dotted lines (generated by `\Cdots`, `\Ldots`, `\Ddots`, etc. but also by `\hdottedline` or the specifier `:`).<sup>21</sup>

That's why, when the class option `draft` is used, the dotted lines are not drawn, for a faster compilation.

---

<sup>20</sup>In the documentation of `{amsmath}`, we can read: *The extra space of `\arraycolsep` that `array` adds on each side is a waste so we remove it [in `{matrix}`] (perhaps we should instead remove it from `array` in general, but that's a harder task).* It's possible to suppress these spaces for a given environment `{array}` with a construction like `\begin{array}{@{}cccccc@{}}`...

<sup>21</sup>The main reason is that we want dotted lines with round dots (and not square dots) with the same space on both extremities of the lines. To achieve this goal, we have to construct our own system of dotted lines.

## 12.8 A technical problem with the argument of \\

For technical reasons, if you use the optional argument of the command `\\\`, the vertical space added will also be added to the “normal” node corresponding at the previous node.

```
\begin{pNiceMatrix}
a & \frac{AB}{} \\
b & c
\end{pNiceMatrix}
```

$$\begin{pmatrix} a & \frac{A}{B} \\ b & c \end{pmatrix}$$

There are two solutions to solve this problem. The first solution is to use a TeX command to insert space between the rows.

```
\begin{pNiceMatrix}
a & \frac{AB}{} \\
\noalign{\kern2mm}
b & c
\end{pNiceMatrix}
```

$$\begin{pmatrix} a & \frac{A}{B} \\ b & c \end{pmatrix}$$

The other solution is to use the command `\multicolumn` in the previous cell.

```
\begin{pNiceMatrix}
a & \multicolumn{1}{c}{\frac{AB}{} } \\
b & c
\end{pNiceMatrix}
```

$$\begin{pmatrix} a & \frac{A}{B} \\ b & c \end{pmatrix}$$

## 12.9 Obsolete environments

The version 3.0 of `nicematrix` has introduced the environment `{pNiceArray}` (and its variants) with the options `first-row`, `last-row`, `first-col` and `last-col`.

Consequently the following environments present in previous versions of `nicematrix` are deprecated:

- `{NiceArrayCwithDelims}` ;
- `{pNiceArrayC}`, `{bNiceArrayC}`, `{BNiceArrayC}`, `{vNiceArrayC}`, `{VNiceArrayC}` ;
- `{NiceArrayRCwithDelims}` ;
- `{pNiceArrayRC}`, `{bNiceArrayRC}`, `{BNiceArrayRC}`, `{vNiceArrayRC}`, `{VNiceArrayRC}`.

Since the version 3.8, an error is raised when one of these environments is used. It’s still possible to use these environments by loading `nicematrix` with the option `obsolete-environments`.

However, these environments will probably be completely deleted in a future version of `nicematrix`.

## 13 Examples

### 13.1 Dotted lines

A tridiagonal matrix:

```
$\begin{pNiceMatrix}[nullify-dots]
a & b & 0 & & \cdots & & 0 \\
b & a & b & & \ddots & & \\
0 & b & a & & \ddots & & \\
& \ddots & \ddots & \ddots & & 0 & \\
\vdots & & & & & b & \\
0 & & \cdots & 0 & b & a
\end{pNiceMatrix}$
```

$$\begin{pmatrix} a & b & 0 & \cdots & & 0 \\ b & a & b & & & \\ 0 & b & a & & & \\ \vdots & & & \ddots & & \\ & & & & b & \\ 0 & \cdots & 0 & b & a \end{pmatrix}$$

A permutation matrix (as an example, we have raised the value of dotted-lines-margin).

```

\$\\begin{pNiceMatrix} [dotted-lines-margin=0.6em]
0 & 1 & 0 & & \\Cdots & 0 \\
\\Vdots & & & \\Ddots & & \\Vdots \\
& & & \\Ddots & & \\
& & & \\Ddots & & \\
0 & 0 & & & & 1 \\
1 & 0 & & \\Cdots & & 0
\\end{pNiceMatrix}\$
```

$$\begin{pmatrix} 0 & 1 & 0 & \dots & 0 \\ \vdots & \ddots & \ddots & \ddots & \vdots \\ 0 & 0 & & & 0 \\ 1 & 0 & \dots & \dots & 1 \\ 0 & & & & 0 \end{pmatrix}$$

An example with \Iddots:

```

\$\\begin{pNiceMatrix}
1 & \\Cdots & & & 1 \\
\\Vdots & & & & 0 \\
& \\Idots & \\Idots & & \\Vdots \\
1 & 0 & \\Cdots & & 0
\\end{pNiceMatrix}$

```

$$\begin{pmatrix} 1 & \dots & & 1 \\ \vdots & & & \\ & & 0 & \\ 1 & 0 & \dots & 0 \end{pmatrix}$$

An example with \multicolumn:

```
\begin{BNiceMatrix}[nullify-dots]
1 & 2 & 3 & 4 & 5 & 6 & 7 & 8 & 9 & 10 \\
1 & 2 & 3 & 4 & 5 & 6 & 7 & 8 & 9 & 10 \\
\cdots & & \multicolumn{6}{C}{10} \text{ other rows} & \cdots \\
1 & 2 & 3 & 4 & 5 & 6 & 7 & 8 & 9 & 10
\end{BNiceMatrix}
```

$$\left\{ \begin{array}{ccccccccc} 1 & 2 & 3 & 4 & 5 & 6 & 7 & 8 & 9 & 10 \\ 1 & 2 & 3 & 4 & 5 & 6 & 7 & 8 & 9 & 10 \\ \dots\dots & & & & & & & & & 10 \text{ other rows} & \dots\dots \\ 1 & 2 & 3 & 4 & 5 & 6 & 7 & 8 & 9 & 10 \end{array} \right\}$$

An example with \Hdotsfor:

```

\begin{pNiceMatrix} [nullify-dots]
0 & 1 & 1 & 1 & 1 & 0 \\
0 & 1 & 1 & 1 & 1 & 0 \\
\vdots & \ddots & \vdots & \vdots & \vdots & \\
& \ddots & & \ddots & & \\
& \ddots & & \ddots & & \\
& \ddots & & \ddots & & \\
0 & 1 & 1 & 1 & 1 & 0
\end{pNiceMatrix}

```

$$\begin{pmatrix} 0 & 1 & 1 & 1 & 1 & 0 \\ 0 & 1 & 1 & 1 & 1 & 0 \\ \vdots & \ddots & & & & \\ \vdots & & \ddots & & & \\ \vdots & & & \ddots & & \\ \vdots & & & & \ddots & \\ 0 & 1 & 1 & 1 & 1 & 0 \end{pmatrix}$$

An example for the resultant of two polynomials:

```
\setlength{\extrarowheight}{1mm}
\[\begin{vNiceArray}{CCCC:CCC} [columns-width=6mm]
a_0 & & & b_0 & & & \\
a_1 & \&\Ddots&& b_1 & \&\Ddots& \\
\vdots & \&\Ddots&& \vdots & \&\Ddots&b_0 \\
a_p & \&&a_0 & & & b_1 \\
& \&\Ddots&&a_1 & \&b_q & \&\Vdots\\
& \&&\Vdots & \& \&\Ddots& \\
& \&&a_p & \& & b_q
\end{vNiceArray}\]
```

$$\left| \begin{array}{ccccccc} a_0 & & & & b_0 & & \\ a_1 & & & & b_1 & & \\ a_p & & & & b_q & & \\ & & & a_0 & & & \\ & & & a_1 & & & \\ & & & a_p & & & \\ & & & & b_0 & & \\ & & & & b_1 & & \\ & & & & b_q & & \end{array} \right|$$

An example for a linear system (the vertical rule has been drawn in cyan with the tools of `colortbl`):

```
\arrayrulecolor{cyan}
$\begin{pNiceArray}{*6C|C} [nullify-dots, last-col, code-for-last-col=\scriptstyle]
1 & & 1 & 1 & 0 & \\
0 & & 1 & 0 & \cdots & L_2 \gets L_2 - L_1 \\
0 & & 0 & 1 & \cdots & L_3 \gets L_3 - L_1 \\
& & & & \cdots & \cdots \\
\vdots & & & & \cdots & \cdots \\
0 & & & & 0 & L_n \gets L_n - L_1
\end{pNiceArray}$
\arrayrulecolor{black}
```

$$\left( \begin{array}{ccccc|c} 1 & 1 & 1 & \cdots & 1 & 0 \\ 0 & 1 & 0 & \cdots & 0 & \vdots \\ 0 & 0 & 1 & \cdots & 0 & \vdots \\ \vdots & & & \ddots & 0 & \vdots \\ 0 & \cdots & 0 & 1 & 0 & 0 \end{array} \right)_{\substack{L_2 \leftarrow L_2 - L_1 \\ L_3 \leftarrow L_3 - L_1 \\ \vdots \\ L_n \leftarrow L_n - L_1}}$$

## 13.2 Width of the columns

In the following example, we use `{NiceMatrixBlock}` with the option `auto-columns-width` because we want the same automatic width for all the columns of the matrices.

```

\begin{NiceMatrixBlock}[auto-columns-width]
\NiceMatrixOptions{code-for-last-col = \color{blue}\scriptstyle}
\setlength{\extrarowheight}{1mm}
\quad \$\begin{pNiceArray}{CCCC:C}[last-col]
1&1&1&1:&1\\
2&4&8&16:&9\\
3&9&27&81:&36\\
4&16&64&256:&100\\
\end{pNiceArray}$
...
\end{NiceMatrixBlock}

```

$$\left( \begin{array}{cccc|c} 1 & 1 & 1 & 1 & 1 \\ 2 & 4 & 8 & 16 & 9 \\ 3 & 9 & 27 & 81 & 36 \\ 4 & 16 & 64 & 256 & 100 \end{array} \right) \quad \left( \begin{array}{cccc|c} 1 & 1 & 1 & 1 & 1 \\ 0 & 1 & 3 & 7 & \frac{7}{2} \\ 0 & 0 & 3 & 18 & 6 \\ 0 & 0 & -2 & -14 & -\frac{9}{2} \end{array} \right) \begin{matrix} L_3 \leftarrow -3L_2 + L_3 \\ L_4 \leftarrow L_2 - L_4 \end{matrix}$$

$$\left( \begin{array}{cccc|c} 1 & 1 & 1 & 1 & 1 \\ 0 & 2 & 6 & 14 & 7 \\ 0 & 6 & 24 & 78 & 33 \\ 0 & 12 & 60 & 252 & 96 \end{array} \right) \begin{matrix} L_2 \leftarrow -2L_1 + L_2 \\ L_3 \leftarrow -3L_1 + L_3 \\ L_4 \leftarrow -4L_1 + L_4 \end{matrix} \quad \left( \begin{array}{cccc|c} 1 & 1 & 1 & 1 & 1 \\ 0 & 1 & 3 & 7 & \frac{7}{2} \\ 0 & 0 & 1 & 6 & 2 \\ 0 & 0 & -2 & -14 & -\frac{9}{2} \end{array} \right) \begin{matrix} L_3 \leftarrow \frac{1}{3}L_3 \\ L_4 \leftarrow 2L_3 + L_4 \end{matrix}$$

$$\left( \begin{array}{cccc|c} 1 & 1 & 1 & 1 & 1 \\ 0 & 1 & 3 & 7 & \frac{7}{2} \\ 0 & 3 & 12 & 39 & \frac{33}{2} \\ 0 & 1 & 5 & 21 & 8 \end{array} \right) \begin{matrix} L_2 \leftarrow \frac{1}{2}L_2 \\ L_3 \leftarrow \frac{1}{2}L_3 \\ L_4 \leftarrow \frac{1}{12}L_4 \end{matrix} \quad \left( \begin{array}{cccc|c} 1 & 1 & 1 & 1 & 1 \\ 0 & 1 & 3 & 7 & \frac{7}{2} \\ 0 & 0 & 1 & 6 & 2 \\ 0 & 0 & 0 & -2 & -\frac{1}{2} \end{array} \right) \begin{matrix} L_4 \leftarrow 2L_3 + L_4 \end{matrix}$$

### 13.3 How to highlight cells of the matrix

In order to highlight a cell of a matrix, it's possible to "draw" one of the correspondant nodes (the "normal node", the "medium node" or the "large node"). In the following example, we use the "large nodes" of the diagonal of the matrix (with the Tikz key "name suffix", it's easy to use the "large nodes").

In order to have the continuity of the lines, we have to set `inner sep = -\pgflinewidth/2`.

```

\$ \begin{pNiceArray}{>{\strut}CCCC}%
[create-large-nodes,margin,extra-margin = 2pt ,
code-after = {\begin{tikzpicture}
[name suffix = -large,
every node/.style = {draw,
inner sep = -\pgflinewidth/2}]
\node [fit = (1-1)] {} ;
\node [fit = (2-2)] {} ;
\node [fit = (3-3)] {} ;
\node [fit = (4-4)] {} ;
\end{tikzpicture}}]
a_{11} & a_{12} & a_{13} & a_{14} \\
a_{21} & a_{22} & a_{23} & a_{24} \\
a_{31} & a_{32} & a_{33} & a_{34} \\
a_{41} & a_{42} & a_{43} & a_{44}
\end{pNiceArray}$

```

$$\left( \begin{array}{|c|cc|cc|} \hline a_{11} & a_{12} & a_{13} & a_{14} & \\ \hline a_{21} & |a_{22}| & a_{23} & a_{24} & \\ \hline a_{31} & a_{32} & |a_{33}| & a_{34} & \\ \hline a_{41} & a_{42} & a_{43} & |a_{44}| & \\ \hline \end{array} \right)$$

The package `nicematrix` is constructed upon the environment `{array}` and, therefore, it's possible to use the package `colortbl` in the environments of `nicematrix`. However, it's not always easy to do a fine tuning of `colortbl`. That's why we propose another method to highlight a row of the matrix. We create a rectangular Tikz node which encompasses the nodes of the second row with the Tikz library `fit`. This Tikz node is filled after the construction of the matrix. In order to see the text *under* this node, we have to use transparency with the `blend mode` equal to `multiply`.

```
\tikzset{highlight/.style={rectangle,
    fill=red!15,
    blend mode = multiply,
    rounded corners = 0.5 mm,
    inner sep=1pt,
    fit = #1}]

$\begin{bNiceMatrix} [code-after = {\tikz \node [highlight = (2-1) (2-3)] {} ;}]
0 & \cdots & 0 \\
1 & \cdots & 1 \\
0 & \cdots & 0
\end{bNiceMatrix}$
```

$$\begin{bmatrix} 0 & \cdots & 0 \\ 1 & \cdots & 1 \\ 0 & \cdots & 0 \end{bmatrix}$$

This code fails with `latex-dvips-ps2pdf` because Tikz for `dvips`, as for now, doesn't support blend modes. However, the following code, in the preamble, should activate blend modes in this way of compilation.

```
\ExplSyntaxOn
\makeatletter
\tl_set:Nn \l_tmpa_tl {pgfsys-dvips.def}
\tl_if_eq:NNT \l_tmpa_tl \pgfsysdriver
  {\cs_set:Npn \pgfsys@blend@mode{\special{ps:~-/\tl_upper_case:n #1~.setblendmode}}}
\makeatother
\ExplSyntaxOff
```

Considerer now the following matrix which we have named `example`.

```
$\begin{pNiceArray}{CCC} [name=example, last-col, create-medium-nodes]
a & a + b & a + b + c & L_1 \\
a & a & a + b & L_2 \\
a & a & a & L_3
\end{pNiceArray}$
```

$$\begin{pmatrix} a & a+b & a+b+c \\ a & a & a+b \\ a & a & a \end{pmatrix} \begin{matrix} L_1 \\ L_2 \\ L_3 \end{matrix}$$

If we want to highlight each row of this matrix, we can use the previous technique three times.

```
\tikzset{mes-options/.style={remember picture,
    overlay,
    name prefix = exemple-,
    highlight/.style = {fill = red!15,
        blend mode = multiply,
        inner sep = 0pt,
        fit = #1}}}
```

```
\begin{tikzpicture}[mes-options]
\node [highlight = (1-1) (1-3)] {} ;
\node [highlight = (2-1) (2-3)] {} ;
\node [highlight = (3-1) (3-3)] {} ;
\end{tikzpicture}
```

We obtain the following matrix.

$$\begin{pmatrix} a & a+b & a+b+c \\ a & a & a+b \\ a & a & a \end{pmatrix} \begin{matrix} L_1 \\ L_2 \\ L_3 \end{matrix}$$

The result may seem disappointing. We can improve it by using the “medium nodes” instead of the “normal nodes”.

```
\begin{tikzpicture}[mes-options, name suffix = -medium]
\node [highlight = (1-1) (1-3)] {} ;
\node [highlight = (2-1) (2-3)] {} ;
\node [highlight = (3-1) (3-3)] {} ;
\end{tikzpicture}
```

We obtain the following matrix.

$$\begin{pmatrix} a & a+b & a+b+c \\ a & a & a+b \\ a & a & a \end{pmatrix} \begin{matrix} L_1 \\ L_2 \\ L_3 \end{matrix}$$

In the following example, we use the “large nodes” to highlight a zone of the matrix.

```
\begin{pNiceArray}{>{\strut}CCCC}%
[create-large-nodes, margin, extra-margin=2pt,
 code-after = {\tikz \path [name suffix = -large,
 fill = red!15,
 blend mode = multiply]
 (1-1.north west)
 |- (2-2.north west)
 |- (3-3.north west)
 |- (4-4.north west)
 |- (4-4.south east)
 |- (1-1.north west) ; } ]
A_{11} & A_{12} & A_{13} & A_{14} \\
A_{21} & A_{22} & A_{23} & A_{24} \\
A_{31} & A_{32} & A_{33} & A_{34} \\
A_{41} & A_{42} & A_{43} & A_{44}
\end{pNiceArray}
```

$$\begin{pmatrix} A_{11} & A_{12} & A_{13} & A_{14} \\ A_{21} & A_{22} & A_{23} & A_{24} \\ A_{31} & A_{32} & A_{33} & A_{34} \\ A_{41} & A_{42} & A_{43} & A_{44} \end{pmatrix}$$

### 13.4 Direct utilisation of the Tikz nodes

In the following example, we illustrate the mathematical product of two matrices.

The utilisation of `{NiceMatrixBlock}` with the option `auto-columns-width` gives the same width for all the columns and, therefore, a perfect alignment of the two superposed matrices.

```
\begin{NiceMatrixBlock}[auto-columns-width]
```

```
\NiceMatrixOptions{nullify-dots}
```

The three matrices will be displayed using an environment `{array}` (an environment `{tabular}` may also be possible).

```
$\begin{array}{cc}
&
\end{array}
```

The matrix  $B$  has a “first row” (for  $C_j$ ) and that’s why we use the key `first-row`.

```
\begin{bNiceArray}{C>{\strut}CCCC} [name=B,first-row]
& & C_j \\
b_{11} & \cdots & b_{1j} & \cdots & b_{1n} \\
\Vdots & & \Vdots & & \Vdots \\
& & b_{kj} \\
& & \Vdots \\
b_{n1} & \cdots & b_{nj} & \cdots & b_{nn}
\end{bNiceArray} \\ \\
```

The matrix  $A$  has a “first column” (for  $L_i$ ) and that’s why we use the key `first-col`.

```
\begin{bNiceArray}{CC>{\strut}CCC} [name=A,first-col]
& a_{11} & \cdots & & a_{nn} \\
& \Vdots & & & \Vdots \\
L_i & a_{i1} & \cdots & a_{ik} & \cdots & a_{in} \\
& \Vdots & & & \Vdots \\
& a_{n1} & \cdots & & a_{nn}
\end{bNiceArray}
&
```

In the matrix product, the two dotted lines have an open extremity.

```
\begin{bNiceArray}{CC>{\strut}CCC}
& & & \\
& & & \Vdots \\
\cdots & & c_{ij} \\
\\
\\
\end{bNiceArray}
\end{array}$

\end{NiceMatrixBlock}

\begin{tikzpicture} [remember picture, overlay]
\node [highlight = (A-3-1) (A-3-5) ] {};
\node [highlight = (B-1-3) (B-5-3) ] {};
\draw [color = gray] (A-3-3) to [bend left] (B-3-3) ;
\end{tikzpicture}
```

$$L_i \begin{bmatrix} a_{11} & \cdots & a_{nn} \\ \vdots & & \vdots \\ a_{i1} & \cdots & a_{ik} & \cdots & a_{in} \\ \vdots & & & & \vdots \\ a_{n1} & \cdots & a_{nn} \end{bmatrix} \quad \begin{bmatrix} b_{11} & \cdots & b_{1j} & \cdots & b_{1n} \\ \vdots & & \vdots & & \vdots \\ b_{n1} & \cdots & b_{nj} & \cdots & b_{nn} \end{bmatrix}^T \quad C_j$$

## 14 Implementation

By default, the package `nicematrix` doesn't patch any existing code.

However, when the option `renew-dots` is used, the commands `\cdots`, `\ldots`, `\dots`, `\vdots`, `\ddots` and `\iddots` are redefined in the environments provided by `nicematrix` as explained previously. In the same way, if the option `renew-matrix` is used, the environment `{matrix}` of `amsmath` is redefined.

On the other hand, the environment `{array}` is never redefined.

Of course, the package `nicematrix` uses the features of the package `array`. It tries to be independent of its implementation. Unfortunately, it was not possible to be strictly independent: the package `nicematrix` relies upon the fact that the package `{array}` uses `\ialign` to begin the `\halign`.

### 14.1 Declaration of the package and extensions loaded

```
<@=@=nicematrix>
```

First, `tikz` and the `Tikz` library `fit` are loaded before the `\ProvidesExplPackage`. They are loaded this way because `\usetikzlibrary` in `expl3` code fails.<sup>22</sup>

```
1 \RequirePackage{tikz}
2 \usetikzlibrary{fit}
3 \RequirePackage{expl3}[2019/07/01]
```

We give the traditional declaration of a package written with `expl3`:

```
4 \RequirePackage{l3keys2e}
5 \ProvidesExplPackage
6   {nicematrix}
7   {`myfiledate}
8   {`myfileversion}
9   {Several features to improve the typesetting of mathematical matrices with TikZ}
```

We test if the class option `draft` has been used. In this case, we raise the flag `\c_@@_draft_bool` because we won't draw the dotted lines if the option `draft` is used.

```
10 \bool_new:N \c_@@_draft_bool
11 \DeclareOption{draft}{\bool_set_true:N \c_@@_draft_bool}
12 \DeclareOption*{ }
13 \ProcessOptions \relax
```

---

<sup>22</sup>cf. [tex.stackexchange.com/questions/57424/using-of-usetikzlibrary-in-an-expl3-package-fails](https://tex.stackexchange.com/questions/57424/using-of-usetikzlibrary-in-an-expl3-package-fails)

The command for the treatment of the options of `\usepackage` is at the end of this package for technical reasons.

We load `array` and `amsmath`.

```

14 \RequirePackage { array }
15 \RequirePackage { amsmath }
16 \RequirePackage { xparse } [ 2018-07-01 ]

17 \cs_new_protected:Npn \@@_error:n { \msg_error:nn { nicematrix } }
18 \cs_new_protected:Npn \@@_error:nn { \msg_error:nnn { nicematrix } }
19 \cs_new_protected:Npn \@@_error:nnn { \msg_error:nnnn { nicematrix } }
20 \cs_new_protected:Npn \@@_fatal:n { \msg_fatal:nn { nicematrix } }
21 \cs_new_protected:Npn \@@_fatal:nn { \msg_fatal:nnn { nicematrix } }
22 \cs_new_protected:Npn \@@_msg_new:nn { \msg_new:nnn { nicematrix } }
23 \cs_new_protected:Npn \@@_msg_new:nnn { \msg_new:nnnn { nicematrix } }

24 \cs_new_protected:Npn \@@_msg_redirect_name:nn
25   { \msg_redirect_name:nnn { nicematrix } }
```

## 14.2 Technical definitions

We test whether the current class is `revtex4-1` or `revtex4-2` because these classes redefines `\array` (of `array`) in a way incompatible with our programmation.

```

26 \bool_new:N \c_@@_revtex_bool
27 \@ifclassloaded { revtex4-1 }
28   { \bool_set_true:N \c_@@_revtex_bool }
29   { }
30 \@ifclassloaded { revtex4-2 }
31   { \bool_set_true:N \c_@@_revtex_bool }
32   { }
```

The following message must be defined right now because it may be used during the loading of the package.

```

33 \@@_msg_new:nn { Draft-mode }
34   { The~compilation~is~in~draft~mode:~the~dotted~lines~won't~be~drawn. }
35 \bool_if:NT \c_@@_draft_bool
36   { \msg_warning:nn { nicematrix } { Draft-mode } }
```

We define a command `\iddots` similar to `\ddots` ( $\cdot\cdot\cdot$ ) but with dots going forward ( $\cdot\cdot\cdot$ ). We use `\ProvideDocumentCommand` of `xparse`, and so, if the command `\iddots` has already been defined (for example by the package `mathdots`), we don't define it again.

```

37 \ProvideDocumentCommand \iddots { }
38   {
39     \mathinner
40     {
41       \mkern 1 mu
42       \raise \p@ \hbox:n { . }
43       \mkern 2 mu
44       \raise 4 \p@ \hbox:n { . }
45       \mkern 2 mu
46       \raise 7 \p@ \vbox { \kern 7 pt \hbox:n { . } } \mkern 1 mu
47     }
48 }
```

This definition is a variant of the standard definition of `\ddots`.

The following counter will count the environments `{NiceArray}`. The value of this counter will be used to prefix the names of the Tikz nodes created in the array.

```
49 \int_new:N \g_@@_env_int
```

We also define a counter to count the environments `{NiceMatrixBlock}`.

```
50 \int_new:N \g_@@_NiceMatrixBlock_int
```

The dimension `\l_@@_columns_width_dim` will be used when the options specify that all the columns must have the same width (but, if the key `columns-width` is used with the special value `auto`, the boolean `\l_@@_auto_columns_width_bool` also will be raised).

```
51 \dim_new:N \l_@@_columns_width_dim
```

The sequence `\g_@@_names_seq` will be the list of all the names of environments used (via the option `name`) in the document: two environments must not have the same name. However, it's possible to use the option `allow-duplicate-names`.

```
52 \seq_new:N \g_@@_names_seq
```

We want to know if we are in an environment of `nicematrix` because we will raise an error if the user tries to use nested environments.

```
53 \bool_new:N \l_@@_in_env_bool
```

If the user uses `{NiceArray}` (and not another environment relying upon `{NiceArrayWithDelims}` like `{pNiceArray}`), we will raise the flag `\l_@@_NiceArray_bool`. We have to know that, because, in `{NiceArray}`, we won't use a structure with `\left` and `\right` and we will use the option of position (`t`, `b` or `c`).

```
54 \bool_new:N \l_@@_NiceArray_bool
```

```
55 \cs_new_protected:Npn \@@_test_if_math_mode:
56 {
57     \if_mode_math: \else:
58         \@@_fatal:n { Outside~math~mode }
59     \fi:
60 }
```

Consider the following code:

```
$\begin{pNiceMatrix}
a & b & c \\
d & e & \Vdots \\
f & \Cdots \\
g & h & i \\
\end{pNiceMatrix}$
```

First, the dotted line created by the `\Vdots` will be drawn. The implicit cell in position 2-3 will be considered as “dotted”. Then, we will have to draw the dotted line specified by the `\Cdots`; the final extremity of that line will be exactly in position 2-3 and, for that new second line, it should be considered as a *closed* extremity (since it is dotted). However, we don't have the (normal) Tikz node of that node (since it's an implicit cell): we can't draw such a line. That's why that dotted line will be said *impossible* and an error will be raised.<sup>23</sup>

```
61 \bool_new:N \l_@@_impossible_line_bool
```

We have to know whether `colortbl` is loaded for the redefinition of `\everycr` and for `\vline`.

```
62 \bool_new:N \c_@@_colortbl_loaded_bool
63 \AtBeginDocument
64 {
65     \ifpackageloaded { colortbl }
66     {
67         \bool_set_true:N \c_@@_colortbl_loaded_bool
68         \cs_set_protected:Npn \@@_vline_i: { \CT@arc@ \vline } }
69     }
70     { }
71 }
```

---

<sup>23</sup>Of course, the user should solve the problem by adding the lacking ampersands.

The length `\l_@@_inter_dots_dim` is the distance between two dots for the dotted lines. The default value is 0.45 em but it will be changed if the option `small` is used.

```
72 \dim_new:N \l_@@_inter_dots_dim
73 \dim_set:Nn \l_@@_inter_dots_dim { 0.45 em }
```

The length `\l_@@_dotted_lines_margin_dim` is the minimal distance between a node (in fact an anchor of that node) and a dotted line (we say “minimal” because, by definition, a dotted line is not a continuous line and, therefore, this distance may vary a little).

```
74 \dim_new:N \l_@@_dotted_lines_margin_dim
75 \dim_set:Nn \l_@@_dotted_lines_margin_dim { 0.3 em }
```

The length `\l_@@_radius_dim` is the radius of the dots for the dotted lines. The default value is 0.34 pt but it will be changed if the option `small` is used.

```
76 \dim_new:N \l_@@_radius_dim
77 \dim_set:Nn \l_@@_radius_dim { 0.53 pt }
```

The name of the current environment or the current command (will be used only in the error messages).

```
78 \str_new:N \g_@@_type_env_str
79 \tl_new:N \g_@@_code_after_tl
```

The counters `\l_@@_save_iRow_int` and `\l_@@_save_jCol_int` will be used to save the values of the eventual LaTeX counters `iRow` and `jCol`. These LaTeX counters will be restored at the end of the environment.

```
80 \int_new:N \l_@@_save_iRow_int
81 \int_new:N \l_@@_save_jCol_int
```

The TeX counters `\c@iRow` and `\c@jCol` will be created in the beginning of the environment `{NiceArrayWithDelims}` (if they don’t exist previously).

#### 14.2.1 Variables for the exterior rows and columns

The keys for the exterior rows and columns are `first-row`, `first-col`, `last-row` and `last-col`. However, internally, these keys are not coded in a similar way.

- **First row**

The integer `\l_@@_first_row_int` is the number of the first row of the array. The default value is 1, but, if the option `first-row` is used, the value will be 0. As usual, the global version is for the passage in the `\group_insert_after:N`.

```
82 \int_new:N \l_@@_first_row_int
83 \int_set:Nn \l_@@_first_row_int 1
```

- **First column**

The integer `\l_@@_first_col_int` is the number of the first column of the array. The default value is 1, but, if the option `first-col` is used, the value will be 0.

```
84 \int_new:N \l_@@_first_col_int
85 \int_set:Nn \l_@@_first_col_int 1
```

- **Last row**

The counter `\l_@@_last_row_int` is the number of the eventual “last row”, as specified by the key `last-row`. A value of `-2` means that there is no “last row”. A value of `-1` means that there is a “last row” but we don’t know the number of that row (the key `last-row` has been used without value and the actual value has not still been read in the `aux` file).

```
86   \int_new:N \l_@@_last_row_int
87   \int_set:Nn \l_@@_last_row_int { -2 }
```

If, in an environment like `{pNiceArray}`, the option `last-row` is used without value, we will globally raise the following flag. It will be used to know if we have, after the construction of the array, to write in the `aux` file the number of the “last row”.<sup>24</sup>

```
88   \bool_new:N \l_@@_last_row_without_value_bool
```

- **Last column**

For the eventual “last column”, we use an integer. A value of `-1` means that there is no last column.

```
89   \int_new:N \l_@@_last_col_int
90   \int_set:Nn \l_@@_last_col_int { -1 }
```

However, we have also a boolean. Consider the following code:

```
\begin{pNiceArray}{CC}[last-col]
1 & 2 \\
3 & 4
\end{pNiceArray}
```

In such a code, the “last column” specified by the key `last-col` is not used. We want to be able to detect such a situation and we create a boolean for that job.

```
91   \bool_new:N \g_@@_last_col_found_bool
```

This boolean is set to `false` at the end of `\@_pre_array`:

#### 14.2.2 The column S of siunitx

We want to know whether the package `siunitx` is loaded and, if it is loaded, we redefine the `S` columns of `siunitx`.

```
92 \bool_new:N \c_@@_siunitx_loaded_bool
93 \AtBeginDocument
94 {
95   \@ifpackageloaded { siunitx }
96   { \bool_set_true:N \c_@@_siunitx_loaded_bool }
97   { }
98 }
```

The command `\NC@rewrite@S` is a LaTeX command created by `siunitx` in connection with the `S` column. In the code of `siunitx`, this command is defined by:

---

<sup>24</sup>We can’t use `\l_@@_last_row_int` for this usage because, if `nicematrix` has read its value from the `aux` file, the value of the counter won’t be `-1` any longer.

```
\renewcommand*{\NC@rewrite@S}[1] []
{
  \@temptokena \exp_after:wN
  {
    \tex_the:D \@temptokena
    > { \__siunitx_table_collect_begin: S {#1} }
    c
    < { \__siunitx_table_print: }
  }
  \NC@find
}
```

We want to patch this command (in the environments of `nicematrix`) in order to have:

```
\renewcommand*{\NC@rewrite@S}[1] []
{
  \@temptokena \exp_after:wN
  {
    \tex_the:D \@temptokena
    > { \@@_Cell: \__siunitx_table_collect_begin: S {#1} }
    c
    < { \__siunitx_table_print: \@@_end_Cell: }
  }
  \NC@find
}
```

However, we don't want do use explicitly any private command of `siunitx`. That's why we will extract the name of the two `\__siunitx...` commands by their position in the code of `\NC@rewrite@S`. Since the command `\NC@rewrite@S` appends some tokens to the *toks* list `\@temptokena`, we use the LaTeX command `\NC@rewrite@S` in a group (`\group_begin:-\group_end:`) and we extract the two command names which are in the toks `\@temptokena`. However, this extraction can be done only when `siunitx` is loaded (and it may be loaded after `nicematrix`) and, in fact, after the beginning of the document — because some instructions of `siunitx` are executed in a `\AtBeginDocument`). That's why this extraction will be done only at the first utilisation of an environment of `nicematrix` with the command `\@@_adapt_S_column:`.

```
99 \cs_set_protected:Npn \@@_adapt_S_column:
100 {
```

In the preamble of the LaTeX document, the boolean `\c_@@_siunitx_loaded_bool` won't be known. That's why we test the existence of `\c_@@_siunitx_loaded_bool` and not its value.<sup>25</sup>

```
101 \bool_if:NT \c_@@_siunitx_loaded_bool
102 {
103   \group_begin:
104   \@temptokena = { }
```

We protect `\NC@find` which is at the end of `\NC@rewrite@S`.

```
105 \cs_set_eq:NN \NC@find \prg_do_nothing:
106 \NC@rewrite@S { }
```

Conversion of the *toks* `\@temptokena` in a token list of `expl3` (the toks are not supported by `expl3` but we can, nevertheless, use the option `V` for `\tl_gset:NV`).

```
107 \tl_gset:NV \g_tmpa_tl \@temptokena
108 \group_end:
109 \tl_new:N \c_@@_table_collect_begin_tl
110 \tl_set:Nx \l_tmpa_tl { \tl_item:Nn \g_tmpa_tl 2 }
111 \tl_gset:Nx \c_@@_table_collect_begin_tl { \tl_item:Nn \l_tmpa_tl 1 }
112 \tl_new:N \c_@@_table_print_tl
113 \tl_gset:Nx \c_@@_table_print_tl { \tl_item:Nn \g_tmpa_tl { -1 } }
```

---

<sup>25</sup>Indeed, `nicematrix` may be used in the preamble of the LaTeX document. For example, in this document, we compose a matrix in the box `\ExampleOne` before loading `arydshln` (because `arydshln` is not totally compatible with `nicematrix`).

The token lists `\c_@@_table_collect_begin_tl` and `\c_@@_table_print_tl` contain now the two commands of `siunitx`.

If the adaptation has been done, the command `\@@_adapt_S_column:` becomes no-op (globally).

```
114     \cs_gset_eq:NN \@@_adapt_S_column: \prg_do_nothing:
115     }
116 }
```

The command `\@@_renew_NC@rewrite@S:` will be used in each environment of `nicematrix` in order to “rewrite” the S column in each environment (only if the boolean `\c_@@_siunitx_loaded_bool` is raised, of course).

```
117 \cs_new_protected:Npn \@@_renew_NC@rewrite@S:
118 {
119     \renewcommand*{\NC@rewrite@S}[1] []
120     {
121         \otemptokena \exp_after:wN
122         {
123             \tex_the:D \otemptokena
124             > { \@@_Cell: \c_@@_table_collect_begin_tl S {##1} }
125             c
126             < { \c_@@_table_print_tl \@@_end_Cell: }
127         }
128         \NC@find
129     }
130 }
```

### 14.3 The options

The boolean `\l_@@_light_syntax_bool` corresponds to the option `light-syntax`.

```
131 \bool_new:N \l_@@_light_syntax_bool
```

The token list `\l_@@_pos_env_str` will contain one of the three values `t`, `c` or `b` and will indicate the position of the environment as in the option of the environment `{array}`. For the environment `{pNiceMatrix}`, `{pNiceArray}` and their variants, the value will programmatically be fixed to `c`. For the environment `{NiceArray}`, however, the three values `t`, `c` and `b` are possible.

```
132 \str_new:N \l_@@_pos_env_str
133 \str_set:Nn \l_@@_pos_env_str c
```

The flag `\l_@@_exterior_arraycolsep_bool` corresponds to the option `exterior-arraycolsep`. If this option is set, a space equal to `\arraycolsep` will be put on both sides of an environment `{NiceArray}` (as it is done in `{array}` of `array`).

```
134 \bool_new:N \l_@@_exterior_arraycolsep_bool
```

The flag `\l_@@_parallelize_diags_bool` controls whether the diagonals are parallelized. The initial value is `true`.

```
135 \bool_new:N \l_@@_parallelize_diags_bool
136 \bool_set_true:N \l_@@_parallelize_diags_bool
```

The flag `\l_@@_hlines_bool` corresponds to the option `\hlines`.

```
137 \bool_new:N \l_@@_hlines_bool
```

The flag `\l_@@_nullify_dots_bool` corresponds to the option `nullify-dots`. When the flag is down, the instructions like `\vdots` are inserted within a `\phantom` (and so the constructed matrix has exactly the same size as a matrix constructed with the classical `{matrix}` and `\ldots`, `\vdots`, etc.).

```
138 \bool_new:N \l_@@_nullify_dots_bool
```

The following flag will be used when the current options specify that all the columns of the array must have the same width equal to the largest width of a cell of the array (except the cells of the potential exterior columns).

```
139 \bool_new:N \l_@@_auto_columns_width_bool
```

The token list `\l_@@_name_str` will contain the optional name of the environment: this name can be used to access to the Tikz nodes created in the array from outside the environment.

```
140 \str_new:N \l_@@_name_str
```

The boolean `\l_@@_extra_medium_bool` will be used to indicate whether the “medium nodes” are created in the array. Idem for the “large nodes”.

```
141 \bool_new:N \l_@@_medium_nodes_bool
142 \bool_new:N \g_@@_medium_nodes_bool
143 \bool_new:N \l_@@_large_nodes_bool
144 \bool_new:N \g_@@_large_nodes_bool
```

The dimensions `\l_@@_left_margin_dim` and `\l_@@_right_margin_dim` correspond to the options `left-margin` and `right-margin`.

```
145 \dim_new:N \l_@@_left_margin_dim
146 \dim_new:N \l_@@_right_margin_dim
147 \dim_new:N \g_@@_width_last_col_dim
148 \dim_new:N \g_@@_width_first_col_dim
```

The dimensions `\l_@@_extra_left_margin_dim` and `\l_@@_extra_right_margin_dim` correspond to the options `extra-left-margin` and `extra-right-margin`.

```
149 \dim_new:N \l_@@_extra_left_margin_dim
150 \dim_new:N \l_@@_extra_right_margin_dim
```

The token list `\l_@@_end_of_row_tl` corresponds to the option `end-of-row`. It specifies the symbol used to mark the ends of rows when the light syntax is used.

```
151 \tl_new:N \l_@@_end_of_row_tl
152 \tl_set:Nn \l_@@_end_of_row_tl { ; }
```

First, we define a set of keys “`NiceMatrix / Global`” which will be used (with the mechanism of `.inherit:n`) by other sets of keys.

```
153 \keys_define:nn { NiceMatrix / Global }
  {
    dotted-lines-margin .dim_set:N = \l_@@_dotted_lines_margin_dim ,
    dotted-lines-margin .value_required:n = true ,
    light-syntax .bool_set:N = \l_@@_light_syntax_bool ,
    light-syntax .default:n = true ,
    end-of-row .tl_set:N = \l_@@_end_of_row_tl ,
    end-of-row .value_required:n = true ,
    code-for-first-col .tl_set:N = \l_@@_code_for_first_col_tl ,
    code-for-first-col .value_required:n = true ,
    code-for-last-col .tl_set:N = \l_@@_code_for_last_col_tl ,
    code-for-last-col .value_required:n = true ,
    code-for-first-row .tl_set:N = \l_@@_code_for_first_row_tl ,
    code-for-first-row .value_required:n = true ,
    code-for-last-row .tl_set:N = \l_@@_code_for_last_row_tl ,
    code-for-last-row .value_required:n = true ,
    small .bool_set:N = \l_@@_small_bool ,
    hlines .bool_set:N = \l_@@_hlines_bool ,
    parallelize-diags .bool_set:N = \l_@@_parallelize_diags_bool ,
```

With the option `renew-dots`, the command `\cdots`, `\ldots`, `\vdots` and `\ddots` are redefined and behave like the commands `\Cdots`, `\Ldots`, `\Vdots` and `\Ddots`.

```
172 renew-dots .bool_set:N = \l_@@_renew_dots_bool ,
173 renew-dots .value_forbidden:n = true ,
174 nullify-dots .bool_set:N = \l_@@_nullify_dots_bool ,
```

In some circumstances, the “medium nodes” are created automatically, for example when a dotted line has an “open” extremity (idem for the “large nodes”).

```

175  create-medium-nodes .bool_set:N = \l_@@_medium_nodes_bool ,
176  create-large-nodes .bool_set:N = \l_@@_large_nodes_bool ,
177  create-extra-nodes .meta:n =
178    { create-medium-nodes , create-large-nodes } ,
179  left-margin .dim_set:N = \l_@@_left_margin_dim ,
180  left-margin .default:n = \arraycolsep ,
181  right-margin .dim_set:N = \l_@@_right_margin_dim ,
182  right-margin .default:n = \arraycolsep ,
183  margin .meta:n = { left-margin = #1 , right-margin = #1 } ,
184  margin .default:n = \arraycolsep ,
185  extra-left-margin .dim_set:N = \l_@@_extra_left_margin_dim ,
186  extra-right-margin .dim_set:N = \l_@@_extra_right_margin_dim ,
187  extra-margin .meta:n =
188    { extra-left-margin = #1 , extra-right-margin = #1 }
189 }
```

We define a set of keys used by the environments of `nicematrix` (but not by the command `\NiceMatrixOptions`).

```

190 \keys_define:nn { NiceMatrix / Env }
191 {
192  columns-width .code:n =
193    \str_if_eq:nnTF { #1 } { auto }
194      { \bool_set_true:N \l_@@_auto_columns_width_bool }
195      { \dim_set:Nn \l_@@_columns_width_dim { #1 } } ,
196  columns-width .value_required:n = true ,
197  name .code:n =
198    \unless \ifmeasuring@
199      \str_set:Nn \l_tmpa_str { #1 }
200      \seq_if_in:NVTF \g_@@_names_seq \l_tmpa_str
201        { \@@_error:nn { Duplicate~name } { #1 } }
202        { \seq_gput_left:NV \g_@@_names_seq \l_tmpa_str }
203      \str_set_eq:NN \l_@@_name_str \l_tmpa_str
204    \fi ,
205  name .value_required:n = true ,
206  code-after .tl_gset:N = \g_@@_code_after_tl ,
207  code-after .value_required:n = true ,
208  first-col .code:n = \int_zero:N \l_@@_first_col_int ,
209  first-row .code:n = \int_zero:N \l_@@_first_row_int ,
210  last-row .int_set:N = \l_@@_last_row_int ,
211  last-row .default:n = -1 ,
212 }
```

We begin the construction of the major sets of keys (used by the different user commands and environments).

```

213 \keys_define:nn { NiceMatrix }
214 {
215  NiceMatrixOptions .inherit:n =
216    {
217      NiceMatrix / Global ,
218    } ,
219  NiceMatrix .inherit:n =
220    {
221      NiceMatrix / Global ,
222      NiceMatrix / Env
223    } ,
224  NiceArray .inherit:n =
225    {
226      NiceMatrix / Global ,
227      NiceMatrix / Env ,
228    } ,
```

```

229 pNiceArray .inherit:n =
230 {
231     NiceMatrix / Global ,
232     NiceMatrix / Env ,
233 }
234 }
```

We finalise the definition of the set of keys “`NiceMatrix / NiceMatrixOptions`” with the options specific to `\NiceMatrixOptions`.

```

235 \keys_define:nn { NiceMatrix / NiceMatrixOptions }
236 {
```

With the option `renew-matrix`, the environment `{matrix}` of `amsmath` and its variants are redefined to behave like the environment `{NiceMatrix}` and its variants.

```

237 renew-matrix .code:n = \@@_renew_matrix: ,
238 renew-matrix .value_forbidden:n = true ,
239 RenewMatrix .code:n = \@@_error:n { Option~RenewMatrix~suppressed } ,
240 transparent .meta:n = { renew-dots , renew-matrix } ,
241 transparent .value_forbidden:n = true,
242 Transparent .code:n = \@@_error:n { Option~Transparent~suppressed } ,
```

The option `exterior-arraycolsep` will have effect only in `{NiceArray}` for those who want to have for `{NiceArray}` the same behaviour as `{array}`.

```

243 exterior-arraycolsep .bool_set:N = \l_@@_exterior_arraycolsep_bool ,
```

If the option `columns-width` is used, all the columns will have the same width.

In `\NiceMatrixOptions`, the special value `auto` is not available.

```

244 columns-width .code:n =
245 \str_if_eq:nnTF { #1 } { auto }
246 { \@@_error:n { Option~auto~for~columns~width } }
247 { \dim_set:Nn \l_@@_columns_width_dim { #1 } } ,
```

Usually, an error is raised when the user tries to give the same to name two distincts environments of `nicematrix` (theses names are global and not local to the current TeX scope). However, the option `allow-duplicate-names` disables this feature.

```

248 allow-duplicate-names .code:n =
249 \@@_msg_redirect_name:nn { Duplicate-name } { none } ,
250 allow-duplicate-names .value_forbidden:n = true ,
```

By default, the specifier used in the preamble of the array (for example in `{pNiceArray}`) to draw a vertical dotted line between two columns is the colon “`:`”. However, it’s possible to change this letter with `letter-for-dotted-lines` and, by the way, the letter “`:`” will remain free for other packages (for example `arydshln`).

```

251 letter-for-dotted-lines .code:n =
252 {
253     \int_compare:nTF { \tl_count:n { #1 } = \c_one_int }
254     { \str_set:Nx \l_@@_letter_for_dotted_lines_str { #1 } }
255     { \@@_error:n { Bad~value~for~letter~for~dotted~lines } }
256 },
257 letter-for-dotted-lines .value_required:n = true ,

258 unknown .code:n = \@@_error:n { Unknown~key~for~NiceMatrixOptions }
259 }

260 \str_new:N \l_@@_letter_for_dotted_lines_str
261 \str_set_eq:NN \l_@@_letter_for_dotted_lines_str \c_colon_str
```

`\NiceMatrixOptions` is the command of the `nicematrix` package to fix options at the document level. The scope of these specifications is the current TeX group.

```
262 \NewDocumentCommand \NiceMatrixOptions { m }
263   { \keys_set:nn { NiceMatrix / NiceMatrixOptions } { #1 } }
```

We finalise the definition of the set of keys “`NiceMatrix / NiceMatrix`” with the options specific to `{NiceMatrix}`.

```
264 \keys_define:nn { NiceMatrix / NiceMatrix }
265   {
266     last-col .code:n = \tl_if_empty:nTF {#1}
267       { \@@_error:n { last-col~empty~for~NiceMatrix } }
268       { \int_set:Nn \l_@@_last_col_int { #1 } } ,
269     unknown .code:n = \@@_error:n { Unknown~option~for~NiceMatrix }
270   }
```

We finalise the definition of the set of keys “`NiceMatrix / NiceArray`” with the options specific to `{NiceArray}`.

```
271 \keys_define:nn { NiceMatrix / NiceArray }
272   {
```

The options `c`, `t` and `b` of the environment `{NiceArray}` have the same meaning as the option of the classical environment `{array}`.

```
273   c .code:n = \str_set:Nn \l_@@_pos_env_str c ,
274   t .code:n = \str_set:Nn \l_@@_pos_env_str t ,
275   b .code:n = \str_set:Nn \l_@@_pos_env_str b ,
```

In the environments `{NiceArray}` and its variants, the option `last-col` must be used without value because the number of columns of the array can be read in the preamble of the array.

```
276   last-col .code:n = \tl_if_empty:nF {#1}
277     { \@@_error:n { last-col~non~empty~for~NiceArray } }
278     \int_zero:N \l_@@_last_col_int ,
279   unknown .code:n = \@@_error:n { Unknown~option~for~NiceArray }
280 }

281 \keys_define:nn { NiceMatrix / pNiceArray }
282   {
283     first-col .code:n = \int_zero:N \l_@@_first_col_int ,
284     last-col .code:n = \tl_if_empty:nF {#1}
285       { \@@_error:n { last-col~non~empty~for~NiceArray } }
286       \int_zero:N \l_@@_last_col_int ,
287     first-row .code:n = \int_zero:N \l_@@_first_row_int ,
288     last-row .int_set:N = \l_@@_last_row_int ,
289     last-row .default:n = -1 ,
290   unknown .code:n = \@@_error:n { Unknown~option~for~NiceMatrix }
291 }
```

## 14.4 Important code used by `{NiceArrayWithDelims}`

The pseudo-environment `\@@_Cell:-\@@_end_Cell:` will be used to format the cells of the array. In the code, the affectations are global because this pseudo-environment will be used in the cells of a `\halign` (via an environment `{array}`).

```
292 \cs_new_protected:Nn \@@_Cell:
293   {
```

We increment `\c@jCol`, which is the counter of the columns.

```
294   \int_gincr:N \c@jCol
```

Now, we increment the counter of the rows. We don't do this incrementation in the `\everycr` because some packages, like `arydshln`, create special rows in the `\halign` that we don't want to take into account.

```

295   \int_compare:nNnT \c@jCol = \c_one_int
296   {
297     \int_compare:nNnT \l_@@_first_col_int = \c_one_int
298     \@@_begin_of_row:
299   }
300   \int_gset:Nn \g_@@_col_total_int
301   { \int_max:nn \g_@@_col_total_int \c@jCol }
```

The content of the cell is composed in the box `\l_tmpa_box` because we want to compute some dimensions of the box. The `\hbox_set_end:` corresponding to this `\hbox_set:Nw` will be in the `\@@_end_Cell:` (and the `\c_math_toggle_token` also).

```

302   \hbox_set:Nw \l_tmpa_box
303   \c_math_toggle_token
304   \bool_if:NT \l_@@_small_bool \scriptstyle
```

We will call *corners* of the matrix the cases which are at the intersection of the exterior rows and exterior columns (of course, the four corners doesn't always exist simultaneously). The codes `\l_@@_code_for_first_row_tl` and `al` don't apply in the corners of the matrix.

```

305   \int_compare:nNnTF \c@iRow = \c_zero_int
306   { \int_compare:nNnT \c@jCol > \c_zero_int \l_@@_code_for_first_row_tl }
307   {
308     \int_compare:nNnT \c@iRow = \l_@@_last_row_int
309     \l_@@_code_for_last_row_tl
310   }
311 }
```

The following macro `\@@_begin_of_row` is usually used in the cell number 1 of the array. However, when the key `first-col` is used, `\@@_begin_of_row` is executed in the cell number 0 of the array.

```

312 \cs_new_protected:Nn \@@_begin_of_row:
313 {
314   \int_gincr:N \c@iRow
315   \dim_gset_eq:NN \g_@@_dp_ante_last_row_dim \g_@@_dp_last_row_dim
316   \dim_gzero:N \g_@@_dp_last_row_dim
317   \dim_gzero:N \g_@@_ht_last_row_dim
318 }
```

The following code is used in each cell of the array. It actualises quantities that, at the end of the array, will give informations about the vertical dimension of the two first rows and the two last rows.

```

319 \cs_new_protected:Npn \@@_actualization_for_first_and_last_row:
320 {
321   \int_compare:nNnT \c@iRow = \c_zero_int
322   {
323     \dim_gset:Nn \g_@@_dp_row_zero_dim
324     { \dim_max:nn \g_@@_dp_row_zero_dim { \box_dp:N \l_tmpa_box } }
325     \dim_gset:Nn \g_@@_ht_row_zero_dim
326     { \dim_max:nn \g_@@_ht_row_zero_dim { \box_ht:N \l_tmpa_box } }
327   }
328   \int_compare:nNnT \c@iRow = \c_one_int
329   {
330     \dim_gset:Nn \g_@@_ht_row_one_dim
331     { \dim_max:nn \g_@@_ht_row_one_dim { \box_ht:N \l_tmpa_box } }
332   }
333   \dim_gset:Nn \g_@@_ht_last_row_dim
334   { \dim_max:nn \g_@@_ht_last_row_dim { \box_ht:N \l_tmpa_box } }
335   \dim_gset:Nn \g_@@_dp_last_row_dim
336   { \dim_max:nn \g_@@_dp_last_row_dim { \box_dp:N \l_tmpa_box } }
337 }
```

```

338 \cs_new_protected:Nn \@@_end_Cell:
339 {
340     \c_math_toggle_token
341     \hbox_set_end:

```

We want to compute in `\g_@@_max_cell_width_dim` the width of the widest cell of the array (except the cells of the “first column” and the “last column”).

```

342     \dim_gset:Nn \g_@@_max_cell_width_dim
343         { \dim_max:nn \g_@@_max_cell_width_dim { \box_wd:N \l_tmpa_box } }

```

The following computations are for the “first row” and the “last row”.

```

344     \@@_actualization_for_first_and_last_row:

```

Now, we can create the Tikz node of the cell.

```

345 \tikz
346 [
347     remember~picture ,
348     inner~sep = \c_zero_dim ,
349     minimum~width = \c_zero_dim ,
350     baseline
351 ]
352 \node
353 [
354     anchor = base ,
355     name = nm - \int_use:N \g_@@_env_int -
356             \int_use:N \c@iRow -
357             \int_use:N \c@jCol ,
358     alias =
359         \str_if_empty:NF \l_@@_name_str
360         {
361             \l_@@_name_str -
362             \int_use:N \c@iRow -
363             \int_use:N \c@jCol
364         }
365     ]
366 \bgroup
367 \box_use:N \l_tmpa_box
368 \egroup ;
369 }
370 \cs_generate_variant:Nn \dim_set:Nn { N x }

```

In the environment `{NiceArrayWithDelims}`, we will have to redefine the column types `w` and `W`. These definitions are rather long because we have to construct the `w`-nodes in these columns. The redefinition of these two column types are very close and that’s why we use a macro `\@@_renewcolumntype:nn`. The first argument is the type of the column (`w` or `W`) and the second argument is a code inserted at a special place and which is the only difference between the two definitions.

```

371 \cs_new_protected:Nn \@@_renewcolumntype:nn
372 {
373     \newcolumntype #1 [ 2 ]
374     {
375         > {
376             \hbox_set:Nw \l_tmpa_box
377             \_@@_Cell:
378         }
379         c
380         < {
381             \_@@_end_Cell:
382             \hbox_set_end:
383             #2
384             \tikz [ remember~picture ]
385             \node
386             [

```

```

387     name = nm - \int_use:N \g_@@_env_int -
388             \int_use:N \c@iRow -
389             \int_use:N \c@jCol - w,
390     alias =
391         \str_if_empty:NF \l_@@_name_str
392     {
393         \l_@@_name_str -
394         \int_use:N \c@iRow -
395         \int_use:N \c@jCol - w
396     } ,
397     inner_sep = \c_zero_dim ,
398 ]
399 { \makebox [ ##2 ] [ ##1 ] { \box_use:N \l_tmpa_box } }
400 ;
401 }
402 }
403 }
```

The argument of the following command `\@@_instruction_of_type:n` defined below is the type of the instruction (Cdots, Vdots, Ddots, etc.). This command writes in the corresponding `\g_@@_type_lines_tl` the instruction which will really draw the line after the construction of the matrix.

For example, for the following matrix,

```
\begin{pNiceMatrix}
1 & 2 & 3 & 4 \\
5 & \Cdots & & 6 \\
7 & \Cdots \\
\end{pNiceMatrix}
```

$$\begin{pmatrix} 1 & 2 & 3 & 4 \\ 5 & \cdots & & 6 \\ 7 & \cdots & & \end{pmatrix}$$

the content of `\g_@@_Cdots_lines_tl` will be:

```
\@@_draw_Cdots:nn {2}{2}
\@@_draw_Cdots:nn {3}{2}
```

We begin with a test of the flag `\c_@@_draft_bool` because, if the key `draft` is used, the dotted lines are not drawn.

```

404 \bool_if:NTF \c_@@_draft_bool
405   { \cs_set_protected:Npn \@@_instruction_of_type:n #1 { } }
406   {
407     \cs_new_protected:Npn \@@_instruction_of_type:n #1
408     { }
```

It's important to use a `\tl_gput_right:cx` and not a `\tl_gput_left:cx` because we want the `\Ddots` lines to be drawn in the order of appearance in the array (for parallelisation).

```

409   \tl_gput_right:cx
410   { g_@@_#1 _ lines _ tl }
411   {
412     \use:c { @@ _ draw _ #1 : nn }
413     { \int_use:N \c@iRow }
414     { \int_use:N \c@jCol }
415   }
416 }
417 }
```

We want to use `\array` of `array`. However, if the class used is `revtex4-1` or `revtex4-2`, we have to do some tuning and use the command `\@array@array` instead of `\array` because these classes do a redefinition of `\array` incompatible with our use of `\array`.

```

418 \cs_new_protected:Npn \@@_array:
419   {
420     \bool_if:NTF \c_@@_revtex_bool
421     {
422       \cs_set_eq:NN \@acoll \@arrayacol
```

```

423     \cs_set_eq:NN \acolr \arrayacol
424     \cs_set_eq:NN \acol \arrayacol
425     \cs_set:Npn \chalignto { }
426     \array@array
427   }
428 \array
\l_@@_pos_env_str may have the value t, c or b.
429 [ \l_@@_pos_env_str ]
430 }

```

The following must *not* be protected because it begins with `\noalign`.

```

431 \cs_new:Npn \@@_everycr:
432   { \noalign { \@@_everycr_i: } }
433 \cs_new_protected:Npn \@@_everycr_i:
434   {
435     \int_gzero:N \c@jCol
436     \bool_if:NT \l_@@_hlines_bool
437   }

```

The counter `\c@iRow` has the value  $-1$  only if there is a “first row” and that we are before that “first row”, i.e. just before the beginning of the array.

```

438   \int_compare:nNnT \c@iRow > { -1 }
439   {
440     \int_compare:nNnF \c@iRow = \l_@@_last_row_int
441     {
442       \hrule \height \arrayrulewidth
443       \skip_vertical:n { - \arrayrulewidth }
444     }
445   }
446 }
447 }

```

The following code `\@@_pre_array:` is used in `{NiceArrayWithDelims}`. It exists as a standalone macro only for lisibility.

```

448 \cs_new_protected:Npn \@@_pre_array:
449   {
450     \cs_if_exist:NT \theiRow
451       { \int_set_eq:NN \l_@@_save_iRow_int \c@iRow }
452     \int_gzero_new:N \c@iRow
453     \cs_if_exist:NT \thejCol
454       { \int_set_eq:NN \l_@@_save_jCol_int \c@jCol }
455     \int_gzero_new:N \c@jCol
456     \normalbaselines

```

If the option `small` is used, we have to do some tuning. In particular, we change the value of `\arraystretch` (this parameter is used in the construction of `\carstrutbox` in the beginning of `{array}`).

```

457 \bool_if:NT \l_@@_small_bool
458   {
459     \cs_set:Npn \arraystretch { 0.47 }
460     \dim_set:Nn \arraycolsep { 1.45 pt }
461   }

```

We switch to a global version of the `\l_@@_medium_nodes_bool` and `\l_@@_large_nodes_bool` because these booleans may be raised in cells of the array (for exemple in commands `\Block`).

```

462 \bool_gset_eq:NN \g_@@_medium_nodes_bool \l_@@_medium_nodes_bool
463 \bool_gset_eq:NN \g_@@_large_nodes_bool \l_@@_large_nodes_bool

```

The environment `{array}` uses internally the command `\ialign`. We change the definition of `\ialign` for several reasons. In particular, `\ialign` sets `\everycr` to `{ }` and we *need* to have to change the value of `\everycr`.

```

464   \cs_set:Npn \ialign
465   {
466     \bool_if:NTF \c_@@_colortbl_loaded_bool
467     {
468       \CT@everycr
469       {
470         \noalign { \cs_gset_eq:NN \CT@row@color \prg_do_nothing: }
471         \c_@@_everycr:
472       }
473     }
474     { \everycr { \c_@@_everycr: } }
475   \tabskip = \c_zero_skip

```

The box `\@arstrutbox` is a box constructed in the beginning of the environment `{array}`. The construction of that box takes into account the current values of `\arraystretch`<sup>26</sup> and `\extrarowheight` (of `array`). That box is inserted (via `\@arstrut`) in the beginning of each row of the array. That's why we use the dimensions of that box to initialize the variables which will be the dimensions of the potential first and last row of the environment. This initialization must be done after the creation of `\@arstrutbox` and that's why we do it in the `\ialign`.

```

476   \dim_gzero_new:N \g_@@_dp_row_zero_dim
477   \dim_gset:Nn \g_@@_dp_row_zero_dim { \box_dp:N \@arstrutbox }
478   \dim_gzero_new:N \g_@@_ht_row_zero_dim
479   \dim_gset:Nn \g_@@_ht_row_zero_dim { \box_ht:N \@arstrutbox }
480   \dim_gzero_new:N \g_@@_ht_row_one_dim
481   \dim_gset:Nn \g_@@_ht_row_one_dim { \box_ht:N \@arstrutbox }
482   \dim_gzero_new:N \g_@@_dp_ante_last_row_dim
483   \dim_gset:Nn \g_@@_dp_ante_last_row_dim { \box_dp:N \@arstrutbox }
484   \dim_gzero_new:N \g_@@_ht_last_row_dim
485   \dim_gset:Nn \g_@@_ht_last_row_dim { \box_ht:N \@arstrutbox }
486   \dim_gzero_new:N \g_@@_dp_last_row_dim
487   \dim_gset:Nn \g_@@_dp_last_row_dim { \box_dp:N \@arstrutbox }

```

After its first utilisation, the definition of `\ialign` will revert automatically to its default definition. With this programmation, we will have, in the cells of the array, a clean version of `\ialign`.<sup>27</sup>

```

488   \cs_set:Npn \ialign
489   {
490     \everycr { }
491     \tabskip = \c_zero_skip
492     \halign
493     {
494       \halign
495     }

```

We define the new column types `L`, `C` and `R` that must be used instead of `l`, `c` and `r` in the preamble of `{NiceArray}`.

```

496   \newcolumntype L { > \c_@@_Cell: l < \c_@@_end_Cell: }
497   \newcolumntype C { > \c_@@_Cell: c < \c_@@_end_Cell: }
498   \newcolumntype R { > \c_@@_Cell: r < \c_@@_end_Cell: }

499   \cs_set_eq:NN \Ldots \c_@@_Ldots
500   \cs_set_eq:NN \Cdots \c_@@_Cdots
501   \cs_set_eq:NN \Vdots \c_@@_Vdots
502   \cs_set_eq:NN \Ddots \c_@@_Ddots
503   \cs_set_eq:NN \Iddots \c_@@_Iddots
504   \cs_set_eq:NN \hdottedline \c_@@_hdottedline:
505   \cs_set_eq:NN \Hspace \c_@@_Hspace:
506   \cs_set_eq:NN \Hdotsfor \c_@@_Hdotsfor:

```

---

<sup>26</sup>The option `small` of `nicematrix` changes (among other) the value of `\arraystretch`. This is done, of course, before the call of `{array}`.

<sup>27</sup>The user will probably not employ directly `\ialign` in the array... but more likely environments that utilize `\ialign` internally (e.g.: `{substack}`).

```

507 \cs_set_eq:NN \multicolumn \@@_multicolumn:nnn
508 \cs_set_eq:NN \Block \@@_Block:
509 \cs_set_eq:NN \OnlyMainNiceMatrix \@@_OnlyMainNiceMatrix:n
510 \bool_if:NT \l_@@_renew_dots_bool
511 {
512     \cs_set_eq:NN \ldots \@@_Ldots
513     \cs_set_eq:NN \cdots \@@_Cdots
514     \cs_set_eq:NN \vdots \@@_Vdots
515     \cs_set_eq:NN \ddots \@@_Ddots
516     \cs_set_eq:NN \iddots \@@_Iddots
517     \cs_set_eq:NN \dots \@@_Ldots
518     \cs_set_eq:NN \hdotsfor \@@_Hdotsfor:
519 }

```

The sequence `\g_@@_multicolumn_cells_seq` will contain the list of the cells of the array where a command `\multicolumn{n}{...}{...}` with  $n > 1$  is issued. In `\g_@@_multicolumn_sizes_seq`, the “sizes” (that is to say the values of  $n$ ) correspondant will be stored. These lists will be used for the creation of the “medium nodes” (if they are created).

```

520 \seq_gclear_new:N \g_@@_multicolumn_cells_seq
521 \seq_gclear_new:N \g_@@_multicolumn_sizes_seq

```

The counter `\c@iRow` will be used to count the rows of the array (its incrementation will be in the first cell of the row).

```
522 \int_gset:Nn \c@iRow { \l_@@_first_row_int - 1 }
```

At the end of the environment `{array}`, `\c@iRow` will be the total number of rows.

`\g_@@_row_total_int` will be the number of rows excepted the last row (if `\l_@@_last_row_bool` has been raised with the option `last-row`).

```
523 \int_gzero_new:N \g_@@_row_total_int
```

The counter `\c@jCol` will be used to count the columns of the array. Since we want to know the total number of columns of the matrix, we also create a counter `\g_@@_col_total_int`. These counters are updated in the command `\@@_Cell`: executed at the beginning of each cell.

```

524 \int_gzero_new:N \g_@@_col_total_int
525 \cs_set_eq:NN \c@ifnextchar \new@ifnextchar

```

We nullify the definitions of the column types `w` and `W` before their redefinition because we want to avoid a warning in the log file for a redefinition of a column type. We must put `\relax` and not `\prg_do_nothing:`.

```

526 \cs_set_eq:NN \NC@find@w \relax
527 \cs_set_eq:NN \NC@find@W \relax
528 \@@_renewcolumntype:nn w { }
529 \@@_renewcolumntype:nn W { \cs_set_eq:NN \hss \hfil }

```

By default, the letter used to specify a dotted line in the preamble of an environment of `nicematrix` (for example in `\{pNiceArray\}`) is the letter `:`. However, this letter is used by some extensions, for example `arydshln`. That’s why it’s possible to change the letter used by `nicematrix` with the option `letter-for-dotted-lines` which changes the value of `\l_@@_letter_for_dotted_lines_str`. We rescan this string (which is always of length 1) in particular for the case where `pdflatex` is used with `french-babel` (the colon is activated by `french-babel` at the beginning of the document).

```

530 \tl_set_rescan:Nno
531     \l_@@_letter_for_dotted_lines_str { } \l_@@_letter_for_dotted_lines_str
532 \exp_args:NV \newcolumntype \l_@@_letter_for_dotted_lines_str
533 {
534     !
535     {
536         \skip_horizontal:n { 0.53 pt }

```

If the array is an array with all the columns of the same width, we don’t ask for the creation of the extra nodes because we will use the “`col`” nodes for the vertical dotted line.

```

537 \bool_if:nF
538 {
539     \l_@@_auto_columns_width_bool

```

```

540     || \dim_compare_p:nNn \l_@@_columns_width_dim > \c_zero_dim
541   }
542   { \bool_gset_true:N \g_@@_large_nodes_bool }

```

Consider the following code:

```

\begin{NiceArray}{C:CC:C}
a & b
c & d \\
e & f & g & h \\
i & j & k & l
\end{NiceArray}

```

The first “:” in the preamble will be encountered during the first row of the environment `{NiceArray}` but the second one will be encountered only in the third row. We have to issue a command `\vdottedline:n` in the `code-after` only one time for each “:” in the preamble. That’s why we keep a counter `\g_@@_last_vdotted_col_int` and with this counter, we know whether a letter “:” encountered during the parsing has already been taken into account in the `code-after`.

```

543   \int_compare:nNnT \c@jCol > \g_@@_last_vdotted_col_int
544   {
545     \int_gset_eq:NN \g_@@_last_vdotted_col_int \c@jCol
546     \tl_gput_right:Nx \g_@@_code_after_tl

```

The command `\@@_vdottedline:n` is protected, and, therefore, won’t be expanded before writing on `\g_@@_code_after_tl`.

```

547   { \@@_vdottedline:n { \int_use:N \c@jCol } }
548   }
549   }
550   }
551   \int_gzero_new:N \g_@@_last_vdotted_col_int
552   \bool_if:NT \c_@@_siunitx_loaded_bool \@@_renew_NC@rewrite@S:
553   \int_gset:Nn \g_@@_last_vdotted_col_int { -1 }
554   \bool_gset_false:N \g_@@_last_col_found_bool

```

During the construction of the array, the instructions `\Cdots`, `\Ldots`, etc. will be written in token lists `\g_@@_Cdots_lines_tl`, etc. which will be executed after the construction of the array.

```

555   \tl_gclear_new:N \g_@@_Cdots_lines_tl
556   \tl_gclear_new:N \g_@@_Ldots_lines_tl
557   \tl_gclear_new:N \g_@@_Vdots_lines_tl
558   \tl_gclear_new:N \g_@@_Ddots_lines_tl
559   \tl_gclear_new:N \g_@@_Iddots_lines_tl
560   \tl_gclear_new:N \g_@@_Hdotsfor_lines_tl
561 }

```

## 14.5 The environment `{NiceArrayWithDelims}`

```

562 \NewDocumentEnvironment { NiceArrayWithDelims } { m m O { } m ! O { } }
563 {
564   \str_if_empty:NT \g_@@_type_env_str
565   {
566     \str_gset:Nn \g_@@_type_env_str
567     { environment ~ { NiceArrayWithDelims } }
568   }
569   \@@_adapt_S_column:
570   \@@_test_if_math_mode:
571   \bool_if:NT \l_@@_in_env_bool { \@@_fatal:n { Yet-in-env } }
572   \bool_set_true:N \l_@@_in_env_bool

```

We deactivate Tikz externalization (since we use Tikz pictures with the options `overlay` and `remember picture`, there would be errors).

```

573   \cs_if_exist:NT \tikz@library@external@loaded
574   {

```

```

575     \tikzset { external / export = false }
576     \cs_if_exist:NT \ifstandalone
577         { \tikzset { external / optimize = false } }
578 }

```

We increment the counter `\g_@@_env_int` which counts the environments of the extension.

```

579     \int_gincr:N \g_@@_env_int
580     \bool_if:NF \l_@@_block_auto_columns_width_bool
581         { \dim_gzero_new:N \g_@@_max_cell_width_dim }

```

We do a redefinition of `\@arrayrule` because we want that the vertical rules drawn by `|` in the preamble of the array don't extend in the potential exterior rows.

```

582     \cs_set_protected:Npn \@arrayrule { \@addtopreamble \@@_vline: }

```

The set of keys is not exactly the same for `{NiceArray}` and for the variants of `{NiceArray}` (`{pNiceArray}`, `{bNiceArray}`, etc.) because, for `{NiceArray}`, we have the options `t`, `c` and `b`.

```

583     \bool_if:NTF \l_@@_NiceArray_bool
584         { \keys_set:nn { NiceMatrix / NiceArray } }
585         { \keys_set:nn { NiceMatrix / pNiceArray } }
586     { #3 , #5 }

```

A value of `-1` for the counter `\l_@@_last_row_int` means that the user has used the option `last-row` without value, that is to say without specifying the number of that last row. In this case, we try to read that value from the `aux` file (if it has been written on a previous run).

```

587     \int_compare:nNnT \l_@@_last_row_int = { -1 }
588     {
589         \bool_set_true:N \l_@@_last_row_without_value_bool

```

A value based on the name is more reliable than a value based on the number of the environment.

```

590     \str_if_empty:NTF \l_@@_name_str
591     {
592         \cs_if_exist:cT { @@_last_row_ \int_use:N \g_@@_env_int }
593         {
594             \int_set:Nn \l_@@_last_row_int
595                 { \use:c { @@_last_row_ \int_use:N \g_@@_env_int } }
596         }
597     }
598     {
599         \cs_if_exist:cT { @@_last_row_ \l_@@_name_str }
600         {
601             \int_set:Nn \l_@@_last_row_int
602                 { \use:c { @@_last_row_ \l_@@_name_str } }
603         }
604     }
605 }

```

The code in `\@@_pre_array:` is used only by `{NiceArrayWithDelims}`. It exists only for historical reasons. We should change that.

```

606     \@@_pre_array:

```

We compute the width of the two delimiters.

```

607     \dim_gzero_new:N \g_@@_left_delim_dim
608     \dim_gzero_new:N \g_@@_right_delim_dim
609     \bool_if:NTF \l_@@_NiceArray_bool
610     {
611         \dim_gset:Nn \g_@@_left_delim_dim { 2 \arraycolsep }
612         \dim_gset:Nn \g_@@_right_delim_dim { 2 \arraycolsep }
613     }
614     {
615         \group_begin:
616         \dim_set_eq:NN \nulldelimiterspace \c_zero_dim
617         \hbox_set:Nn \l_tmpa_box
618         {
619             \c_math_toggle_token
620             \left #1 \vcenter to 3 cm { } \right .
621             \c_math_toggle_token
622         }

```

```

623 \dim_gset:Nn \g_@@_left_delim_dim { \box_wd:N \l_tmpa_box }
624 \hbox_set:Nn \l_tmpa_box
625 {
626     \dim_set_eq:NN \nulldelimiterspace \c_zero_dim
627     \c_math_toggle_token
628     \left. \vcenter to 3 cm { } \right. #2
629     \c_math_toggle_token
630 }
631 \dim_gset:Nn \g_@@_right_delim_dim { \box_wd:N \l_tmpa_box }
632 \group_end:
633 }

```

The array will be composed in a box (named `\l_@@_the_array_box`) because we have to do manipulations concerning the potential exterior rows.

```
634 \box_clear_new:N \l_@@_the_array_box
```

We construct the preamble of the array in `\l_tmpa_tl`.

```

635 \tl_set:Nn \l_tmpa_tl { #4 }
636 \int_compare:nNnTF \l_@@_first_col_int = \c_zero_int
637 { \tl_put_left:NV \l_tmpa_tl \c_@@_preamble_first_col_tl }
638 {
639     \bool_if:NT \l_@@_NiceArray_bool
640     {
641         \bool_if:NF \l_@@_exterior_arraycolsep_bool
642         { \tl_put_left:Nn \l_tmpa_tl { @ { } } }
643     }
644 }
645 \int_compare:nNnTF \l_@@_last_col_int > { -1 }
646 { \tl_put_right:NV \l_tmpa_tl \c_@@_preamble_last_col_tl }
647 {
648     \bool_if:NT \l_@@_NiceArray_bool
649     {
650         \bool_if:NF \l_@@_exterior_arraycolsep_bool
651         { \tl_put_right:Nn \l_tmpa_tl { @ { } } }
652     }
653 }

```

Here is the beginning of the box which will contain the array. The `\hbox_set_end:` corresponding to this `\hbox_set:Nw` will be in the second part of the environment (and the closing `\c_math_toggle_token` also).

```

654 \hbox_set:Nw \l_@@_the_array_box
655 \skip_horizontal:n \l_@@_left_margin_dim
656 \skip_horizontal:n \l_@@_extra_left_margin_dim
657 \c_math_toggle_token
658 \bool_if:NTF \l_@@_light_syntax_bool
659 { \begin { @@-light-syntax } }
660 { \begin { @@-normal-syntax } }
661 }
662 {
663 \bool_if:NTF \l_@@_light_syntax_bool
664 { \end { @@-light-syntax } }
665 { \end { @@-normal-syntax } }
666 \c_math_toggle_token
667 \skip_horizontal:n \l_@@_right_margin_dim
668 \skip_horizontal:n \l_@@_extra_right_margin_dim
669 \hbox_set_end:

```

Now, the box containing the array is constructed (in `\l_@@_the_array_box`). However, we have some computations to do before inserting that box in the TeX flow (mainly because the exterior columns are in overlapping positions).

```

670 \int_compare:nNnT \l_@@_last_row_int > { -2 }
671 {
672     \bool_if:NF \l_@@_last_row_without_value_bool

```

```

673     {
674         \int_compare:nNnF \l_@@_last_row_int = \c@iRow
675         {
676             \@@_error:n { Wrong~last~row }
677             \int_gset_eq:NN \l_@@_last_row_int \c@iRow
678         }
679     }
680 }
```

Now, we compute  $\l_{\text{tmpa\_dim}}$  which is the vertical dimension of the “first row” above the array (when the key `first-row` is used).

```

681     \int_compare:nNnTF \l_@@_first_row_int = \c_zero_int
682     {
683         \dim_set:Nn \l_tmpa_dim
684         { \g_@@_dp_row_zero_dim + \lineskip + \g_@@_ht_row_zero_dim }
685     }
686     { \dim_zero:N \l_tmpa_dim }
```

We compute  $\l_{\text{tmpb\_dim}}$  which is the vertical dimension of the “last row” below the array (when the key `last-row` is used). A value of  $-2$  for  $\l_@@_last_row_int$  means that there is no “last row”.<sup>28</sup>

```

687     \int_compare:nNnTF \l_@@_last_row_int > { -2 }
688     {
689         \dim_set:Nn \l_tmpb_dim
690         { \g_@@_ht_last_row_dim + \lineskip + \g_@@_dp_last_row_dim }
691     }
692     { \dim_zero:N \l_tmpb_dim }
```

Now, we begin the real construction in the output flow of TeX. First, we take into account a potential “first column” (we remind that this “first column” has been constructed in an overlapping position and that we have computed its width in  $\g_@@_width_first_col_dim$ : see p. 48).

```

693     \int_compare:nNnT \l_@@_first_col_int = \c_zero_int
694     {
695         \skip_horizontal:n \arraycolsep
696         \skip_horizontal:n \g_@@_width_first_col_dim
697     }
```

The construction of the real box is different in `{NiceArray}` and in its variants (`{pNiceArray}`, etc.) because, in `{NiceArray}`, we have to take into account the option of position (`t`, `c` or `b`). We begin with `{NiceArray}`.

```

698     \bool_if:NTF \l_@@_NiceArray_bool
699     {
700         \int_compare:nNnT \l_@@_first_row_int = \c_zero_int
701         {
702             \str_if_eq:VnTF \l_@@_pos_env_str { t }
703             {
704                 \box_move_up:nn
705                 { \l_tmpa_dim - \g_@@_ht_row_zero_dim + \g_@@_ht_row_one_dim }
706             }
707         }
708     }
709     {
710         \int_compare:nNnT \l_@@_last_row_int > 0
711         {
712             \str_if_eq:VnT \l_@@_pos_env_str { b }
713             {
714                 \box_move_down:nn
715                 {
716                     \l_tmpb_dim
717                     - \g_@@_dp_last_row_dim + \g_@@_dp_ante_last_row_dim
718                 }
719             }
720         }
721     }
```

---

<sup>28</sup>A value of  $-1$  for  $\l_@@_last_row_int$  means that there is a “last row” but the number of that row is unknown (the user have not set the value with the option `last row`).

```

720         }
721     { \box_use_drop:N \l_@@_the_array_box }
722 }

```

Now, in the case of an environment `{pNiceArray}`, `{bNiceArray}`, etc.

```

723 {
724     \hbox_set:Nn \l_tmpa_box
725     {
726         \c_math_toggle_token
727         \left #1
728         \vcenter
729         {

```

We take into account the “first row” (we have previously computed its size in `\l_tmpa_dim`).

```

730     \skip_vertical:n { - \l_tmpa_dim }
731     \hbox:n
732     {
733         \skip_horizontal:n { - \arraycolsep }
734         \box_use_drop:N \l_@@_the_array_box
735         \skip_horizontal:n { - \arraycolsep }
736     }

```

We take into account the “last row” (we have previously computed its size in `\l_tmpb_dim`).

```

737     \skip_vertical:n { - \l_tmpb_dim }
738     }
739     \right #2
740     \c_math_toggle_token
741     }
742     \box_set_ht:Nn \l_tmpa_box { \box_ht:N \l_tmpa_box + \l_tmpa_dim }
743     \box_set_dp:Nn \l_tmpa_box { \box_dp:N \l_tmpa_box + \l_tmpb_dim }
744     \box_use_drop:N \l_tmpa_box
745 }

```

We take into account a potential “last column” (this “last column” has been constructed in an overlapping position and we have computed its width in `\g_@@_width_last_col_dim`: see p. 49).

```

746 \bool_if:NT \g_@@_last_col_found_bool
747 {
748     \skip_horizontal:n \g_@@_width_last_col_dim
749     \skip_horizontal:n \arraycolsep
750 }
751 \@@_after_array:
752 }

```

This is the end of the environment `{NiceArrayWithDelims}`.

The construction of the array in the environment `{NiceArrayWithDelims}` is, in fact, done by the environment `{@@-light-syntax}` or by the environment `{@@-normal-syntax}` (whether the option `light-syntax` is used or not). When the key `light-syntax` is not used, the construction is a standard environment (and, thus, it’s possible to use verbatim in the array).

```
753 \NewDocumentEnvironment { @@-normal-syntax } { }
```

Here is the call to `\array` (we have a dedicated macro `\@@_array`: because of compatibility with the classes `revtex4-1` and `revtex4-2`).

```

754 { \exp_args:NV \@@_array: \l_tmpa_tl }
755 {

```

If all the columns must have the same width (if the user has used the option `columns-width` or the option `auto-column-width` of the environment `{NiceMatrixBlock}`), we will add a row in the array to fix the width of the columns and construct the “col” nodes `nm-a-col-j` (these nodes will be used by the horizontal open dotted lines and by the commands `\@@_vdottedline:n`). We have written a dedicated function for that job.

```

756 \@@_create_row_of_col_nodes:
757 \endarray
758 }

```

When the key `light-syntax` is used, we use an environment which takes its whole body as an argument (with the specifier `b` of `xparse`).

```

759 \NewDocumentEnvironment { @@-light-syntax } { b }
760 {

```

Here is the call to `\array` (we have a dedicated macro `\@@_array`: because of compatibility with the classes `revtex4-1` and `revtex4-2`).

```

761   \exp_args:NV \@@_array: \l_tmpa_tl

```

The body of the environment, which is stored in the argument #1, is now splitted into items (and *not* tokens)

```

762   \seq_gclear_new:N \g_@@_rows_seq
763   \tl_set_rescan:Nno \l_@@_end_of_row_tl { } \l_@@_end_of_row_tl
764   \exp_args:NNV \seq_gset_split:Nnn \g_@@_rows_seq \l_@@_end_of_row_tl { #1 }

```

We need a global affectation because, when executing `\l_tmpa_tl`, we will exit the first cell of the array.

```

765   \seq_gpop_left:NN \g_@@_rows_seq \l_tmpa_tl
766   \exp_args:NV \@@_line_with_light_syntax_i:n \l_tmpa_tl
767   \seq_map_function:NN \g_@@_rows_seq \@@_line_with_light_syntax:n
768   \@@_create_row_of_col_nodes:
769   \endarray
770 }

```

Now, the second part of the environment. It is empty. That's not surprising because we have caught the whole body of the environment with the specifier `b` provided by `xparse`.

```

771 {
772 \cs_new_protected:Npn \@@_line_with_light_syntax_i:n #1
773 {
774   \seq_gclear_new:N \g_@@_cells_seq
775   \seq_gset_split:Nnn \g_@@_cells_seq { ~ } { #1 }
776   \seq_gpop_left:NN \g_@@_cells_seq \l_tmpa_tl
777   \l_tmpa_tl
778   \seq_map_function:NN \g_@@_cells_seq \@@_cell_with_light_syntax:n
779 }
780 \cs_new_protected:Npn \@@_line_with_light_syntax:n #1
781 {
782   \tl_if_empty:nF { #1 }
783   { \ \ \ \@@_line_with_light_syntax_i:n { #1 } }
784 }
785 \cs_new_protected:Npn \@@_cell_with_light_syntax:n #1 { & #1 }

```

The command `\@@_create_row_of_col_nodes:` will construct the potential last row. That last row (when it is created) is a false row used to fix the width of the columns (when the array is constructed with an option whwhich specify the width of the columns) and create the `col`-nodes (that nodes will be used by `\vdottedline` for instance).

```

786 \cs_new:Npn \@@_create_row_of_col_nodes:
787 {
788   \bool_if:nT
789   {
790     \l_@@_auto_columns_width_bool
791     || \dim_compare_p:nNn \l_@@_columns_width_dim > \c_zero_dim
792   }
793   {
794     \crrc
795     \int_compare:nNnT \l_@@_first_col_int = 0 { \omit & }
796     \omit

```

First, we put a “`col`” node on the left of the first column (of course, we have to do that *after* the `\omit`).

```

797     \skip_horizontal:N \arraycolsep
798     \tikz [ remember picture , overlay ]
799       \coordinate [ name = nm - \int_use:N \g_@@_env_int - col - 0 ] ;
800     \skip_horizontal:n { - \arraycolsep }

```

We compute in `\g_tmpa_dim` the common width of the columns. We use a global variable because we are in a cell of an `\halign` and because we have to use this variable in other cells (of the same

row). The affectation of `\g_tmpa_dim`, like all the affectations, must be done after the `\omit` of the cell.

```

801     \bool_if:nTF
802     {
803         \l_@@_auto_columns_width_bool
804         && ! \l_@@_block_auto_columns_width_bool
805     }
806     {
807         \dim_gset:Nn \g_tmpa_dim
808             { \g_@@_max_cell_width_dim + 2 \arraycolsep }
809     }
810     {
811         \dim_gset:Nn \g_tmpa_dim
812             { \l_@@_columns_width_dim + 2 \arraycolsep }
813     }
814     \skip_horizontal:N \g_tmpa_dim
815     \tikz [ remember~picture , overlay ]
816         \coordinate [ name = nm - \int_use:N \g_@@_env_int - col - 1 ] ;

```

We begin a loop over the columns. The integer `\g_tmpa_int` will be the number of the current column. This integer is not used to fix the width of the column (since all the columns have the same width equal to `\g_@@_tmpa_dim`) but for the Tikz nodes.

```

817     \int_gset:Nn \g_tmpa_int 1
818     \bool_if:nTF \g_@@_last_col_found_bool
819         { \prg_replicate:nn { \g_@@_col_total_int - 3 } }
820         { \prg_replicate:nn { \g_@@_col_total_int - 2 } }
821         {
822             &
823             \omit

```

The incrementation of the counter `\g_tmpa_int` must be done after the `\omit` of the cell.

```

824         \int_gincr:N \g_tmpa_int
825         \skip_horizontal:N \g_tmpa_dim

```

We create a “col” node on the right of the current column.

```

826             \@@_create_col_node:
827         }

```

For the last column, we want a special treatment because of the final `\arraycolsep`.

```

828         &
829         \omit
830         \int_gincr:N \g_tmpa_int
831         \skip_horizontal:N \g_tmpa_dim
832         \skip_horizontal:n { - \arraycolsep }
833         \@@_create_col_node:
834         \skip_horizontal:N \arraycolsep
835     }
836 }

837 \cs_new_protected:Npn \@@_create_col_node:
838 {
839     \tikz [ remember~picture , overlay ]
840         \coordinate
841         [
842             name = nm - \int_use:N \g_@@_env_int -
843                 col - \int_use:N \g_tmpa_int
844         ] ;
845 }

```

Here is the preamble for the “first column” (if the user uses the key `first-col`)

```

846 \tl_const:Nn \c_@@_preamble_first_col_tl
847 {
848     >
849     {

```

```
850     \@@_begin_of_row:
```

The contents of the cell is constructed in the box `\l_tmpa_box` because we have to compute some dimensions of this box.

```
851     \hbox_set:Nw \l_tmpa_box
852     \c_math_toggle_token
853     \bool_if:NT \l_@@_small_bool \scriptstyle
```

We insert `\l_@@_code_for_first_col_tl...` but we don't insert it in the potential "first row" and in the potential "last row".

```
854     \bool_if:nT
855     {
856         \int_compare_p:nNn \c@iRow > \c_zero_int
857         &&
858         (
859             \int_compare_p:nNn \l_@@_last_row_int < 0
860             ||
861             \int_compare_p:nNn \c@iRow < \l_@@_last_row_int
862         )
863     }
864     { \l_@@_code_for_first_col_tl }
865 }
866 l
867 <
868 {
869     \c_math_toggle_token
870     \hbox_set_end:
871     \@@_actualization_for_first_and_last_row:
```

We actualise the width of the "first column" because we will use this width after the construction of the array.

```
872     \dim_gset:Nn \g_@@_width_first_col_dim
873     {
874         \dim_max:nn
875             \g_@@_width_first_col_dim
876             { \box_wd:N \l_tmpa_box }
877     }
```

The content of the cell is inserted in an overlapping position.

```
878     \hbox_overlap_left:n
879     {
880         \tikz
881         [
882             remember~picture ,
883             inner~sep = \c_zero_dim ,
884             minimum~width = \c_zero_dim ,
885             baseline
886         ]
887         \node
888         [
889             anchor = base ,
890             name =
891                 nm -
892                 \int_use:N \g_@@_env_int -
893                 \int_use:N \c@iRow -
894                 0 ,
895             alias =
896                 \str_if_empty:NF \l_@@_name_str
897                 {
898                     \l_@@_name_str -
899                     \int_use:N \c@iRow -
900                     0
901                 }
902         ]
903         { \box_use:N \l_tmpa_box } ;
904         \skip_horizontal:n
```

```

905         {
906             \g_@@_left_delim_dim +
907             \l_@@_left_margin_dim +
908             \l_@@_extra_left_margin_dim
909         }
910     }
911     \skip_horizontal:n { - 2 \arraycolsep }
912 }
913 }
```

Here is the preamble for the “last column” (if the user uses the key `last-col`).

```

914 \tl_const:Nn \c_@@_preamble_last_col_tl
915 {
916     >
917 }
```

With the flag `\g_@@_last_col_found_bool`, we will know that the “last column” is really used.

```

918     \bool_gset_true:N \g_@@_last_col_found_bool
919     \int_gincr:N \c@jCol
920     \int_gset:Nn \g_@@_col_total_int
921     { \int_max:nn \g_@@_col_total_int \c@jCol }
```

The contents of the cell is constructed in the box `\l_tmpa_box` because we have to compute some dimensions of this box.

```

922     \hbox_set:Nw \l_tmpa_box
923     \c_math_toggle_token
924     \bool_if:NT \l_@@_small_bool \scriptstyle
```

We insert `\l_@@_code_for_last_col_tl...` but we don’t insert it in the potential “first row” and in the potential “last row”.

```

925     \bool_if:nT
926     {
927         \int_compare_p:nNn \c@iRow > \c_zero_int
928         &&
929         (
930             \int_compare_p:nNn \l_@@_last_row_int < 0
931             ||
932             \int_compare_p:nNn \c@iRow < \l_@@_last_row_int
933         )
934     }
935     { \l_@@_code_for_last_col_tl }
936 }
937 l
938 <
939 {
940     \c_math_toggle_token
941     \hbox_set_end:
942     \c_@@_actualization_for_first_and_last_row:
```

We actualise the width of the “last column” because we will use this width after the construction of the array.

```

943     \dim_gset:Nn \g_@@_width_last_col_dim
944     {
945         \dim_max:nn
946         \g_@@_width_last_col_dim
947         { \box_wd:N \l_tmpa_box }
948     }
949 \skip_horizontal:n { - 2 \arraycolsep }
```

The content of the cell is inserted in an overlapping position.

```

950     \hbox_overlap_right:n
951     {
952         \skip_horizontal:n
953         {
954             \g_@@_right_delim_dim +
955             \l_@@_right_margin_dim +
956             \l_@@_extra_right_margin_dim
```

```

957     }
958     \tikz
959     [
960         remember~picture ,
961         inner~sep = \c_zero_dim ,
962         minimum~width = \c_zero_dim ,
963         baseline
964     ]
965     \node
966     [
967         anchor = base ,
968         name =
969         nm -
970         \int_use:N \g_@@_env_int -
971         \int_use:N \c@iRow -
972         \int_use:N \c@jCol ,
973         alias =
974         \str_if_empty:NF \l_@@_name_str
975         {
976             \l_@@_name_str -
977             \int_use:N \c@iRow -
978             \int_use:N \c@jCol
979         }
980     ]
981     { \box_use:N \l_tmpa_box } ;
982 }
983 }
984 }
```

The environment `{NiceArray}` is constructed upon the environment `{NiceArrayWithDelims}` but, in fact, there is a flag `\l_@@_NiceArray_bool`. In `{NiceArrayWithDelims}`, some special code will be executed if this flag is raised.

```

985 \NewDocumentEnvironment { NiceArray } { }
986 {
987     \bool_set_true:N \l_@@_NiceArray_bool
988     \str_if_empty:NT \g_@@_type_env_str
989     { \str_gset:Nn \g_@@_type_env_str { environment ~ { NiceArray } } }
```

We put `.` and `.` for the delimiters but, in fact, that doesn't matter because these arguments won't be used in `{NiceArrayWithDelims}` (because the flag `\l_@@_NiceArray_bool` is raised).

```

990     \NiceArrayWithDelims . .
991 }
992 { \endNiceArrayWithDelims }
```

We create the variants of the environment `{NiceArrayWithDelims}`. These variants exist since the version 3.0 of nicematrix.

```

993 \NewDocumentEnvironment { pNiceArray } { }
994 {
995     \str_if_empty:NT \g_@@_type_env_str
996     { \str_gset:Nn \g_@@_type_env_str { environment ~ { pNiceArray } } }
997     \@@_test_if_math_mode:
998     \NiceArrayWithDelims ( )
999 }
1000 { \endNiceArrayWithDelims }

1001 \NewDocumentEnvironment { bNiceArray } { }
1002 {
1003     \str_if_empty:NT \g_@@_type_env_str
1004     { \str_gset:Nn \g_@@_type_env_str { environment ~ { bNiceArray } } }
1005     \@@_test_if_math_mode:
1006     \NiceArrayWithDelims [ ]
1007 }
```

```

1008 { \endNiceArrayWithDelims }
1009 \NewDocumentEnvironment { BNiceArray } { }
1010 {
1011   \str_if_empty:NT \g_@@_type_env_str
1012     { \str_gset:Nn \g_@@_type_env_str { environment ~ { BNiceArray } } }
1013   \@@_test_if_math_mode:
1014   \NiceArrayWithDelims \{ \}
1015 }
1016 { \endNiceArrayWithDelims }
1017 \NewDocumentEnvironment { vNiceArray } { }
1018 {
1019   \str_if_empty:NT \g_@@_type_env_str
1020     { \str_gset:Nn \g_@@_type_env_str { environment ~ { vNiceArray } } }
1021   \@@_test_if_math_mode:
1022   \NiceArrayWithDelims | |
1023 }
1024 { \endNiceArrayWithDelims }
1025 \NewDocumentEnvironment { VNiceArray } { }
1026 {
1027   \str_if_empty:NT \g_@@_type_env_str
1028     { \str_gset:Nn \g_@@_type_env_str { environment ~ { VNiceArray } } }
1029   \@@_test_if_math_mode:
1030   \NiceArrayWithDelims \| \\
1031 }
1032 { \endNiceArrayWithDelims }

```

## 14.6 The environment {NiceMatrix} and its variants

```

1033 \cs_new_protected:Npn \@@_define_env:n #1
1034 {
1035   \NewDocumentEnvironment { #1 NiceMatrix } { ! O { } }
1036   {
1037     \str_gset:Nn \g_@@_type_env_str { environment ~ { #1 NiceMatrix } }
1038     \keys_set:nn { NiceMatrix / NiceMatrix } { ##1 }
1039     \begin { #1 NiceArray }
1040       {
1041         *
1042         {
1043           \int_compare:nNnTF \l_@@_last_col_int = { -1 }
1044             \c@MaxMatrixCols
1045             { \int_eval:n { \l_@@_last_col_int - 1 } }
1046         }
1047         C
1048       }
1049     }
1050   { \end { #1 NiceArray } }
1051 }
1052 \@@_define_env:n { }
1053 \@@_define_env:n p
1054 \@@_define_env:n b
1055 \@@_define_env:n B
1056 \@@_define_env:n v
1057 \@@_define_env:n V

```

## 14.7 How to know whether a cell is “empty”

The conditionnal `\@@_if_not_empty_cell:nnT` tests whether a cell is empty. The first two arguments must be LaTeX3 counters for the row and the column of the considered cell.

```

1058 \prg_set_conditional:Npnn \@@_if_not_empty_cell:nn #1 #2 { T , TF }
1059 {

```

First, we want to test whether the cell is in the virtual sequence of “non-empty” cells. There are several important remarks:

- we don’t use a `expl3` sequence for efficiency;
- the “non-empty” cells in this sequence are not, in fact, all the non-empty cells of the array: on the contrary they are only cells declared as non-empty for a special reason (as of now, there are only cells which are on a dotted line which is already drawn or which will be drawn “just after”);
- the flag `\l_tmpa_bool` will be raised when the cell is actually on this virtual sequence.

```

1060 \bool_set_false:N \l_tmpa_bool
1061 \cs_if_exist:cTF
1062 { @@ _ dotted _ \int_use:N #1 - \int_use:N #2 }
1063 \prg_return_true:
1064 {
```

We know that the cell is not in the virtual sequence of the “non-empty” cells. Now, we test whether the cell is a “virtual cell”, that is to say a cell after the `\\"` of the line of the array. It’s easy to known whether a cell is virtual: the cell is virtual if, and only if, the corresponding Tikz node doesn’t exist.

```

1065 \cs_if_free:cTF
1066 {
1067   pgf@sh@ns@nm -
1068   \int_use:N \g_@@_env_int -
1069   \int_use:N #1 -
1070   \int_use:N #2
1071 }
1072 { \prg_return_false: }
1073 {
```

Now, we want to test whether the cell is in the virtual sequence of “empty” cells. There are several important remarks:

- we don’t use a `expl3` sequence for efficiency ;
- the “empty” cells in this sequence are not, in fact, all the non-empty cells of the array: on the contrary they are only cells declared as non-empty for a special reason ;
- the flag `\l_tmpa_bool` will be raised when the cell is actually on this virtual sequence.

```

1074 \bool_set_false:N \l_tmpa_bool
1075 \cs_if_exist:cT
1076 { @@ _ empty _ \int_use:N #1 - \int_use:N #2 }
1077 {
1078   \int_compare:nNnt
1079   { \use:c { @@ _ empty _ \int_use:N #1 - \int_use:N #2 } }
1080   =
1081   \g_@@_env_int
1082   { \bool_set_true:N \l_tmpa_bool }
1083 }
1084 \bool_if:NTF \l_tmpa_bool
1085 \prg_return_false:
```

In the general case, we consider the width of the Tikz node corresponding to the cell. In order to compute this width, we have to extract the coordinate of the west and east anchors of the node. This extraction needs a command environment `{pgfpicture}` but, in fact, nothing is drawn.

```

1086 {
1087   \begin{pgfpicture}
```

We store the name of the node corresponding to the cell in `\l_tmpa_tl`.

```

1088 \tl_set:Nx \l_tmpa_tl
1089 {
1090   nm -
1091   \int_use:N \g_@@_env_int -
1092   \int_use:N #1 -
```

```

1093           \int_use:N #2
1094       }
1095   \pgfpointanchor {\l_tmpa_tl} { east }
1096   \dim_gset:Nn \g_tmpa_dim \pgf@x
1097   \pgfpointanchor {\l_tmpa_tl} { west }
1098   \dim_gset:Nn \g_tmpb_dim \pgf@x
1099   \end { pgfpicture }
1100   \dim_compare:nNnTF
1101     { \dim_abs:n { \g_tmpb_dim - \g_tmpa_dim } } < { 0.5 pt }
1102     \prg_return_false:
1103     \prg_return_true:
1104   }
1105 }
1106 }
1107 }

```

## 14.8 After the construction of the array

```

1108 \cs_new_protected:Nn \@@_after_array:
1109 {
1110   \int_compare:nNnTF \c@iRow > \c_zero_int
1111     \@@_after_array_i:
1112   {
1113     \@@_error:n { Zero~row }
1114     \@@_restore_iRow_jCol:
1115   }
1116 }

```

We deactivate Tikz externalization (since we use Tikz pictures with the options `overlay` and `remember picture`, there would be errors).

```

1117 \cs_new_protected:Nn \@@_after_array_i:
1118 {
1119   \group_begin:
1120   \cs_if_exist:NT \tikz@library@external@loaded
1121     { \tikzset { external / export = false } }

```

Now, the definition of `\c@jCol` and `\g_@@_col_total_int` change: `\c@jCol` will be the number of columns without the “last column”; `\g_@@_col_total_int` will be the number of columns with this “last column”.<sup>29</sup>

```

1122 \int_gset_eq:NN \c@jCol \g_@@_col_total_int
1123 \bool_if:nT \g_@@_last_col_found_bool { \int_gdecr:N \c@jCol }

```

We fix also the value of `\c@iRow` and `\g_@@_row_total_int` with the same principle.

```

1124 \int_gset_eq:NN \g_@@_row_total_int \c@iRow
1125 \int_compare:nNnT \l_@@_last_row_int > { -1 }
1126   { \int_gsub:Nn \c@iRow \c_one_int }

```

In the user has used the option `last-row` without value, we write in the aux file the number of that last row for the next run.

```

1127 \bool_if:NT \l_@@_last_row_without_value_bool
1128 {
1129   \iow_now:Nn \mainaux \ExplSyntaxOn
1130   \iow_now:Nx \mainaux
1131   {
1132     \cs_gset:cpn { @@_last_row_ } \int_use:N \g_@@_env_int }
1133     { \int_use:N \g_@@_row_total_int }
1134 }

```

If the environment has a name, we also write a value based on the name because it’s more reliable than a value based on the number of the environment.

```

1135 \str_if_empty:NF \l_@@_name_str
1136 {
1137   \iow_now:Nx \mainaux

```

---

<sup>29</sup>We remind that the potential “first column” has the number 0.

```

1138     {
1139         \cs_gset:cpn { @@_last_row_ \l_@@_name_str }
1140         { \int_use:N \g_@@_row_total_int }
1141     }
1142 }
1143 \iow_now:Nn \mainaux \ExplSyntaxOff
1144 }
```

By default, the diagonal lines will be parallelized<sup>30</sup>. There are two types of diagonals lines: the \Ddots diagonals and the \Iddots diagonals. We have to count both types in order to know whether a diagonal is the first of its type in the current {NiceArray} environment.

```

1145 \bool_if:NT \l_@@_parallelize_diags_bool
1146 {
1147     \int_zero_new:N \l_@@_ddots_int
1148     \int_zero_new:N \l_@@_iddots_int
```

The dimensions \l\_@@\_delta\_x\_one\_dim and \l\_@@\_delta\_y\_one\_dim will contain the  $\Delta_x$  and  $\Delta_y$  of the first \Ddots diagonal. We have to store these values in order to draw the others \Ddots diagonals parallel to the first one. Similarly \l\_@@\_delta\_x\_two\_dim and \l\_@@\_delta\_y\_two\_dim are the  $\Delta_x$  and  $\Delta_y$  of the first \Iddots diagonal.

```

1149     \dim_zero_new:N \l_@@_delta_x_one_dim
1150     \dim_zero_new:N \l_@@_delta_y_one_dim
1151     \dim_zero_new:N \l_@@_delta_x_two_dim
1152     \dim_zero_new:N \l_@@_delta_y_two_dim
1153 }
```

The booleans \g\_@@\_medium\_nodes\_bool and \g\_@@\_large\_nodes\_bool may be raised directly in cells of the array (for example in commands \Block) but also because the user has used the options `create-medium-nodes` and `create-large-nodes` (these options raise the booleans \l\_@@\_medium\_nodes\_bool and \l\_@@\_large\_nodes\_bool but theses booleans are converted into the global version \g\_@@\_medium\_nodes\_bool and \g\_@@\_large\_nodes\_bool before the creation of the array).

```

1154 \bool_if:nTF \g_@@_medium_nodes_bool
1155 {
1156     \bool_if:NTF \g_@@_large_nodes_bool
1157         \@@_create_medium_and_large_nodes:
1158         \@@_create_medium_nodes:
1159     }
1160     { \bool_if:NT \g_@@_large_nodes_bool \@@_create_large_nodes: }
1161 \int_zero_new:N \l_@@_initial_i_int
1162 \int_zero_new:N \l_@@_initial_j_int
1163 \int_zero_new:N \l_@@_final_i_int
1164 \int_zero_new:N \l_@@_final_j_int
1165 \bool_set_false:N \l_@@_initial_open_bool
1166 \bool_set_false:N \l_@@_final_open_bool
```

If the option `small` is used, the values \l\_@@\_radius\_dim and \l\_@@\_inter\_dots\_dim (used to draw the dotted lines) are changed.

```

1167 \bool_if:NT \l_@@_small_bool
1168 {
1169     \dim_set:Nn \l_@@_radius_dim { 0.37 pt }
1170     \dim_set:Nn \l_@@_inter_dots_dim { 0.25 em }
1171 }
```

Now, we really draw the lines. The code to draw the lines has been constructed in the token lists \g\_@@\_Vdots\_lines\_tl, etc.

```

1172 \g_@@_Hdotsfor_lines_tl
1173 \g_@@_Vdots_lines_tl
1174 \g_@@_Ddots_lines_tl
1175 \g_@@_Iddots_lines_tl
1176 \g_@@_Cdots_lines_tl
1177 \g_@@_Ldots_lines_tl
```

---

<sup>30</sup>It's possible to use the option `parallelize-diags` to disable this parallelization.

Now, the `code-after`.

```

1178 \tikzset
1179 {
1180     every~picture / .style =
1181     {
1182         overlay ,
1183         remember~picture ,
1184         name~prefix = nm - \int_use:N \g_@@_env_int -
1185     }
1186 }
1187 \cs_set_eq:NN \line \@@_line:nn
1188 \g_@@_code_after_tl
1189 \tl_gclear:N \g_@@_code_after_tl
1190 \group_end:
1191 \str_gclear:N \g_@@_type_env_str
1192 \@@_restore_iRow_jCol:
1193 }
1194 \cs_new_protected:Nn \@@_restore_iRow_jCol:
1195 {
1196     \cs_if_exist:NT \theiRow { \int_gset_eq:NN \c@iRow \l_@@_save_iRow_int }
1197     \cs_if_exist:NT \thejCol { \int_gset_eq:NN \c@jCol \l_@@_save_jCol_int }
1198 }
```

A dotted line will be said *open* in one of its extremities when it stops on the edge of the matrix and *closed* otherwise. In the following matrix, the dotted line is closed on its left extremity and open on its right.

$$\begin{pmatrix} a+b+c & a+b & a \\ a & \dots & \dots \\ a & a+b & a+b+c \end{pmatrix}$$

For a closed extremity, we use the normal node and for a open one, we use the “medium node” or, if it exists, the `w-node`.

$$\begin{pmatrix} a+b+c & a+b & a \\ \textcolor{red}{a} & \dots & \dots \\ a & a+b & a+b+c \end{pmatrix}$$

The command `\@@_find_extremities_of_line:nnnn` takes four arguments:

- the first argument is the row of the cell where the command was issued;
- the second argument is the column of the cell where the command was issued;
- the third argument is the  $x$ -value of the orientation vector of the line;
- the fourth argument is the  $y$ -value of the orientation vector of the line;

This command computes:

- `\l_@@_initial_i_int` and `\l_@@_initial_j_int` which are the coordinates of one extremity of the line;
- `\l_@@_final_i_int` and `\l_@@_final_j_int` which are the coordinates of the other extremity of the line;
- `\l_@@_initial_open_bool` and `\l_@@_final_open_bool` to indicate whether the extremities are open or not.

```

1199 \cs_new_protected:Nn \@@_find_extremities_of_line:nnnn
1200 {
```

First, we declare the current cell as “dotted” because we forbide intersections of dotted lines.

```
1201 \cs_set:cpn { @@ _ dotted _ #1 - #2 } { }
```

Initialization of variables.

```

1202 \int_set:Nn \l_@@_initial_i_int { #1 }
1203 \int_set:Nn \l_@@_initial_j_int { #2 }
1204 \int_set:Nn \l_@@_final_i_int { #1 }
1205 \int_set:Nn \l_@@_final_j_int { #2 }
```

We will do two loops: one when determinating the initial cell and the other when determinating the final cell. The boolean `\l_@@_stop_loop_bool` will be used to control these loops.

```

1206 \bool_set_false:N \l_@@_stop_loop_bool
1207 \bool_do_until:Nn \l_@@_stop_loop_bool
1208 {
1209     \int_add:Nn \l_@@_final_i_int { #3 }
1210     \int_add:Nn \l_@@_final_j_int { #4 }
```

We test if we are still in the matrix.

```

1211 \bool_set_false:N \l_@@_final_open_bool
1212 \int_compare:nNnTF \l_@@_final_i_int > \c@iRow
1213 {
1214     \int_compare:nNnT { #3 } = 1
1215     { \bool_set_true:N \l_@@_final_open_bool }
1216 }
1217 {
1218     \int_compare:nNnTF \l_@@_final_j_int < 1
1219     {
1220         \int_compare:nNnT { #4 } = { -1 }
1221         { \bool_set_true:N \l_@@_final_open_bool }
1222     }
1223 {
1224     \int_compare:nNnT \l_@@_final_j_int > \c@jCol
1225     {
1226         \int_compare:nNnT { #4 } = 1
1227         { \bool_set_true:N \l_@@_final_open_bool }
1228     }
1229 }
1230 }
1231 \bool_if:NTF \l_@@_final_open_bool
```

If we are outside the matrix, we have found the extremity of the dotted line and it's a *open* extremity.

```
1232 {
```

We do a step backwards because we will draw the dotted line upon the last cell in the matrix (we will use the “medium node” of this cell).

```

1233 \int_sub:Nn \l_@@_final_i_int { #3 }
1234 \int_sub:Nn \l_@@_final_j_int { #4 }
1235 \bool_set_true:N \l_@@_stop_loop_bool
1236 }
```

If we are in the matrix, we test whether the cell is empty. If it's not the case, we stop the loop because we have found the correct values for `\l_@@_final_i_int` and `\l_@@_final_j_int`.

```

1237 {
1238     \@@_if_not_empty_cell:nnTF \l_@@_final_i_int \l_@@_final_j_int
1239     { \bool_set_true:N \l_@@_stop_loop_bool }
```

If the case is empty, we declare that the cell as non-empty. Indeed, we will draw a dotted line and the cell will be on that dotted line. All the cells of a dotted line have to be mark as “dotted” because we don't want intersections between dotted lines.

```

1240 {
1241     \cs_set:cpn
1242     {
1243         @@ _ dotted _
1244         \int_use:N \l_@@_final_i_int -
1245         \int_use:N \l_@@_final_j_int
1246     }
1247     { }
1248 }
```

```

1249         }
1250     }
We test whether the initial extremity of the dotted line is an implicit cell already dotted (by another
dotted line). In this case, we can't draw the line because we have no Tikz node at the extremity
of the arrow (and we can't use the "medium node" or the "large node" because we should use the
normal node since the extremity is not open).
1251 \cs_if_free:cT
1252 {
1253     pgf@sh@ns@nm -
1254     \int_use:N \g_@@_env_int -
1255     \int_use:N \l_@@_final_i_int -
1256     \int_use:N \l_@@_final_j_int
1257 }
1258 {
1259     \bool_if:NF \l_@@_final_open_bool
1260     {
1261         \msg_error:n { nicematrix } { Impossible-line }
1262         { \int_use:N \l_@@_final_i_int }
1263         \bool_set_true:N \l_@@_impossible_line_bool
1264     }
1265 }

```

For `\l_@@_initial_i_int` and `\l_@@_initial_j_int` the programming is similar to the previous one.

```

1266 \bool_set_false:N \l_@@_stop_loop_bool
1267 \bool_do_until:Nn \l_@@_stop_loop_bool
1268 {
1269     \int_sub:Nn \l_@@_initial_i_int { #3 }
1270     \int_sub:Nn \l_@@_initial_j_int { #4 }
1271     \bool_set_false:N \l_@@_initial_open_bool
1272     \int_compare:nNnTF \l_@@_initial_i_int < 1
1273     {
1274         \int_compare:nNnT { #3 } = 1
1275         { \bool_set_true:N \l_@@_initial_open_bool }
1276     }
1277     {
1278         \int_compare:nNnTF \l_@@_initial_j_int < 1
1279         {
1280             \int_compare:nNnT { #4 } = 1
1281             { \bool_set_true:N \l_@@_initial_open_bool }
1282         }
1283         {
1284             \int_compare:nNnT \l_@@_initial_j_int > \c@jCol
1285             {
1286                 \int_compare:nNnT { #4 } = { -1 }
1287                 { \bool_set_true:N \l_@@_initial_open_bool }
1288             }
1289         }
1290     }
1291     \bool_if:NTF \l_@@_initial_open_bool
1292     {
1293         \int_add:Nn \l_@@_initial_i_int { #3 }
1294         \int_add:Nn \l_@@_initial_j_int { #4 }
1295         \bool_set_true:N \l_@@_stop_loop_bool
1296     }
1297     {
1298         \@@_if_not_empty_cell:nnTF
1299             \l_@@_initial_i_int \l_@@_initial_j_int
1300             { \bool_set_true:N \l_@@_stop_loop_bool }
1301             {
1302                 \cs_set:cpn

```

```

1303
1304     {
1305         @@ _ dotted _
1306         \int_use:N \l_@@_initial_i_int -
1307         \int_use:N \l_@@_initial_j_int
1308     }
1309     {
1310 }
1311 }
```

We test whether the initial extremity of the dotted line is an implicit cell already dotted (by another dotted line). In this case, we can't draw the line because we have no Tikz node at the extremity of the arrow (and we can't use the “medium node” or the “large node” because we should use the normal node since the extremity is not open).

```

1312 \cs_if_free:cT
1313 {
1314     pgf@sh@ns@nm -
1315     \int_use:N \g_@@_env_int -
1316     \int_use:N \l_@@_initial_i_int -
1317     \int_use:N \l_@@_initial_j_int
1318 }
1319 {
1320     \bool_if:NF \l_@@_initial_open_bool
1321     {
1322         \msg_error:nnx { nicematrix } { Impossible-line }
1323         {
1324             \int_use:N \l_@@_initial_i_int
1325             \bool_set_true:N \l_@@_impossible_line_bool
1326         }
1327 }
```

If we have at least one open extremity, we create the “medium nodes” in the matrix<sup>31</sup>. We remind that, when used once, the command `\@@_create_medium_nodes:` becomes no-op in the current TeX group.

```

1327 \bool_if:nT \l_@@_initial_open_bool \@@_create_medium_nodes:
1328 \bool_if:NT \l_@@_final_open_bool \@@_create_medium_nodes:
1329 }
```

The command `\@@_retrieve_coords:nn` retrieves the Tikz coordinates of the two extremities of the dotted line we will have to draw<sup>32</sup>. This command has four implicit arguments which are `\l_@@_initial_i_int`, `\l_@@_initial_j_int`, `\l_@@_final_i_int` and `\l_@@_final_j_int`.

The two arguments of the command `\@@_retrieve_coords:nn` are the suffix and the anchor that must be used for the two nodes.

The coordinates are stored in `\g_@@_x_initial_dim`, `\g_@@_y_initial_dim`, `\g_@@_x_final_dim`, `\g_@@_y_final_dim`. These variables are global for technical reasons: we have to do an affectation in an environment `{tikzpicture}`.

```

1330 \cs_new_protected:Nn \@@_retrieve_coords:nn
1331 {
1332     \dim_gzero_new:N \g_@@_x_initial_dim
1333     \dim_gzero_new:N \g_@@_y_initial_dim
1334     \dim_gzero_new:N \g_@@_x_final_dim
1335     \dim_gzero_new:N \g_@@_y_final_dim
1336     \begin{tikzpicture} [remember picture]
1337         \tikz@parse@node \pgfutil@firstofone
1338         ( nm - \int_use:N \g_@@_env_int -
1339             \int_use:N \l_@@_initial_i_int -
1340             \int_use:N \l_@@_initial_j_int #1 )
1341         \dim_gset:Nn \g_@@_x_initial_dim \pgf@x
1342         \dim_gset:Nn \g_@@_y_initial_dim \pgf@y
```

---

<sup>31</sup>We should change this. Indeed, for an open extremity of an *horizontal* dotted line, we use the `w-node`, if, it exists, and not the “medium node”.

<sup>32</sup>In fact, with diagonal lines, or vertical lines in columns of type `L` or `R`, an adjustment of one of the coordinates may be done.

```

1343     \tikz@parse@node \pgfutil@firstofone
1344     ( nm - \int_use:N \g_@@_env_int -
1345       \int_use:N \l_@@_final_i_int -
1346       \int_use:N \l_@@_final_j_int #2 )
1347     \dim_gset:Nn \g_@@_x_final_dim \pgf@x
1348     \dim_gset:Nn \g_@@_y_final_dim \pgf@y
1349   \end { tikzpicture }
1350 }
1351 \cs_generate_variant:Nn \@@_retrieve_coords:nn { x x }

```

For the horizontal lines with open extremities, we must take into account the “col” nodes created in the environments which have a fixed width of the columns. The following command will recompute the  $x$ -value of the extremities in this case (erasing the value computed in  $\@@_retrieve_coords:nn$ ).

```

1352 \cs_new_protected:Nn \@@_adjust_with_col_nodes:
1353 {
1354   \bool_if:NT \l_@@_initial_open_bool
1355   {
1356     \cs_if_exist:cT
1357     { pgf@sh@ns@nm - \int_use:N \g_@@_env_int - col - 0 }
1358     {
1359       \begin { tikzpicture } [ remember~picture ]
1360       \tikz@parse@node \pgfutil@firstofone
1361       ( nm - \int_use:N \g_@@_env_int - col - 0 )
1362       \dim_gset:Nn \g_@@_x_initial_dim \pgf@x
1363       \end { tikzpicture }
1364     }
1365   }
1366   \bool_if:NT \l_@@_final_open_bool
1367   {
1368     \cs_if_exist:cT
1369     {
1370       pgf@sh@ns@nm - \int_use:N \g_@@_env_int - col -
1371       \int_use:N \c@jCol
1372     }
1373     {
1374       \begin { tikzpicture } [ remember~picture ]
1375       \tikz@parse@node \pgfutil@firstofone
1376       ( nm - \int_use:N \g_@@_env_int - col - \int_use:N \c@jCol )
1377       \dim_gset:Nn \g_@@_x_final_dim \pgf@x
1378       \end { tikzpicture }
1379     }
1380   }
1381 }

1382 \cs_new_protected:Nn \@@_draw_Ldots:nn
1383 {
1384   \cs_if_free:cT { @@ _ dotted _ #1 - #2 }
1385   {
1386     \bool_set_false:N \l_@@_impossible_line_bool
1387     \@@_find_extremities_of_line:nnnn { #1 } { #2 } \c_zero_int \c_one_int
1388     \bool_if:NF \l_@@_impossible_line_bool \@@_actually_draw_Ldots:
1389   }
1390 }

```

The command  $\@@_actually_draw_Ldots:$  draws the Ldots line using  $\l_@@_initial_i_int$ ,  $\l_@@_initial_j_int$ ,  $\l_@@_initial_open_bool$ ,  $\l_@@_final_i_int$ ,  $\l_@@_final_j_int$  and  $\l_@@_final_open_bool$ . We have a dedicated command because it is used also by  $\Hdotsfor$ .

```

1391 \cs_new_protected:Nn \@@_actually_draw_Ldots:
1392 {
1393   \@@_retrieve_coords:xx

```

```

1394 {
1395     \bool_if:NTF \l_@@_initial_open_bool
1396     {
1397         \cs_if_exist:cTF
1398         {
1399             pgf@sh@ns@nm
1400             - \int_use:N \g_@@_env_int
1401             - \int_use:N \l_@@_initial_i_int
1402             - \int_use:N \l_@@_initial_j_int - w
1403         }
1404         { - w.base~west }
1405         { - medium.base~west }
1406     }
1407     { .base~east }
1408   }
1409   {
1410     \bool_if:NTF \l_@@_final_open_bool
1411     {
1412         \cs_if_exist:cTF
1413         {
1414             pgf@sh@ns@nm
1415             - \int_use:N \g_@@_env_int
1416             - \int_use:N \l_@@_final_i_int
1417             - \int_use:N \l_@@_final_j_int - w
1418         }
1419         { - w.base~east }
1420         { - medium.base~east }
1421     }
1422     { .base~west }
1423   }
1424   \@@_adjust_with_col_nodes:
1425   \bool_if:NT \l_@@_initial_open_bool
1426     { \dim_gset_eq:NN \g_@@_y_initial_dim \g_@@_y_final_dim }
1427   \bool_if:NT \l_@@_final_open_bool
1428     { \dim_gset_eq:NN \g_@@_y_final_dim \g_@@_y_initial_dim }

We raise the line of a quantity equal to the radius of the dots because we want the dots really “on”  

the line of texte.

1429   \dim_gadd:Nn \g_@@_y_initial_dim { 0.53 pt }
1430   \dim_gadd:Nn \g_@@_y_final_dim { 0.53 pt }
1431   \@@_draw_tikz_line:
1432 }

1433 \cs_new_protected:Nn \@@_draw_Cdots:nn
1434 {
1435   \cs_if_free:cT { @@ _ dotted _ #1 - #2 }
1436   {
1437     \bool_set_false:N \l_@@_impossible_line_bool
1438     \@@_find_extremities_of_line:nnnn { #1 } { #2 } \c_zero_int \c_one_int
1439     \bool_if:NF \l_@@_impossible_line_bool
1440     {
1441       \@@_retrieve_coords:xx
1442       {
1443         \bool_if:NTF \l_@@_initial_open_bool
1444         {
1445           \cs_if_exist:cTF
1446           {
1447             pgf@sh@ns@nm
1448             - \int_use:N \g_@@_env_int
1449             - \int_use:N \l_@@_initial_i_int
1450             - \int_use:N \l_@@_initial_j_int - w
1451           }
1452         }
1453       }
1454     }
1455   }

```

```

1452         { - w.mid~west }
1453         { - medium.mid~west }
1454     }
1455     { .mid~east }
1456 }
1457 {
1458 \bool_if:NTF \l_@@_final_open_bool
1459 {
1460     \cs_if_exist:cTF
1461     {
1462         pgf@sh@ns@nm
1463         - \int_use:N \g_@@_env_int
1464         - \int_use:N \l_@@_final_i_int
1465         - \int_use:N \l_@@_final_j_int - w
1466     }
1467     { - w.mid~east }
1468     { - medium.mid~east }
1469 }
1470 { .mid~west }
1471 }
1472 \@@_adjust_with_col_nodes:
1473 \bool_if:NT \l_@@_initial_open_bool
1474     { \dim_gset_eq:NN \g_@@_y_initial_dim \g_@@_y_final_dim }
1475 \bool_if:NT \l_@@_final_open_bool
1476     { \dim_gset_eq:NN \g_@@_y_final_dim \g_@@_y_initial_dim }
1477 \@@_draw_tikz_line:
1478 }
1479 }
1480 }
```

For the vertical dots, we have to distinguish different instances because we want really vertical lines. Be careful: it's not possible to insert the command `\@@_retrieve_coords:nn` in the arguments T and F of the `expl3` commands (why?).

```

1481 \cs_new_protected:Nn \@@_draw_Vdots:nn
1482 {
1483     \cs_if_free:cT { @@ _ dotted _ #1 - #2 }
1484     {
1485         \bool_set_false:N \l_@@_impossible_line_bool
1486         \@@_find_extremities_of_line:nmmn { #1 } { #2 } \c_one_int \c_zero_int
1487         \bool_if:NF \l_@@_impossible_line_bool
1488         {
1489             \@@_retrieve_coords:xx
1490             {
1491                 \bool_if:NTF \l_@@_initial_open_bool
1492                     { - medium.north~west }
1493                     { .south~west }
1494             }
1495             {
1496                 \bool_if:NTF \l_@@_final_open_bool
1497                     { - medium.south~west }
1498                     { .north~west }
1499             }
1500 }
```

The boolean `\l_tmpa_bool` indicates whether the column is of type l (L of `{NiceArray}`) or may be considered as if.

```

1500     \bool_set:Nn \l_tmpa_bool
1501     { \dim_compare_p:nNn \g_@@_x_initial_dim = \g_@@_x_final_dim }
1502     \@@_retrieve_coords:xx
1503     {
1504         \bool_if:NTF \l_@@_initial_open_bool
1505             { - medium.north }
1506             { .south }
1507     }
```

```

1508 {
1509     \bool_if:NTF \l_@@_final_open_bool
1510         { - medium.south }
1511         { .north }
1512     }

```

The boolean `\l_tmpb_bool` indicates whether the column is of type c (C of `{NiceArray}`) or may be considered as if.

```

1513     \bool_set:Nn \l_tmpb_bool
1514         { \dim_compare_p:nNn \g_@@_x_initial_dim = \g_@@_x_final_dim }
1515     \bool_if:NF \l_tmpb_bool
1516         {
1517             \dim_gset:Nn \g_@@_x_initial_dim
1518                 {
1519                     \bool_if:NTF \l_tmpa_bool \dim_min:nn \dim_max:nn
1520                         \g_@@_x_initial_dim \g_@@_x_final_dim
1521                 }
1522             \dim_gset_eq:NN \g_@@_x_final_dim \g_@@_x_initial_dim
1523         }
1524     \@@_draw_tikz_line:
1525 }
1526 }
1527 }

```

For the diagonal lines, the situation is a bit more complicated because, by default, we parallelize the diagonals lines. The first diagonal line is drawn and then, all the other diagonal lines are drawn parallel to the first one.

```

1528 \cs_new_protected:Nn \@@_draw_Ddots:nn
1529 {
1530     \cs_if_free:cT { @_ dotted _ #1 - #2 }
1531     {
1532         \bool_set_false:N \l_@@_impossible_line_bool
1533         \@@_find_extremities_of_line:nnnn { #1 } { #2 } \c_one_int \c_one_int
1534         \bool_if:NF \l_@@_impossible_line_bool
1535         {
1536             \@@_retrieve_coords:xx
1537             {
1538                 \bool_if:NTF \l_@@_initial_open_bool
1539                     { - medium.north-west }
1540                     { .south-east }
1541             }
1542             {
1543                 \bool_if:NTF \l_@@_final_open_bool
1544                     { - medium.south-east }
1545                     { .north-west }
1546             }
1547     }

```

We have retrieved the coordinates in the usual way (they are stored in `\g_@@_x_initial_dim`, etc.). If the parallelization of the diagonals is set, we will have (maybe) to adjust the fourth coordinate.

```

1547 \bool_if:NT \l_@@_parallelize_diags_bool
1548 {
1549     \int_incr:N \l_@@_ddots_int

```

We test if the diagonal line is the first one (the counter `\l_@@_ddots_int` is created for this usage).

```

1550     \int_compare:nNnTF \l_@@_ddots_int = \c_one_int

```

If the diagonal line is the first one, we have no adjustment of the line to do but we store the  $\Delta_x$  and the  $\Delta_y$  of the line because these values will be used to draw the others diagonal lines parallels to the first one.

```

1551 {
1552     \dim_set:Nn \l_@@_delta_x_one_dim
1553         { \g_@@_x_final_dim - \g_@@_x_initial_dim }
1554     \dim_set:Nn \l_@@_delta_y_one_dim

```

```

1555     { \g_@y_final_dim - \g_@y_initial_dim }
1556 }

```

If the diagonal line is not the first one, we have to adjust the second extremity of the line by modifying the coordinate `\g_@y_initial_dim`.

```

1557 {
1558     \dim_gset:Nn \g_@y_final_dim
1559     {
1560         \g_@y_initial_dim +
1561         ( \g_@x_final_dim - \g_@x_initial_dim ) *
1562         \dim_ratio:nn \l_@@delta_y_one_dim \l_@@delta_x_one_dim
1563     }
1564 }
1565 }

```

Now, we can draw the dotted line (after a possible change of `\g_@y_initial_dim`).

```

1566 \@@_draw_tikz_line:
1567 }
1568 }
1569 }

```

We draw the `\Iddots` diagonals in the same way.

```

1570 \cs_new_protected:Nn \@@_draw_Iddots:nn
1571 {
1572     \cs_if_free:cT { @ _ dotted _ #1 - #2 }
1573     {
1574         \bool_set_false:N \l_@@impossible_line_bool
1575         \@@_find_extremities_of_line:nnnn { #1 } { #2 } 1 { -1 }
1576         \bool_if:NF \l_@@impossible_line_bool
1577         {
1578             \@@_retrieve_coords:xx
1579             {
1580                 \bool_if:NTF \l_@@initial_open_bool
1581                 { - medium.north-east }
1582                 { .south-west }
1583             }
1584             {
1585                 \bool_if:NTF \l_@@final_open_bool
1586                 { - medium.south-west }
1587                 { .north-east }
1588             }
1589             \bool_if:NT \l_@@parallelize_diags_bool
1590             {
1591                 \int_incr:N \l_@@iddots_int
1592                 \int_compare:nNnTF \l_@@iddots_int = \c_one_int
1593                 {
1594                     \dim_set:Nn \l_@@delta_x_two_dim
1595                     { \g_@x_final_dim - \g_@x_initial_dim }
1596                     \dim_set:Nn \l_@@delta_y_two_dim
1597                     { \g_@y_final_dim - \g_@y_initial_dim }
1598                 }
1599                 {
1600                     \dim_gset:Nn \g_@y_final_dim
1601                     {
1602                         \g_@y_initial_dim +
1603                         ( \g_@x_final_dim - \g_@x_initial_dim ) *
1604                         \dim_ratio:nn \l_@@delta_y_two_dim \l_@@delta_x_two_dim
1605                     }
1606                 }
1607             }
1608             \@@_draw_tikz_line:
1609         }
1610     }
1611 }

```

The command `\NiceMatrixLastEnv` is not used by the package `nicematrix`. It's only a facility given to the final user. It gives the number of the last environment (in fact the number of the current environment but it's meant to be used after the environment in order to refer to that environment — and its nodes — without having to give it a name).

```
1612 \NewExpandableDocumentCommand \NiceMatrixLastEnv { }
1613   { \int_use:N \g_@@_env_int }
```

## 14.9 The actual instructions for drawing the dotted line with Tikz

The command `\@@_draw_tikz_line`: draws the line using four implicit arguments:

`\g_@@_x_initial_dim`, `\g_@@_y_initial_dim`, `\g_@@_x_final_dim` and `\g_@@_y_final_dim`. These variables are global for technical reasons: their first affectation was in an instruction `\tikz`.

```
1614 \cs_new_protected:Nn \@@_draw_tikz_line:
1615 {
```

The dimension `\l_@@_l_dim` is the length  $\ell$  of the line to draw. We use the floating point reals of `expl3` to compute this length.

```
1616 \dim_zero_new:N \l_@@_l_dim
1617 \dim_set:Nn \l_@@_l_dim
1618   {
1619     \fp_to_dim:n
1620     {
1621       sqrt
1622       (
1623         ( \dim_use:N \g_@@_x_final_dim
1624           - \dim_use:N \g_@@_x_initial_dim
1625         ) ^ 2
1626         +
1627         ( \dim_use:N \g_@@_y_final_dim
1628           - \dim_use:N \g_@@_y_initial_dim
1629         ) ^ 2
1630       )
1631     }
1632   }
```

We draw only if the length is not equal to zero (in fact, in the first compilation, the length may be equal to zero).

```
1633 \dim_compare:nNnf \l_@@_l_dim = \c_zero_dim
```

The integer `\l_tmpa_int` is the number of dots of the dotted line.

```
1634   {
1635     \bool_if:NTF \l_@@_initial_open_bool
1636     {
1637       \bool_if:NTF \l_@@_final_open_bool
1638       {
1639         \int_set:Nn \l_tmpa_int
1640         { \dim_ratio:nn \l_@@_l_dim \l_@@_inter_dots_dim }
1641       }
1642     {
1643       \int_set:Nn \l_tmpa_int
1644       {
1645         \dim_ratio:nn
1646         { \l_@@_l_dim - \l_@@_dotted_lines_margin_dim }
1647         \l_@@_inter_dots_dim
1648       }
1649     }
1650   }
1651   {
1652     \bool_if:NTF \l_@@_final_open_bool
1653     {
1654       \int_set:Nn \l_tmpa_int
```

```

1655     {
1656         \dim_ratio:nn
1657             { \l_@@_l_dim - \l_@@_dotted_lines_margin_dim }
1658             \l_@@_inter_dots_dim
1659     }
1660 }
1661 {
1662     \int_set:Nn \l_tmpa_int
1663     {
1664         \dim_ratio:nn
1665             { \l_@@_l_dim - ( \l_@@_dotted_lines_margin_dim * 2 ) }
1666             \l_@@_inter_dots_dim
1667     }
1668 }
1669 }
```

The dimensions  $\l_tmpa_dim$  and  $\l_tmpb_dim$  are the coordinates of the vector between two dots in the dotted line.

```

1670     \dim_set:Nn \l_tmpa_dim
1671     {
1672         ( \g_@@_x_final_dim - \g_@@_x_initial_dim ) *
1673         \dim_ratio:nn \l_@@_inter_dots_dim \l_@@_l_dim
1674     }
1675     \dim_set:Nn \l_tmpb_dim
1676     {
1677         ( \g_@@_y_final_dim - \g_@@_y_initial_dim ) *
1678         \dim_ratio:nn \l_@@_inter_dots_dim \l_@@_l_dim
1679     }
```

The length  $\ell$  is the length of the dotted line. We note  $\Delta$  the length between two dots and  $n$  the number of intervals between dots. We note  $\delta = \frac{1}{2}(\ell - n\Delta)$ . The distance between the initial extremity of the line and the first dot will be equal to  $k \cdot \delta$  where  $k = 0, 1$  or  $2$ . We first compute this number  $k$  in  $\l_tmpb_int$ .

```

1680     \int_set:Nn \l_tmpb_int
1681     {
1682         \bool_if:NTF \l_@@_initial_open_bool
1683             { \bool_if:NTF \l_@@_final_open_bool 1 0 }
1684             { \bool_if:NTF \l_@@_final_open_bool 2 1 }
1685     }
```

In the loop over the dots ( $\int_step_inline:nnnn$ ), the dimensions  $\g_@@_x_initial_dim$  and  $\g_@@_y_initial_dim$  will be used for the coordinates of the dots. But, before the loop, we must move until the first dot.

```

1686     \dim_gadd:Nn \g_@@_x_initial_dim
1687     {
1688         ( \g_@@_x_final_dim - \g_@@_x_initial_dim ) *
1689         \dim_ratio:nn
1690         { \l_@@_l_dim - \l_@@_inter_dots_dim * \l_tmpa_int }
1691         { \l_@@_l_dim * 2 }
1692         * \l_tmpb_int
1693     }
```

(In a multiplication of a dimension and an integer, the integer must always be put in second position.)

```

1694     \dim_gadd:Nn \g_@@_y_initial_dim
1695     {
1696         ( \g_@@_y_final_dim - \g_@@_y_initial_dim ) *
1697         \dim_ratio:nn
1698         { \l_@@_l_dim - \l_@@_inter_dots_dim * \l_tmpa_int }
1699         { \l_@@_l_dim * 2 } *
1700         \l_tmpb_int
1701     }
1702     \begin{tikzpicture} [ overlay ]
1703     \int_step_inline:nnn 0 \l_tmpa_int
1704     {
```

```

1705     \pgfpathcircle
1706     { \pgfpoint { \g_@@_x_initial_dim } { \g_@@_y_initial_dim } }
1707     { \l_@@_radius_dim }
1708     \pgfusepath { fill }
1709     \dim_gadd:Nn \g_@@_x_initial_dim \l_tmpa_dim
1710     \dim_gadd:Nn \g_@@_y_initial_dim \l_tmpb_dim
1711   }
1712   \end{tikzpicture}
1713 }
1714 }
```

## 14.10 User commands available in the new environments

We give new names for the commands `\ldots`, `\cdots`, `\vdots` and `\ddots` because these commands will be redefined (if the option `renew-dots` is used).

```

1715 \cs_set_eq:NN \@@_ldots \ldots
1716 \cs_set_eq:NN \@@_cdots \cdots
1717 \cs_set_eq:NN \@@_vdots \vdots
1718 \cs_set_eq:NN \@@_ddots \ddots
1719 \cs_set_eq:NN \@@_iddots \iddots
```

The command `\@@_add_to_empty_cells`: adds the current cell to `\g_@@_empty_cells_seq` which is the list of the empty cells (the cells explicitly declared “empty”: there may be, of course, other empty cells in the matrix).

```

1720 \cs_new_protected:Nn \@@_add_to_empty_cells:
1721 {
1722   \cs_gset:cpx
1723   { @@ _ empty _ \int_use:N \c@iRow - \int_use:N \c@jCol }
1724   { \int_use:N \g_@@_env_int }
1725 }
```

The commands `\@@_Ldots`, `\@@_Cdots`, `\@@_Vdots`, `\@@_Ddots` and `\@@_Idots` will be linked to `\Ldots`, `\Cdots`, `\Vdots`, `\Ddots` and `\Idots` in the environments `{NiceArray}` (the other environments of `nicematrix` rely upon `{NiceArray}`).

The starred versions of these commands are deprecated since version 3.1 but they are still available.

```

1726 \NewDocumentCommand \@@_Ldots { s }
1727 {
1728   \bool_if:nF { #1 } { \@@_instruction_of_type:n { Ldots } }
1729   \bool_if:NF \l_@@_nullify_dots_bool { \phantom \@@_ldots }
1730   \@@_add_to_empty_cells:
1731 }

1732 \NewDocumentCommand \@@_Cdots { s }
1733 {
1734   \bool_if:nF { #1 } { \@@_instruction_of_type:n { Cdots } }
1735   \bool_if:NF \l_@@_nullify_dots_bool { \phantom \@@_cdots }
1736   \@@_add_to_empty_cells:
1737 }

1738 \NewDocumentCommand \@@_Vdots { s }
1739 {
1740   \bool_if:nF { #1 } { \@@_instruction_of_type:n { Vdots } }
1741   \bool_if:NF \l_@@_nullify_dots_bool { \phantom \@@_vdots }
1742   \@@_add_to_empty_cells:
1743 }
```

```

1744 \NewDocumentCommand \@@_Ddots { s }
1745 {
1746   \bool_if:nF { #1 } { \@@_instruction_of_type:n { Ddots } }
1747   \bool_if:NF \l_@@_nullify_dots_bool { \phantom \@@_ddots }
1748   \@@_add_to_empty_cells:
1749 }

1750 \NewDocumentCommand \@@_Iddots { s }
1751 {
1752   \bool_if:nF { #1 } { \@@_instruction_of_type:n { Iddots } }
1753   \bool_if:NF \l_@@_nullify_dots_bool { \phantom \@@_iddots }
1754   \@@_add_to_empty_cells:
1755 }

```

The command `\@@_Hspace:` will be linked to `\hspace` in `{NiceArray}`.

```

1756 \cs_new_protected:Nn \@@_Hspace:
1757 {
1758   \@@_add_to_empty_cells:
1759   \hspace
1760 }

```

In the environment `{NiceArray}`, the command `\multicolumn` will be linked to the following command `\@@_multicolumn:nnn`.

```

1761 \cs_set_eq:NN \@@_old_multicolumn \multicolumn
1762 \cs_new:Npn \@@_multicolumn:nnn #1 #2 #3
1763 {
1764   \@@_old_multicolumn { #1 } { #2 } { #3 }
1765   \int_compare:nNnT #1 > 1
1766   {
1767     \seq_gput_left:Nx \g_@@_multicolumn_cells_seq
1768     { \int_eval:n \c@iRow - \int_use:N \c@jCol }
1769     \seq_gput_left:Nn \g_@@_multicolumn_sizes_seq { #1 }
1770   }
1771   \int_gadd:Nn \c@jCol { #1 - 1 }
1772 }

```

The command `\@@_Hdotsfor` will be linked to `\Hdotsfor` in `{NiceArray}`. This command uses an optional argument like `\hdotsfor` but this argument is discarded (in `\Hdotsfor`, this argument is used for fine tuning of the space between two consecutive dots). Tikz nodes are created for all the cells of the array, even the implicit cells of the `\Hdotsfor`.

This command must not be protected since it begins with `\multicolumn`.

```

1773 \cs_new:Npn \@@_Hdotsfor:
1774 {
1775   \multicolumn { 1 } { c } { }
1776   \@@_Hdotsfor_i
1777 }

```

The command `\@@_Hdotsfor_i` is defined with the tools of `xparse` because it has an optionnal argument. Note that such a command defined by `\NewDocumentCommand` is protected and that's why we have put the `\multicolumn` before (in the definition of `\@@_Hdotsfor:`).

```

1778 \bool_if:NTF \c_@@_draft_bool
1779 {
1780   \NewDocumentCommand \@@_Hdotsfor_i { 0 { } m }
1781   { \prg_replicate:nn { #2 - 1 } { & \multicolumn { 1 } { c } { } } }
1782 }
1783 {
1784   \NewDocumentCommand \@@_Hdotsfor_i { 0 { } m }
1785   {
1786     \tl_gput_right:Nx \g_@@_Hdotsfor_lines_tl
1787     {

```

```

1788         \@@_draw_Hdotsfor:nnn
1789         { \int_use:N \c@iRow }
1790         { \int_use:N \c@jCol }
1791         { #2 }
1792     }
1793     \prg_replicate:nn { #2 - 1 } { & \multicolumn { 1 } { c } { } }
1794 }
1795 }

1796 \cs_new_protected:Nn \@@_draw_Hdotsfor:nnn
1797 {
1798     \bool_set_false:N \l_@@_initial_open_bool
1799     \bool_set_false:N \l_@@_final_open_bool

```

For the row, it's easy.

```

1800     \int_set:Nn \l_@@_initial_i_int { #1 }
1801     \int_set:Nn \l_@@_final_i_int { #1 }

```

For the column, it's a bit more complicated.

```

1802     \int_compare:nNnTF #2 = 1
1803     {
1804         \int_set:Nn \l_@@_initial_j_int 1
1805         \bool_set_true:N \l_@@_initial_open_bool
1806     }
1807     {
1808         \int_set:Nn \l_tmpa_int { #2 - 1 }
1809         \@@_if_not_empty_cell:nnTF \l_@@_initial_i_int \l_tmpa_int
1810         { \int_set:Nn \l_@@_initial_j_int { #2 - 1 } }
1811         {
1812             \int_set:Nn \l_@@_initial_j_int {#2}
1813             \bool_set_true:N \l_@@_initial_open_bool
1814         }
1815     }
1816     \int_compare:nNnTF { #2 + #3 - 1 } = \c@jCol
1817     {
1818         \int_set:Nn \l_@@_final_j_int { #2 + #3 - 1 }
1819         \bool_set_true:N \l_@@_final_open_bool
1820     }
1821     {
1822         \int_set:Nn \l_tmpa_int { #2 + #3 }
1823         \@@_if_not_empty_cell:nnTF \l_@@_final_i_int \l_tmpa_int
1824         { \int_set:Nn \l_@@_final_j_int { #2 + #3 } }
1825         {
1826             \int_set:Nn \l_@@_final_j_int { #2 + #3 - 1 }
1827             \bool_set_true:N \l_@@_final_open_bool
1828         }
1829     }
1830     \bool_if:nT { \l_@@_initial_open_bool || \l_@@_final_open_bool }
1831     \@@_create_medium_nodes:
1832     \@@_actually_draw_Ldots:

```

We declare all the cells concerned by the \Hdotsfor as “dotted” (for the dotted lines created by \Cdots, \Ldots, etc., this job is done by \@@\_find\_extremities\_of\_line:nnnn). This declaration is done by defining a special control sequence (to nil).

```

1833     \int_step_inline:nnn { #2 } { #2 + #3 - 1 }
1834     { \cs_set:cpn { @@ _ dotted _ #1 - ##1 } { } }
1835 }

```

## 14.11 The command \line accessible in code-after

In the code-after, the command \@@\_line:nn will be linked to \line. This command takes two arguments which are the specification of two cells in the array (in the format  $i-j$ ) and draws a dotted line between these cells.

First, we write a command with an argument of the format  $i-j$  and applies the command `\int_eval:n` to  $i$  and  $j$ ; this must *not* be protected (and is, of course fully expandable).<sup>33</sup>

```
1836 \cs_new:Npn \@@_double_int_eval:n #1-#2 \q_stop
1837   { \int_eval:n { #1 } - \int_eval:n { #2 } }
```

With the following construction, the command `\@@_double_int_eval:n` is applied to both arguments before the application of `\@@_line_i:nn` (the construction uses the fact the `\@@_line_i:nn` is protected and that `\@@_double_int_eval:n` is fully expandable).

```
1838 \cs_new_protected:Npn \@@_line:nn #1 #2
1839   {
1840     \use:x
1841     {
1842       \@@_line_i:nn
1843         { \@@_double_int_eval:n #1 \q_stop }
1844         { \@@_double_int_eval:n #2 \q_stop }
1845     }
1846   }
1847 \cs_new_protected:Nn \@@_line_i:nn
1848   {
1849     \bool_if:NF \c_@@_draft_bool
1850     {
1851       \dim_zero_new:N \g_@@_x_initial_dim
1852       \dim_zero_new:N \g_@@_y_initial_dim
1853       \dim_zero_new:N \g_@@_x_final_dim
1854       \dim_zero_new:N \g_@@_y_final_dim
1855       \bool_set_false:N \l_@@_initial_open_bool
1856       \bool_set_false:N \l_@@_final_open_bool
1857       \bool_if:nTF
1858       {
1859         \cs_if_exist_p:c { pgf@sh@ns@nm - \int_use:N \g_@@_env_int - #1 }
1860         &&
1861         \cs_if_exist_p:c { pgf@sh@ns@nm - \int_use:N \g_@@_env_int - #2 }
1862       }
1863       {
1864         \begin{tikzpicture}
1865           \path~(#1)----(#2)-node[at~start]~(i)~{}~-node[at~end]~(f)~{};
1866           \tikz@parse@node \pgfutil@firstofone ( i )
1867           \dim_gset:Nn \g_@@_x_initial_dim \pgf@x
1868           \dim_gset:Nn \g_@@_y_initial_dim \pgf@y
1869           \tikz@parse@node \pgfutil@firstofone ( f )
1870           \dim_gset:Nn \g_@@_x_final_dim \pgf@x
1871           \dim_gset:Nn \g_@@_y_final_dim \pgf@y
1872         \end{tikzpicture}
1873         \@@_draw_tikz_line:
1874       }
1875       {
1876         \@@_error:nnn { unknown~cell~for~line~in~code~after }
1877         { #1 } { #2 }
1878       }
1879     }
1880   }
```

The commands `\Ldots`, `\Cdots`, `\Vdots`, `\Ddots`, and `\Iddots` don't use this command because they have to do other settings (for example, the diagonal lines must be parallelized).

## 14.12 The commands to draw dotted lines to separate columns and rows

The command `\hdottedline` draws an horizontal dotted line to separate two rows. Similarly, the letter ":" in the preamble draws a vertical dotted line (the letter can be changed with the option

---

<sup>33</sup>Indeed, we want that the user may use the command `\line in code-after` with LaTeX counters in the arguments — with the command `\value`.

`letter-for-dotted-lines`). Both mechanisms write instructions in the `code-after`. The actual instructions in the `code-after` use the commands `\@@_hdottedline:n` and `\@@_vdottedline:n`.

We want the horizontal lines at the same position<sup>34</sup> as the line created by `\hline` (or `\hdashline` of `arydshln`). That's why we use a `\noalign` to insert a box with a `\dotfill`.

Some extensions, like the extension `doc`, do a redefinition of the command `\dotfill` of LaTeX. That's why we define a command `\@@_dotfill`: as we wish. We test whether we are in draft mode because, in this case, we don't draw the dotted lines.

```
1881 \bool_if:NTF \c_@@_draft_bool
1882   { \cs_set_eq:NN \@@_dotfill: \prg_do_nothing: }
1883   {
1884     \cs_set:Npn \@@_dotfill:
1885     {
```

If the option `small` is used, we change the space between dots (we can't use `\l_@@_inter_dots_dim` which will be set after the construction of the array). We can't put the `\bool_if:NT` in the first argument of `\hbox_to_wd:nn` because `\cleaders` is a special TeX primitive.

```
1886   \bool_if:NT \l_@@_small_bool
1887     { \dim_set:Nn \l_@@_inter_dots_dim { 0.25 em } }
1888   \cleaders
1889   \hbox_to_wd:nn
1890     { \l_@@_inter_dots_dim }
1891     {
1892       \c_math_toggle_token
1893       \bool_if:NT \l_@@_small_bool \scriptstyle
1894       \hss . \hss
1895       \c_math_toggle_token
1896     }
1897   \hfill
1898 }
1899 }
```

This command must *not* be protected because it starts with `\noalign`.

```
1900 \cs_new:Npn \@@_hdottedline:
1901   {
1902     \noalign
1903     {
1904       \bool_gset_true:N \g_@@_large_nodes_bool
1905       \cs_if_exist:cTF { @@_width_ \int_use:N \g_@@_env_int }
1906         { \dim_set_eq:Nc \l_tmpa_dim { @@_width_ \int_use:N \g_@@_env_int } }
1907         { \dim_set:Nn \l_tmpa_dim { 5 mm } }
1908     \hbox_overlap_right:n
1909     {
1910       \bool_if:nT
1911         {
1912           \l_@@_NiceArray_bool
1913             &&
1914           ! \l_@@_exterior_arraycolsep_bool
1915             &&
1916           \int_compare_p:nNn \l_@@_first_col_int > \c_zero_int
1917         }
1918         { \skip_horizontal:n { - \arraycolsep } }
1919     \hbox_to_wd:nn
1920     {
1921       \l_tmpa_dim + 2 \arraycolsep
1922       - \l_@@_left_margin_dim - \l_@@_right_margin_dim
1923     }
1924     \@@_dotfill:
1925   }
1926 }
```

---

<sup>34</sup>In fact, almost the same position because of the width of the line: the width of a dotted line is not the same as the width of a line created by `\hline`.

```

1928 \cs_new_protected:Nn \@@_vdottedline:n
1929 {

```

We should allow the letter ":" in the first position of the preamble but that would need a special programmation.

```

1930 \int_compare:nNnTF #1 = \c_zero_int
1931   { \@@_error:n { Use-of-:~in-first-position } }
1932   {
1933     \bool_if:NF \c_@@_draft_bool
1934     {
1935       \dim_zero_new:N \g_@@_x_initial_dim
1936       \dim_zero_new:N \g_@@_y_initial_dim
1937       \dim_zero_new:N \g_@@_x_final_dim
1938       \dim_zero_new:N \g_@@_y_final_dim
1939       \bool_set_true:N \l_@@_initial_open_bool
1940       \bool_set_true:N \l_@@_final_open_bool

```

If a "col" node exists (if the array has been constructed with a fixed width of column), we use it.

```

1941 \cs_if_exist:cTF
1942   { pgf@sh@ns@nm -\int_use:N \g_@@_env_int - col - #1 }
1943   {
1944     \begin{tikzpicture} [ remember picture ]
1945       \tikz@parse@node\pgfutil@firstofone
1946         ( col - #1 )
1947       \dim_gset:Nn \g_@@_x_initial_dim \pgf@x
1948       \dim_gset:Nn \g_@@_x_final_dim \pgf@x
1949       \dim_gset:Nn \g_@@_y_final_dim \pgf@y
1950     \end{tikzpicture}
1951     \dim_gset:Nn \g_@@_y_initial_dim { - \c_max_dim }
1952     \int_step_inline:nn \c@jCol
1953     {
1954       \begin{tikzpicture} [ remember picture ]
1955         \tikz@parse@node\pgfutil@firstofone
1956           ( 1 - ##1 . north-east )
1957         \dim_gset:Nn \g_@@_y_initial_dim
1958           { \dim_max:nn \g_@@_y_initial_dim \pgf@y }
1959         \end{tikzpicture}
1960     }
1961   }

```

If not, we use the "large node".

```

1962 {
1963   \begin{tikzpicture} [ remember picture ]
1964     \tikz@parse@node\pgfutil@firstofone
1965       ( 1 - #1 - large .north-east )
1966     \dim_gset:Nn \g_@@_x_initial_dim \pgf@x
1967     \dim_gset:Nn \g_@@_y_initial_dim \pgf@y
1968     \tikz@parse@node\pgfutil@firstofone
1969       ( \int_use:N \c@iRow - #1 - large .south-east )
1970     \dim_gset:Nn \g_@@_x_final_dim \pgf@x
1971     \dim_gset:Nn \g_@@_y_final_dim \pgf@y
1972   \end{tikzpicture}

```

However, if the previous column was constructed with a letter *w*, we use the *w*-nodes (and we erase the previous computation of the *x*-value of the vertical dotted line).

```

1973 \cs_if_exist:cTF
1974   { pgf@sh@ns@nm -\int_use:N \g_@@_env_int - 1 - #1 - w }
1975   {
1976     \begin{tikzpicture} [ remember picture ]
1977       \tikz@parse@node\pgfutil@firstofone
1978         ( 1 - #1 - w .north-east )
1979       \dim_gset:Nn \g_@@_x_initial_dim \pgf@x
1980       \tikz@parse@node\pgfutil@firstofone
1981         ( \int_use:N \c@iRow - #1 - w .south-east )
1982       \dim_gset:Nn \g_@@_x_final_dim \pgf@x

```

```

1983         \end{tikzpicture} \\
1984         \dim_gadd:Nn \g_@@_x_initial_dim \arraycolsep
1985         \dim_gadd:Nn \g_@@_x_final_dim \arraycolsep
1986     }
1987     \\
1988     \@@_draw_tikz_line:
1989   }
1990 }
1991 }
```

## 14.13 The vertical rules

We don't want that a vertical rule drawn by the specifier “|” extends in the eventual “first row” and “last row” of the array.

The natural way to do that would be to redefine the specifier “|” with `\newcolumntype`:

```
\newcolumntype{|}{ ! { \int_compare:nNnF \c@iRow = \c_zero_int \vline } }
```

However, this code fails if the user uses `\DefineShortVerb{\|}` of `fancyverb`. Moreover, it would not be able to deal correctly with two consecutive specifiers “|” (in a preamble like `ccc||ccc`).

That's why we will do a redefinition of the macro `\arrayrule` of `array` and this redefinition will add `\@@_vline:` instead of `\vline` to the preamble.

Here is the definition of `\@@_vline:`. This definition *must* be protected because you don't want that macro expanded during the construction of the preamble (the tests must be effective in each row and not once when the preamble is constructed).

```

1992 \cs_new_protected:Npn \@@_vline:
1993 {
1994   \int_compare:nNnTF \l_@@_first_col_int = \c_zero_int
1995   {
1996     \int_compare:nNnTF \c@jCol = \c_zero_int
1997     {
1998       \int_compare:nNnTF \l_@@_first_row_int = \c_zero_int
1999       {
2000         \int_compare:nNnF \c@iRow = \c_zero_int
2001         {
2002           \int_compare:nNnF \c@iRow = \l_@@_last_row_int
2003           \@@_vline_i:
2004         }
2005       }
2006     }
2007     \int_compare:nNnF \c@iRow = \c_zero_int
2008     {
2009       \int_compare:nNnF \c@iRow = \l_@@_last_row_int
2010       \@@_vline_i:
2011     }
2012   }
2013 }
2014 {
2015   \int_compare:nNnF \c@iRow = \c_zero_int
2016   {
2017     \int_compare:nNnF \c@iRow = \l_@@_last_row_int
2018     \@@_vline_i:
2019   }
2020 }
2021 }
2022 {
2023   \int_compare:nNnTF \c@jCol = \c_zero_int
2024   {
2025     \int_compare:nNnF \c@iRow = { -1 }
2026     {
```

```

2027     \int_compare:nNnF \c@iRow = { \l_@@_last_row_int - 1 }
2028         \@@_vline_i:
2029     }
2030 }
2031 {
2032     \int_compare:nNnF \c@iRow = \c_zero_int
2033     {
2034         \int_compare:nNnF \c@iRow = \l_@@_last_row_int
2035             \@@_vline_i:
2036         }
2037     }
2038 }
2039 }
```

If `colortbl` is loaded, the following macro will be redefined (in a `\AtBeginDocument`) to take into account the color fixed by `\arrayrulecolor` of `colortbl`.

```
2040 \cs_set_eq:NN \@@_vline_i: \vline
```

We give now the definition of `\OnlyMainNiceMatrix`. Internally, it is not used by `nicematrix`. It's only a facility given to the final user, which may be useful in the definitions of new columns types (with `\newcolumntype`).

First, we give the definition of `\OnlyMainNiceMatrix` in the general case: it's no-op (thus, a definition of column type may be used outside the environments of `nicematrix`, in `{array}`, etc.).

```
2041 \cs_set_eq:NN \OnlyMainNiceMatrix \use:n
```

Now, we give the definition of `\OnlyMainNiceMatrix` which will be used in the environments of `nicematrix`. This command `\@@_OnlyMainNiceMatrix:n` will be linked to `\OnlyMainNiceMatrix` in `\@@_pre_array:`. This command is “fully expandable” and that's why we have not protected it, even tough this characteristic will probably not be used.

```

2042 \cs_new:Npn \@@_OnlyMainNiceMatrix:n #1
2043 {
2044     \int_compare:nNnF \c@iRow = \c_zero_int
2045         { \int_compare:nNnF \c@iRow = \l_@@_last_row_int { #1 } }
2046 }
```

## 14.14 The environment `{NiceMatrixBlock}`

The following flag will be raised when all the columns of the environments of the block must have the same width in “auto” mode.

```
2047 \bool_new:N \l_@@_block_auto_columns_width_bool
```

As of now, there is only one option available for the environment `{NiceMatrixBlock}`.

```

2048 \keys_define:nn { NiceMatrix / NiceMatrixBlock }
2049 {
2050     auto-columns-width .code:n =
2051     {
2052         \bool_set_true:N \l_@@_block_auto_columns_width_bool
2053         \dim_gzero_new:N \g_@@_max_cell_width_dim
2054         \bool_set_true:N \l_@@_auto_columns_width_bool
2055     }
2056 }
```

  

```

2057 \NewDocumentEnvironment { NiceMatrixBlock } { ! O { } }
2058 {
2059     \int_gincr:N \g_@@_NiceMatrixBlock_int
2060     \dim_zero:N \l_@@_columns_width_dim
2061     \keys_set:nn { NiceMatrix / NiceMatrixBlock } { #1 }
2062     \bool_if:NT \l_@@_block_auto_columns_width_bool
```

```

2063     {
2064         \cs_if_exist:cT { @@_max_cell_width_ \int_use:N \g_@@_NiceMatrixBlock_int }
2065         {
2066             \dim_set:Nx \l_@@_columns_width_dim
2067             { \use:c { @@_max_cell_width_ \int_use:N \g_@@_NiceMatrixBlock_int } }
2068         }
2069     }
2070 }

```

At the end of the environment `{NiceMatrixBlock}`, we write in the main `.aux` file instructions for the column width of all the environments of the block (that's why we have stored the number of the first environment of the block in the counter `\l_@@_first_env_block_int`).

```

2071 {
2072     \bool_if:NT \l_@@_block_auto_columns_width_bool
2073     {
2074         \iow_now:Nn \mainaux \ExplSyntaxOn
2075         \iow_now:Nx \mainaux
2076         {
2077             \cs_gset:cpn
2078             { @@ _ max _ cell _ width _ \int_use:N \g_@@_NiceMatrixBlock_int }
2079             { \dim_use:N \g_@@_max_cell_width_dim }
2080         }
2081         \iow_now:Nn \mainaux \ExplSyntaxOff
2082     }
2083 }

```

## 14.15 The extra nodes

First, two variants of the functions `\dim_min:nn` and `\dim_max:nn`.

```

2084 \cs_generate_variant:Nn \dim_min:nn { v n }
2085 \cs_generate_variant:Nn \dim_max:nn { v n }

```

We have three macros of creation of nodes: `\@@_create_medium_nodes:`, `\@@_create_large_nodes:` and `\@@_create_medium_and_large_nodes:`. They must *not* be used in the `code-after` because the `code-after` is executed in a scope of prefix name of Tikz.

We have to compute the mathematical coordinates of the “medium nodes”. These mathematical coordinates are also used to compute the mathematical coordinates of the “large nodes”. That's why we write a command `\@@_computations_for_medium_nodes:` to do these computations.

The command `\@@_computations_for_medium_nodes:` must be used in a `{tikzpicture}`. For each row  $i$ , we compute two dimensions `l_@@_row_i_min_dim` and `l_@@_row_i_max_dim`. The dimension `l_@@_row_i_min_dim` is the minimal  $y$ -value of all the cells of the row  $i$ . The dimension `l_@@_row_i_max_dim` is the maximal  $y$ -value of all the cells of the row  $i$ .

Similarly, for each column  $j$ , we compute two dimensions `l_@@_column_j_min_dim` and `l_@@_column_j_max_dim`. The dimension `l_@@_column_j_min_dim` is the minimal  $x$ -value of all the cells of the column  $j$ . The dimension `l_@@_column_j_max_dim` is the maximal  $x$ -value of all the cells of the column  $j$ .

Since these dimensions will be computed as maximum or minimum, we initialize them to `\c_max_dim` or `-\c_max_dim`.

```

2086 \cs_new_protected:Npn \@@_computations_for_medium_nodes:
2087 {
2088     \int_step_variable:nnNn \l_@@_first_row_int \g_@@_row_total_int \@@_i:
2089     {
2090         \dim_zero_new:c { l_@@_row_\@@_i: _min_dim }
2091         \dim_set_eq:cN { l_@@_row_\@@_i: _min_dim } \c_max_dim
2092         \dim_zero_new:c { l_@@_row_\@@_i: _max_dim }
2093         \dim_set:cn { l_@@_row_\@@_i: _max_dim } { - \c_max_dim }
2094     }

```

```

2095 \int_step_variable:nnNn \l_@@_first_col_int \g_@@_col_total_int \@@_j:
2096 {
2097     \dim_zero_new:c { l_@@_column_\@@_j: _min_dim }
2098     \dim_set_eq:cN { l_@@_column_\@@_j: _min_dim } \c_max_dim
2099     \dim_zero_new:c { l_@@_column_\@@_j: _max_dim }
2100     \dim_set:cN { l_@@_column_\@@_j: _max_dim } { - \c_max_dim }
2101 }

```

We begin the two nested loops over the rows and the columns of the array.

```

2102 \int_step_variable:nnNn \l_@@_first_row_int \g_@@_row_total_int \@@_i:
2103 {
2104     \int_step_variable:nnNn
2105         \l_@@_first_col_int \g_@@_col_total_int \@@_j:

```

Maybe the cell  $(i-j)$  is an implicit cell (that is to say a cell after implicit ampersands &). In this case, of course, we don't update the dimensions we want to compute.

```

2106     { \cs_if_exist:cT
2107         { pgf@sh@ns@nm - \int_use:N \g_@@_env_int - \@@_i: - \@@_j: }

```

We retrieve the coordinates of the anchor `south west` of the (normal) node of the cell  $(i-j)$ . They will be stored in `\pgf@x` and `\pgf@y`.

```

2108 {
2109     \tikz@parse@node \pgfutil@firstofone
2110         ( nm - \int_use:N \g_@@_env_int
2111             - \@@_i: - \@@_j: .south-west )
2112     \dim_set:cN { l_@@_row_\@@_i: _min_dim}
2113         { \dim_min:vn { l_@@_row_ \@@_i: _min_dim } \pgf@y }
2114     \seq_if_in:NxF \g_@@_multicolumn_cells_seq { \@@_i: - \@@_j: }
2115         {
2116             \dim_set:cN { l_@@_column_ \@@_j: _min_dim}
2117                 { \dim_min:vn { l_@@_column_ \@@_j: _min_dim } \pgf@x }
2118         }

```

We retrieve the coordinates of the anchor `north east` of the (normal) node of the cell  $(i-j)$ . They will be stored in `\pgf@x` and `\pgf@y`.

```

2119 \tikz@parse@node \pgfutil@firstofone
2120     ( nm - \int_use:N \g_@@_env_int - \@@_i: - \@@_j: .north-east )
2121     \dim_set:cN { l_@@_row_ \@@_i: _ max_dim }
2122         { \dim_max:vn { l_@@_row_ \@@_i: _ max_dim } \pgf@y }
2123     \seq_if_in:NxF \g_@@_multicolumn_cells_seq { \@@_i: - \@@_j: }
2124         {
2125             \dim_set:cN { l_@@_column_ \@@_j: _ max_dim }
2126                 { \dim_max:vn { l_@@_column_ \@@_j: _ max_dim } \pgf@x }
2127         }
2128     }
2129 }
2130 }
2131 }

```

Here is the command `\@@_create_medium_nodes`:. When this command is used, the “medium nodes” are created. These nodes won't be constructed twice because when used once, this command becomes no-op.

```

2132 \cs_new_protected:Npn \@@_create_medium_nodes:
2133 {
2134     \begin{tikzpicture} [ remember picture , overlay ]
2135         \@@_computations_for_medium_nodes:
2136         \tikzset { name-suffix = -medium }

```

Now, we can create the “medium nodes”. We use a command `\@@_create_nodes`: because this command will also be used for the creation of the “large nodes” (after changing the value of `name-suffix`).

```

2137 \@@_create_nodes:
2138 \end{tikzpicture}
2139 \cs_set_protected:Npn \@@_create_medium_nodes: { }
2140 \cs_set_protected:Npn \@@_create_medium_and_large_nodes:

```

```

2141     { \@@_create_large_nodes: }
2142 }

The command \@@_create_large_nodes: must be used when we want to create only the “large nodes” and not the medium ones (if we want to create both, we have to use the command \@@_create_medium_and_large_nodes:). However, the computation of the mathematical coordinates of the “large nodes” needs the computation of the mathematical coordinates of the “medium nodes”. That’s why we use first \@@_computations_for_medium_nodes: and then the command \@@_computations_for_large_nodes:.

2143 \cs_new_protected:Npn \@@_create_large_nodes:
2144 {
2145     \begin{tikzpicture} [remember picture, overlay]
2146         \@@_computations_for_medium_nodes:
2147         \@@_computations_for_large_nodes:
2148         \tikzset { name-suffix = -large }
2149         \@@_create_nodes:
2150     \end{tikzpicture}
2151     \@@_compute_width_of_array:
2152     \cs_set_protected:Npn \@@_create_large_nodes: { }
2153     \cs_set_protected:Npn \@@_create_medium_and_large_nodes:
2154         { \@@_create_medium_nodes: }
2155 }

2156 \cs_new_protected:Npn \@@_create_medium_and_large_nodes:
2157 {
2158     \begin{tikzpicture} [remember picture, overlay]
2159         \@@_computations_for_medium_nodes:

```

Now, we can create the “medium nodes”. We use a command \@@\_create\_nodes: because this command will also be used for the creation of the “large nodes” (after changing the value of `name-suffix`).

```

2160     \tikzset { name-suffix = -medium }
2161     \@@_create_nodes:
2162     \@@_computations_for_large_nodes:
2163     \tikzset { name-suffix = -large }
2164     \@@_create_nodes:
2165     \@@_compute_width_of_array:
2166     \end{tikzpicture}
2167     \@@_compute_width_of_array:
2168     \cs_set_protected:Npn \@@_create_medium_and_large_nodes: { }
2169     \cs_set_protected:Npn \@@_create_medium_nodes: { }
2170     \cs_set_protected:Npn \@@_create_large_nodes: { }
2171 }
```

For “large nodes”, the exterior rows and columns don’t interfer. That’s why the loop over the columns will start at 1 and stop at `\c@jCol` (and not `\g_@@_col_total_int`). Idem for the rows.

```

2172 \cs_new_protected:Npn \@@_computations_for_large_nodes:
2173 {
2174     \int_set:Nn \l_@@_first_row_int 1
2175     \int_set:Nn \l_@@_first_col_int 1
```

We have to change the values of all the dimensions `l_@@_row_i_min_dim`, `l_@@_row_i_max_dim`, `l_@@_column_j_min_dim` and `l_@@_column_j_max_dim`.

```

2176     \int_step_variable:nNn { \c@iRow - 1 } \@@_i:
2177     {
2178         \dim_set:cn { l_@@_row _ \@@_i: _ min _ dim }
2179         {
2180             (
2181                 \dim_use:c { l_@@_row _ \@@_i: _ min _ dim } +
2182                 \dim_use:c { l_@@_row _ \int_eval:n { \@@_i: + 1 } _ max _ dim }
2183             )
2184             / 2
2185         }
2186         \dim_set_eq:cc { l_@@_row _ \int_eval:n { \@@_i: + 1 } _ max _ dim }
```

```

2187      { l_@_row_@\_i: _min_dim }
2188    }
2189 \int_step_variable:nNn { \c@jCol - 1 } \@\_j:
2190 {
2191   \dim_set:cn { l_@_column_ \@\_j: _max_dim }
2192   {
2193     (
2194       \dim_use:c
2195       { l_@_column_ \@\_j: _max_dim } +
2196       \dim_use:c
2197       { l_@_column_ \int_eval:n { \@\_j: + 1 } _min_dim }
2198     )
2199     / 2
2200   }
2201   \dim_set_eq:cc { l_@_column_ \int_eval:n { \@\_j: + 1 } _min_dim }
2202   { l_@_column_ \@\_j: _max_dim }
2203 }
2204 \dim_sub:cn
2205 { l_@_column_ 1 _min_dim }
2206 \l_@_left_margin_dim
2207 \dim_add:cn
2208 { l_@_column_ \int_use:N \c@jCol _max_dim }
2209 \l_@_right_margin_dim
2210 }
```

The control sequence `\@_create_nodes:` is used twice: for the construction of the “medium nodes” and for the construction of the “large nodes”. The nodes are constructed with the value of all the dimensions `l_@_row_i_min_dim`, `l_@_row_i_max_dim`, `l_@_column_j_min_dim` and `l_@_column_j_max_dim`. Between the construction of the “medium nodes” and the “large nodes”, the values of these dimensions are changed.

```

2211 \cs_new_protected:Npn \@\_create_nodes:
2212 {
2213   \int_step_variable:nnNn \l_@_first_row_int \g_@_row_total_int \@\_i:
2214   {
2215     \int_step_variable:nnNn \l_@_first_col_int \g_@_col_total_int \@\_j:
```

We create two ponctual nodes for the extremities of a diagonal of the rectangular node we want to create. These nodes (`@~south~west`) and (`@~north~east`) are not available for the user of nicematrix. That’s why their names are independent of the row and the column. In the two nested loops, they will be overwritten until the last cell.

```

2216   {
2217     \coordinate ( @~south~west )
2218     at ( \dim_use:c { l_@_column_ \@\_j: _min_dim } ,
2219           \dim_use:c { l_@_row_ \@\_i: _min_dim } ) ;
2220     \coordinate ( @~north~east )
2221     at ( \dim_use:c { l_@_column_ \@\_j: _max_dim } ,
2222           \dim_use:c { l_@_row_ \@\_i: _max_dim } ) ;
```

We can eventually draw the rectangular node for the cell (`\@\_i-\@\_j`). This node is created with the Tikz library `fit`. Don’t forget that the Tikz option `name suffix` has been set to `-medium` or `-large`.

```

2223   \node
2224   [
2225     node~contents = { } ,
2226     fit = ( @~south~west ) ( @~north~east ) ,
2227     inner~sep = \c_zero_dim ,
2228     name = nm - \int_use:N \g_@_env_int - \@\_i: - \@\_j: ,
2229     alias =
2230     \str_if_empty:NF \l_@_name_str
2231     { \l_@_name_str - \@\_i: - \@\_j: }
2232   ]
2233   ;
2234 }
```

```
2235     }
```

Now, we create the nodes for the cells of the `\multicolumn`. We recall that we have stored in `\g_@@_multicolumn_cells_seq` the list of the cells where a `\multicolumn{n}{...}{...}` with  $n > 1$  was issued and in `\g_@@_multicolumn_sizes_seq` the correspondant values of  $n$ .

```
2236 \seq_mapthread_function:NNN
2237   \g_@@_multicolumn_cells_seq
2238   \g_@@_multicolumn_sizes_seq
2239   \@@_node_for_multicolumn:nn
2240 }
```

We can now compute the width of the array (used by `\hdottedline`). We should modify this point because it's a waste to construct all the “large nodes” only for computing the width of the array.

```
2241 \cs_new_protected:Npn \@@_compute_width_of_array:
2242 {
2243   \begin{tikzpicture} [ remember picture , overlay ]
2244     \tikz@parse@node \pgfutil@firstofone
2245       ( nm - \int_use:N \g_@@_env_int - 1 - 1 - large .north-west )
2246     \dim_gset:Nn \g_tmpa_dim \pgf@x
2247     \tikz@parse@node \pgfutil@firstofone
2248       ( nm - \int_use:N \g_@@_env_int - 1 -
2249         \int_use:N \c@jCol - large .north-east )
2250     \dim_gset:Nn \g_tmpb_dim \pgf@x
2251   \end{tikzpicture}
2252   \iow_now:Nn \mainaux \ExplSyntaxOn
2253   \iow_now:Nx \mainaux
2254   {
2255     \cs_gset:cpn { @width_ \int_use:N \g_@@_env_int }
2256     { \dim_eval:n { \g_tmpb_dim - \g_tmpa_dim } }
2257   }
2258   \iow_now:Nn \mainaux \ExplSyntaxOff
2259 }
```

  

```
2260 \cs_new_protected:Npn \@@_extract_coords: #1 - #2 \q_stop
2261 {
2262   \cs_set:Npn \@@_i: { #1 }
2263   \cs_set:Npn \@@_j: { #2 }
2264 }
```

The command `\@@_node_for_multicolumn:nn` takes two arguments. The first is the position of the cell where the command `\multicolumn{n}{...}{...}` was issued in the format  $i-j$  and the second is the value of  $n$  (the length of the “multi-cell”).

```
2265 \cs_new_protected:Nn \@@_node_for_multicolumn:nn
2266 {
2267   \@@_extract_coords: #1 \q_stop
2268   \coordinate ( @@-south-west ) at
2269   (
2270     \dim_use:c { l_@@_column _ \@@_j: _ min _ dim } ,
2271     \dim_use:c { l_@@_row _ \@@_i: _ min _ dim }
2272   );
2273   \coordinate ( @@-north-east ) at
2274   (
2275     \dim_use:c { l_@@_column _ \int_eval:n { \@@_j: + #2 - 1 } _ max _ dim } ,
2276     \dim_use:c { l_@@_row _ \@@_i: _ max _ dim }
2277   );
2278   \node
2279   [
2280     node_contents = { } ,
2281     fit = ( @@-south-west ) ( @@-north-east ) ,
2282     inner_sep = \c_zero_dim ,
2283     name = nm - \int_use:N \g_@@_env_int - \@@_i: - \@@_j: ,
2284     alias =
2285       \str_if_empty:NF \l_@@_name_str
```

```

2286     { \l_@@_name_str - \@@_i: - \@@_j: }
2287   ]
2288 ;
2289 }
```

## 14.16 Block matrices

The code in this section is for the construction of *block matrices*. It has no direct link with the environment `{NiceMatrixBlock}`.

The following command will be linked to `\Block` in the environments of `nicematrix`. We define it with `\NewDocumentCommand` of `xparse` because it has an optional argument between `<` and `>` (for TeX instructions put before the math mode of the label)

```

2290 \NewDocumentCommand \@@_Block: { m D < > { } m }
2291   { \@@_Block_i #1 \q_stop { #2 } { #3 } }
```

The first argument of `\@@_Block:` (which is required) has a special syntax. It must be of the form  $i-j$  where  $i$  and  $j$  are the size (in rows and columns) of the block.

```
2292 \cs_new:Npn \@@_Block_i #1#2 \q_stop { \@@_Block_ii:nnnn { #1 } { #2 } }
```

Now, the arguments have been extracted: `#1` is  $i$  (the number of rows of the block), `#2` is  $j$  (the number of columns of the block), `#3` are the tokens to put before the math mode and `#4` is the label of the block. The following command must *not* be protected because it contains a command `\multicolumn` (in the case of a block of only one row).

```

2293 \cs_new:Npn \@@_Block_ii:nnnn #1 #2 #3 #4
2294 {
```

In the case of a block of only one row, we create a special node of shape `coordinate` in order to remember the  $y$ -value of the baseline of the current row.

```

2295 \int_compare:nNnT { #1 } = 1
2296 {
2297   \begin{tikzpicture} [remember picture, baseline]
2298     \coordinate
2299       ( nm - \int_use:N \g_@@_env_int
2300         - Block
2301         - \int_use:N \c@iRow
2302         - \int_use:N \c@jCol ) ;
2303   \end{tikzpicture}
2304 }
2305 \bool_gset_true:N \g_@@_medium_nodes_bool
```

We write an instruction in the `code-after`. We write the instruction in the beginning of the `code-after` (the `left` in `\tl_gput_left:Nx`) because we want the Tikz nodes corresponding of the block created *before* potential instructions written by the user in the `code-after` (these instructions may use the Tikz node of the created block).

```

2306 \tl_gput_left:Nx \g_@@_code_after_tl
2307 {
2308   \@@_Block_iii:nnnnn
2309   { \int_use:N \c@iRow }
2310   { \int_use:N \c@jCol }
2311   { \int_eval:n { \c@iRow + #1 - 1 } }
2312   { \int_eval:n { \c@jCol + #2 - 1 } }
2313   \exp_not:n { { #3 $ #4 $ } }
2314 }
2315 }
```

The following command `\@@_Block_iii:nnnnn` will be used in the `code-after`.

```

2316 \cs_new_protected:Npn \@@_Block_iii:nnnnn #1 #2 #3 #4 #5
2317 {
2318   \bool_if:nTF
2319   {
2320     \int_compare_p:nNn { #3 } > \c@iRow
```

```

2321     || \int_compare_p:nNn { #4 } > \c@jCol
2322   }
2323   { \msg_error:nnnn { nicematrix } { Block-too-large } { #1 } { #2 } }
2324   {

```

If the block has only one row, we have to do a special work in order to have the contains of the node aligned with the contents of the other rows of the array.

```

2325   \int_compare:nNnTF { #1 } = { #3 }
2326   {
2327     \begin{tikzpicture}

```

First, we compute in `\l_tmpa_dim` the *y*-value of the baseline of the row. We have constructed a special node of shape `coordinate` in this order.

```

2328     \tikz@parse@node \pgfutil@firstofone (Block-#1-#2)
2329     \dim_set:Nn \l_tmpa_dim \pgf@y
2330     \node
2331     [
2332       fit = ( #1 - #2 - medium . north-west )
2333         ( #3 - #4 - medium . south-east ) ,
2334       inner sep = 0 pt ,
2335     ]
2336   (#1-#2) { } ;

```

With the following instruction, we retrieve the *x*-value and the *y*-value of the center of the block. We will only use the *x*-value, available in `\pgf@x`.

```

2337     \tikz@parse@node \pgfutil@firstofone (#1-#2)
2338     \path (\pgf@x,\l_tmpa_dim) node [ anchor = base ] { #5 } ;
2339   \end{tikzpicture}
2340 }

```

If the number of rows is different of 1, it's necessary to create two Tikz nodes because we want the label `#5` really drawn in the *center* of the node.

```

2341   {
2342     \begin{tikzpicture}
2343     \node
2344     [
2345       fit = ( #1 - #2 - medium . north-west )
2346         ( #3 - #4 - medium . south-east ) ,
2347       inner sep = 0 pt ,
2348     ]
2349   (#1-#2) { } ;
2350   \node at (#1-#2.center) { #5 } ;
2351   \end{tikzpicture}
2352 }
2353 }
2354 }

```

We don't forget the name of the node because the user may wish to use it.

```

2349   (#1-#2) { } ;
2350   \node at (#1-#2.center) { #5 } ;
2351   \end{tikzpicture}
2352 }
2353 }
2354 }

```

## 14.17 How to draw the dotted lines transparently

```

2355 \cs_set_protected:Npn \@@_renew_matrix:
2356 {
2357   \RenewDocumentEnvironment { pmatrix } { }
2358   { \pNiceMatrix }
2359   { \endpNiceMatrix }
2360   \RenewDocumentEnvironment { vmatrix } { }
2361   { \vNiceMatrix }
2362   { \endvNiceMatrix }
2363   \RenewDocumentEnvironment { Vmatrix } { }
2364   { \VNiceMatrix }
2365   { \endVNiceMatrix }
2366   \RenewDocumentEnvironment { bmatrix } { }
2367   { \bNiceMatrix }

```

```

2368     { \endbNiceMatrix }
2369     \RenewDocumentEnvironment { Bmatrix } { }
2370     { \BNiceMatrix }
2371     { \endBNiceMatrix }
2372 }
```

## 14.18 Automatic arrays

```

2373 \cs_new_protected:Npn \@@_set_size:n #1-#2 \q_stop
2374 {
2375     \int_set:Nn \l_@@_nb_rows_int { #1 }
2376     \int_set:Nn \l_@@_nb_cols_int { #2 }
2377 }

2378 \NewDocumentCommand \AutoNiceMatrixWithDelims { m m O { } m O { } m ! O { } }
2379 {
2380     \int_zero_new:N \l_@@_nb_rows_int
2381     \int_zero_new:N \l_@@_nb_cols_int
2382     \@@_set_size:n #4 \q_stop
2383     \begin { NiceArrayWithDelims } { #1 } { #2 }
2384     { * { \l_@@_nb_cols_int } { C } } [ #3 , #5 , #7 ]
2385     \int_compare:nNnT \l_@@_first_row_int = \c_zero_int
2386     {
2387         \int_compare:nNnT \l_@@_first_col_int = \c_zero_int { & }
2388         \prg_replicate:nn { \l_@@_nb_cols_int - 1 } { & }
2389         \int_compare:nNnT \l_@@_last_col_int > { -1 } { & } \\
2390     }
2391     \prg_replicate:nn \l_@@_nb_rows_int
2392     {
2393         \int_compare:nNnT \l_@@_first_col_int = \c_zero_int { & }
2394     }
```

You put { } before #6 to avoid a hasty expansion of an eventual `\arabic{iRow}` at the beginning of the row which would result in an incorrect value of that `iRow` (since `iRow` is incremented in the first cell of the row of the `\halign`).

```

2394     \prg_replicate:nn { \l_@@_nb_cols_int - 1 } { { } #6 & } #6
2395     \int_compare:nNnT \l_@@_last_col_int > { -1 } { & } \\
2396 }
2397 \int_compare:nNnT \l_@@_last_row_int > { -2 }
2398 {
2399     \int_compare:nNnT \l_@@_first_col_int = \c_zero_int { & }
2400     \prg_replicate:nn { \l_@@_nb_cols_int - 1 } { & }
2401     \int_compare:nNnT \l_@@_last_col_int > { -1 } { & } \\
2402 }
2403 \end { NiceArrayWithDelims }
2404 }
2405 \cs_set_protected:Npn \@@_define_com:nnn #1 #2 #3
2406 {
2407     \cs_set_protected:cpx { #1 AutoNiceMatrix }
2408     {
2409         \str_gset:Nx \g_@@_type_env_str
2410         { command ~ \c_backslash_str #1 AutoNiceMatrix }
2411         \AutoNiceMatrixWithDelims { #2 } { #3 }
2412     }
2413 }
2414 \@@_define_com:nnn p ( )
2415 \@@_define_com:nnn b [ ]
2416 \@@_define_com:nnn v | |
2417 \@@_define_com:nnn V \| \|
2418 \@@_define_com:nnn B \{ \}
```

## 14.19 We process the options

We process the options when the package is loaded (with `\usepackage`) but we recommend to use `\NiceMatrixOptions` instead.

We must process these options after the definition of the environment `{NiceMatrix}` because the option `renew-matrix` executes the code `\cs_set_eq:NN \env@matrix \NiceMatrix`. Of course, the command `\NiceMatrix` must be defined before such an instruction is executed.

```

2419 \keys_define:nn { NiceMatrix / Package }
2420   {
2421     renew-dots .bool_set:N = \l_@@_renew_dots_bool ,
2422     renew-dots .value_forbidden:n = true ,
2423     renew-matrix .code:n = \@@_renew_matrix: ,
2424     renew-matrix .value_forbidden:n = true ,
2425     transparent .meta:n = { renew-dots , renew-matrix } ,
2426     transparent .value_forbidden:n = true,
2427     obsolete-environments .code:n =
2428       \@@_msg_redirect_name:nn { Obsolete-environment } { none }
2429   }
2430 \ProcessKeysOptions { NiceMatrix / Package }
```

## 14.20 Error messages of the package

```

2431 \@@_msg_new:nn { unknown-cell-for-line-in-code-after }
2432   {
2433     Your~command~\token_to_str:N\line\{#1\}\{#2\}~in~the~'code-after'~
2434     can't~be~executed~because~a~Tikz~node~doesn't~exist.\\
2435     If~you~go~on~this~command~will~be~ignored.
2436   }
2437 \@@_msg_new:nn { last-col-non-empty-for-NiceArray }
2438   {
2439     In~the~\g_@@_type_env_str,~you~must~use~the~option~
2440     'last-col'~without~value.\\
2441     However,~you~can~go~on~for~this~time~
2442     (the~value~'\l_keys_value_tl'~will~be~ignored).
2443   }
2444 \@@_msg_new:nn { last-col-empty-for-NiceMatrix }
2445   {
2446     In~the~\g_@@_type_env_str,~you~can't~use~the~option~
2447     'last-col'~without~value.~You~must~give~the~number~of~that~last~column.\\
2448     If~you~go~on~this~option~will~be~ignored.
2449   }
2450 \@@_msg_new:nn { Block-too-large }
2451   {
2452     You~try~to~draw~a~block~in~the~cell~#1-#2~of~your~matrix~but~the~matrix~is~
2453     too~small~for~that~block.\\
2454     If~you~go~on,~this~command~will~be~ignored.
2455   }
2456 \@@_msg_new:nn { Impossible-line }
2457   {
2458     A~dotted-line~can't~be~drawn~because~you~have~not~put~
2459     all~the~ampersands~required~on~the~row~#1.\\
2460     If~you~go~on,~this~dotted~line~will~be~ignored.
2461   }
2462 \@@_msg_new:nn { Wrong-last-row }
2463   {
2464     You~have~used~'last-row=\int_use:N \l_@@_last_row_int'~but~your~
2465     \g_@@_type_env_str\ seems~to~have~\int_use:N \c@iRow \ rows.~
2466     If~you~go~on,~the~value~of~\int_use:N \c@iRow \ will~be~used~for~
2467     last~row.~You~can~avoid~this~problem~by~using~'last-row'~
2468     without~value~(more~compilations~might~be~necessary).
2469   }
2470 \@@_msg_new:nn { Yet-in-env }
2471   {
2472     Environments~\{NiceArray\}~(or~\{NiceMatrix\},~etc.)~can't~be~nested.\\
```

```

2473     This~error~is~fatal.
2474 }
2475 \@@_msg_new:nn { Outside~math~mode }
2476 {
2477   The~\g_@@_type_env_str\ can~be~used~only~in~math~mode~
2478   (and~not~in~\token_to_str:N \vcenter).\\\
2479   This~error~is~fatal.
2480 }
2481 \@@_msg_new:nn { Option~Transparent~suppressed }
2482 {
2483   The~option~'Transparent'~has~been~renamed~'transparent'.\\\
2484   If~you~go~on~this~command~will~be~ignored.
2485 }
2486 \@@_msg_new:nn { Option~RenewMatrix~suppressed }
2487 {
2488   The~option~'RenewMatrix'~has~been~renamed~'renew-matrix'.\\\
2489   If~you~go~on~this~command~will~be~ignored.
2490 }
2491 \@@_msg_new:nn { Bad~value~for~letter~for~dotted~lines }
2492 {
2493   The~value~of~key~'\tl_use:N\l_keys_key_tl'~must~be~of~length~1.\\\
2494   If~you~go~on~it~will~be~ignored.
2495 }
2496 \@@_msg_new:nnn { Unknown~key~for~NiceMatrixOptions }
2497 {
2498   The~key~'\tl_use:N\l_keys_key_tl'~is~unknown~for~the~command~
2499   \token_to_str:N \NiceMatrixOptions. \\\
2500   If~you~go~on~it~will~be~ignored. \\
2501   For~a~list~of~the~available~keys,~type~H~<return>.
2502 }
2503 {
2504   The~available~options~are~(in~alphabetic~order):~  

2505   allow-duplicate-names,~  

2506   code-for-first-col,~  

2507   code-for-first-row,~  

2508   code-for-last-col,~  

2509   code-for-last-row,~  

2510   create-extra-nodes,~  

2511   create-medium-nodes,~  

2512   create-large-nodes,~  

2513   dotted-lines-margin,~  

2514   end-of-row,~  

2515   exterior-arraycolsep,~  

2516   hlines,~  

2517   left-margin,~  

2518   letter-for-dotted-lines,~  

2519   light-syntax,~  

2520   nullify-dots,~  

2521   parallelize-diags,~  

2522   renew-dots,~  

2523   renew-matrix,~  

2524   right-margin,~  

2525   small,~  

2526   and~transparent
2527 }
2528 \@@_msg_new:nnn { Unknown~option~for~NiceArray }
2529 {
2530   The~option~'\tl_use:N\l_keys_key_tl'~is~unknown~for~the~environment~
2531   \{NiceArray\}. \\
2532   If~you~go~on~it~will~be~ignored. \\
2533   For~a~list~of~the~available~options,~type~H~<return>.

```

```

2534 }
2535 {
2536 The~available~options~are~(in~alphabetic~order):~
2537 b,~
2538 c,~
2539 code-after,~
2540 code-for-first-col,~
2541 code-for-first-row,~
2542 code-for-last-col,~
2543 code-for-last-row,~
2544 columns-width,~
2545 create-extra-nodes,~
2546 create-medium-nodes,~
2547 create-large-nodes,~
2548 dotted-lines-margin,~
2549 end-of-row,~
2550 extra-left-margin,~
2551 extra-right-margin,~
2552 first-col,~
2553 first-row,~
2554 hlines,~
2555 last-col,~
2556 last-row,~
2557 left-margin,~
2558 light-syntax,~
2559 name,~
2560 nullify-dots,~
2561 parallelize-diags,~
2562 renew-dots,~
2563 right-margin,~
2564 small,~
2565 and~t.
2566 }

```

This error message is used for the set of keys `NiceMatrix/NiceMatrix` and `NiceMatrix/pNiceArray` (but not by `NiceMatrix/NiceArray` because, for this set of keys, there is also the options `t`, `c` and `b`).

```

2567 \@@_msg_new:nnn { Unknown-option-for-NiceMatrix }
2568 {
2569   The~option~'\tl_use:N\l_keys_key_tl'~is~unknown~for~the~
2570   \g_@@_type_env_str. \\
2571   If~you~go~on,~it~will~be~ignored. \\
2572   For~a~list~of~the~available~options,~type~H~<return>.
2573 }
2574 {
2575   The~available~options~are~(in~alphabetic~order):~
2576   code-after,~
2577   code-for-first-col,~
2578   code-for-first-row,~
2579   code-for-last-col,~
2580   code-for-last-row,~
2581   columns-width,~
2582   create-extra-nodes,~
2583   create-medium-nodes,~
2584   create-large-nodes,~
2585   dotted-lines-margin,~
2586   end-of-row,~
2587   extra-left-margin,~
2588   extra-right-margin,~
2589   first-col,~
2590   first-row,~
2591   hlines,~
2592   last-col,~
2593   last-row,~
2594   left-margin,~

```

```

2595 light-syntax,~  

2596 name,~  

2597 nullify-dots,~  

2598 parallelize-diags,~  

2599 renew-dots,~  

2600 right-margin,~  

2601 and~small.  

2602 }  

2603 \@@_msg_new:nnn { Duplicate~name }  

2604 {  

2605   The~name~'\l_keys_value_tl'~is~already~used~and~you~shouldn't~use~  

2606   the~same~environment~name~twice.~You~can~go~on,~but,~  

2607   maybe,~you~will~have~incorrect~results~especially~  

2608   if~you~use~'columns-width=auto'.~If~you~don't~want~to~see~this~  

2609   message~again,~use~the~option~'allow-duplicate-names'.\\  

2610   For~a~list~of~the~names~already~used,~type~H~<return>. \\  

2611 }  

2612 {  

2613   The~names~already~defined~in~this~document~are:~  

2614   \seq_use:Nnnn \g_@@_names_seq { ,~ } { ,~ } { ~and~ }.  

2615 }  

2616 \@@_msg_new:nn { Option~auto~for~columns-width }  

2617 {  

2618   You~can't~give~the~value~'auto'~to~the~option~'columns-width'~here.~  

2619   If~you~go~on,~the~option~will~be~ignored.  

2620 }  

2621 \@@_msg_new:nn { Zero~row }  

2622 {  

2623   There~is~a~problem.~Maybe~your~\g_@@_type_env_str~is~empty.~  

2624   Maybe~you~have~used~l,~c~and~r~instead~of~L,~C~and~R~in~the~preamble~  

2625   of~your~environment.~\\  

2626   If~you~go~on,~the~result~may~be~incorrect.  

2627 }  

2628 \@@_msg_new:nn { Use~of~::~in~first~position }  

2629 {  

2630   You~can't~use~the~column~specifier~'\l_@@_letter_for_dotted_lines_str'~in~the~  

2631   first~position~of~the~preamble~of~the~\g_@@_type_env_str.~\\  

2632   If~you~go~on,~this~dotted~line~will~be~ignored.  

2633 }

```

## 14.21 Obsolete environments

```

2634 \@@_msg_new:nn { Obsolete~environment }  

2635 {  

2636   The~environment~\{@currenvir\}~is~obsolete.~We~should~use~#1~instead.~  

2637   However,~you~can~go~on~for~this~time.~  

2638   If~you~don't~want~to~see~this~error~again,~you~should~load~'nicematrix'~  

2639   with~the~option~'obsolete-environments'.  

2640 }  

2641 \NewDocumentEnvironment { pNiceArrayC } { }  

2642 {  

2643   \@@_error:nn { Obsolete~environment }  

2644   { the~option~'last-col' }  

2645   \int_set:Nn \l_@@_last_col_int \c_zero_dim  

2646   \pNiceArray  

2647 }  

2648 { \endpNiceArray }  

2649 \NewDocumentEnvironment { bNiceArrayC } { }  

2650 {  

2651   \@@_error:nn { Obsolete~environment }  

2652   { the~option~'last-col' }  

2653   \int_set:Nn \l_@@_last_col_int \c_zero_dim

```

```

2654     \bNiceArray
2655   }
2656 { \endbNiceArray }

2657 \NewDocumentEnvironment { BNiceArrayC } { }
2658 {
2659     \@@_error:nn { Obsolete~environment }
2660     { the~option~'last-col' }
2661     \int_set:Nn \l_@@_last_col_int \c_zero_dim
2662     \BNiceArray
2663   }
2664 { \endBNiceArray }

2665 \NewDocumentEnvironment { vNiceArrayC } { }
2666 {
2667     \@@_error:nn { Obsolete~environment }
2668     { the~option~'last-col' }
2669     \int_set:Nn \l_@@_last_col_int \c_zero_dim
2670     \vNiceArray
2671   }
2672 { \endvNiceArray }

2673 \NewDocumentEnvironment { VNiceArrayC } { }
2674 {
2675     \@@_error:nn { Obsolete~environment }
2676     { the~option~'last-col' }
2677     \int_set:Nn \l_@@_last_col_int \c_zero_dim
2678     \VNiceArray
2679   }
2680 { \endVNiceArray }

2681 \NewDocumentEnvironment { pNiceArrayRC } { }
2682 {
2683     \@@_error:nn { Obsolete~environment }
2684     { the~options~'last-col'~and~'first-row' }
2685     \int_set:Nn \l_@@_last_col_int \c_zero_dim
2686     \int_set:Nn \l_@@_first_row_int \c_zero_int
2687     \pNiceArray
2688   }
2689 { \endpNiceArray }

2690 \NewDocumentEnvironment { bNiceArrayRC } { }
2691 {
2692     \@@_error:nn { Obsolete~environment }
2693     { the~options~'last-col'~and~'first-row' }
2694     \int_set:Nn \l_@@_last_col_int \c_zero_dim
2695     \int_set:Nn \l_@@_first_row_int \c_zero_int
2696     \bNiceArray
2697   }
2698 { \endbNiceArray }

2699 \NewDocumentEnvironment { BNiceArrayRC } { }
2700 {
2701     \@@_error:nn { Obsolete~environment }
2702     { the~options~'last-col'~and~'first-row' }
2703     \int_set:Nn \l_@@_last_col_int \c_zero_dim
2704     \int_set:Nn \l_@@_first_row_int \c_zero_int
2705     \BNiceArray
2706   }
2707 { \endBNiceArray }

2708 \NewDocumentEnvironment { vNiceArrayRC } { }
2709 {
2710     \@@_error:nn { Obsolete~environment }
2711     { the~options~'last-col'~and~'first-row' }
2712     \bool_set_true:N \l_@@_last_col_bool
2713     \int_set:Nn \l_@@_first_row_int \c_zero_int
2714     \vNiceArray

```

```

2715     }
2716     { \end{vNiceArray} }
2717 \NewDocumentEnvironment { VNiceArrayRC } { }
2718 {
2719     \@@_error:nn { Obsolete~environment }
2720     { the~options~'last-col'~and~'first-row' }
2721     \int_set:Nn \l_@@_last_col_int \c_zero_dim
2722     \int_set:Nn \l_@@_first_row_int \c_zero_int
2723     \VNiceArray
2724 }
2725 { \end{VNiceArray} }

2726 \NewDocumentEnvironment { NiceArrayCwithDelims } { }
2727 {
2728     \@@_error:nn { Obsolete~environment }
2729     { the~option~'last-col' }
2730     \int_set:Nn \l_@@_last_col_int \c_zero_dim
2731     \NiceArrayWithDelims
2732 }
2733 { \end{NiceArrayWithDelims} }

2734 \NewDocumentEnvironment { NiceArrayRCwithDelims } { }
2735 {
2736     \@@_error:nn { Obsolete~environment }
2737     { the~options~'last-col'~and~'first-row' }
2738     \int_set:Nn \l_@@_last_col_int \c_zero_dim
2739     \int_set:Nn \l_@@_first_row_int \c_zero_int
2740     \NiceArrayWithDelims
2741 }
2742 { \end{NiceArrayWithDelims} }

```

## 15 History

### Changes between versions 1.0 and 1.1

The dotted lines are no longer drawn with Tikz nodes but with Tikz circles (for efficiency). Modification of the code which is now twice faster.

### Changes between versions 1.1 and 1.2

New environment `{NiceArray}` with column types L, C and R.

### Changes between version 1.2 and 1.3

New environment `{pNiceArrayC}` and its variants.

Correction of a bug in the definition of `{BNiceMatrix}`, `{vNiceMatrix}` and `{VNiceMatrix}` (in fact, it was a typo).

Options are now available locally in `{pNiceMatrix}` and its variants.

The names of the options are changed. The old names were names in “camel style”.

### Changes between version 1.3 and 1.4

The column types w and W can now be used in the environments `{NiceArray}`, `{pNiceArrayC}` and its variants with the same meaning as in the package `array`.

New option `columns-width` to fix the same width for all the columns of the array.

## Changes between version 1.4 and 2.0

The versions 1.0 to 1.4 of `nicematrix` were focused on the continuous dotted lines whereas the version 2.0 of `nicematrix` provides different features to improve the typesetting of mathematical matrices.

## Changes between version 2.0 and 2.1

New implementation of the environment `{pNiceArrayRC}`. With this new implementation, there is no restriction on the width of the columns.

The package `nicematrix` no longer loads `mathtools` but only `amsmath`.

Creation of “medium nodes” and “large nodes”.

## Changes between version 2.1 and 2.1.1

Small corrections: for example, the option `code-for-first-row` is now available in the command `\NiceMatrixOptions`.

Following a discussion on TeX StackExchange<sup>35</sup>, Tikz externalization is now deactivated in the environments of the extension `nicematrix`.<sup>36</sup>

## Changes between version 2.1 and 2.1.2

Option `draft`: with this option, the dotted lines are not drawn (quicker).

## Changes between version 2.1.2 and 2.1.3

When searching the end of a dotted line from a command like `\Cdots` issued in the “main matrix” (not in the exterior column), the cells in the exterior column are considered as outside the matrix. That means that it’s possible to do the following matrix with only a `\Cdots` command (and a single `\Vdots`).

$$\begin{pmatrix} 0 & \overset{C_j}{\cdots} & 0 \\ 0 & \vdots & a \cdots \cdots \\ 0 & & 0 \end{pmatrix}_{L_i}$$

## Changes between version 2.1.3 and 2.1.4

Replacement of some options `0 { }` in commands and environments defined with `xparse` by `! 0 { }` (because a recent version of `xparse` introduced the specifier `!` and modified the default behaviour of the last optional arguments).

See [www.texdev.net/2018/04/21/xparse-optional-arguments-at-the-end](http://www.texdev.net/2018/04/21/xparse-optional-arguments-at-the-end)

## Changes between version 2.1.4 and 2.1.5

Compatibility with the classes `revtex4-1` and `revtex4-2`.

Option `allow-duplicate-names`.

## Changes between version 2.1.5 and 2.2

Possibility to draw horizontal dotted lines to separate rows with the command `\hdottedline` (similar to the classical command `\hline` and the command `\hdashline` of `arydshln`).

Possibility to draw vertical dotted lines to separate columns with the specifier `:` in the preamble (similar to the classical specifier `|` and the specifier `:` of `arydshln`).

<sup>35</sup>cf. [tex.stackexchange.com/questions/450841/tikz-externalize-and-nicematrix-package](https://tex.stackexchange.com/questions/450841/tikz-externalize-and-nicematrix-package)

<sup>36</sup>Before this version, there was an error when using `nicematrix` with Tikz externalization. In any case, it’s not possible to externalize the Tikz elements constructed by `nicematrix` because they use the options `overlay` and `remember picture`.

## Changes between version 2.2 and 2.2.1

Improvement of the vertical dotted lines drawn by the specifier “:” in the preamble.  
Modification of the position of the dotted lines drawn by `\hdottedline`.

## Changes between version 2.2.1 and 2.3

Compatibility with the column type S of `siunitx`.

Option `hlines`.

A warning is issued when the `draft` mode is used. In this case, the dotted lines are not drawn.

## Changes between version 2.3 and 3.0

Modification of `\Hdotsfor`. Now `\Hdotsfor` erases the `\vlines` (of “|”) as `\hdotsfor` does.  
Composition of exterior rows and columns on the four sides of the matrix (and not only on two sides) with the options `first-row`, `last-row`, `first-col` and `last-col`.

## Changes between version 3.0 and 3.1

Command `\Block` to draw block matrices.

Error message when the user gives an incorrect value for `last-row`.

A dotted line can no longer cross another dotted line (except the dotted lines drawn by `\cdottedline`, the symbol : (in the preamble of the array) and `\line` in `code-after`).

The starred versions of `\Cdots`, `\Ldots`, etc. are now deprecated because, with the new implementation, they become pointless. These starred versions are no longer documented.

The vertical rules in the matrices (drawn by |) are now compatible with the color fixed by `colortbl`.  
Correction of a bug: it was not possible to use the colon : in the preamble of an array when `pdflatex` was used with `french-babel` (because `french-babel` activates the colon in the beginning of the document).

## Changes between version 3.1 and 3.2 (and 3.2a)

Option `small`.

## Changes between version 3.2 and 3.3

The options `first-row`, `last-row`, `first-col` and `last-col` are now available in the environments `{NiceMatrix}`, `{pNiceMatrix}`, `{bNiceMatrix}`, etc.

The option `columns-width=auto` doesn't need any more a second compilation.

The options `renew-dots`, `renew-matrix` and `transparent` are now available as package options (as said in the documentation).

The previous version of `nicematrix` was incompatible with a recent version of `expl3` (released 2019/09/30). This version is compatible.

## Changes between version 3.3 and 3.4

Following a discussion on TeX StackExchange<sup>37</sup>, optimization of Tikz externalization is disabled in the environments of `nicematrix` when the class `standalone` or the package `standalone` is used.

## Changes between version 3.4 and 3.5

Correction on a bug on the two previous versions where the `code-after` was not executed.

---

<sup>37</sup>cf. [tex.stackexchange.com/questions/510841/nicematrix-and-tikz-external-optimize](https://tex.stackexchange.com/questions/510841/nicematrix-and-tikz-external-optimize)

## Changes between version 3.5 and 3.6

LaTeX counters `iRow` and `jCol` available in the cells of the array.

Addition of `\normalbaselines` before the construction of the array: in environments like `{align}` of `amsmath` the value of `\baselineskip` is changed and if the options `first-row` and `last-row` were used in an environment of `nicematrix`, the position of the delimiters was wrong.

A warning is written in the `.log` file if an obsolete environment is used.

There is no longer artificial errors `Duplicate~name` in the environments of `amsmath`.

## Changes between version 3.6 and 3.7

The four “corners” of the matrix are correctly protected against the four codes: `code-for-first-col`, `code-for-last-col`, `code-for-first-row` and `code-for-last-row`.

New command `\pAutoNiceMatrix` and its variants (suggestion of Christophe Bal).

## Changes between version 3.7 and 3.8

New programmation for the command `\Block` when the block has only one row. With this programmation, the vertical rules drawn by the specifier “`|`” at the end of the block is actually drawn. In previous versions, they were not because the block of one row was constructed with `\multicolumn`. An error is raised when an obsolete environment is used.

## Changes between version 3.8 and 3.9

New commands `\NiceMatrixLastEnv` and `\OnlyMainNiceMatrix`.

New options `create-medium-nodes` and `create-large-nodes`.

## Changes between version 3.9 and 3.10

New option `light-syntax` (and `end-of-row`).

New option `dotted-lines-margin` for fine tuning of the dotted lines.

# Index

The italic numbers denote the pages where the corresponding entry is described, numbers underlined point to the definition, all others indicate the places where it is used.

Symbols	
<code>\@commands:</code>	
<code>\@Block:</code>	508, 2290
<code>\@Block_i</code>	2291, 2292
<code>\@Block_ii:nnnn</code>	2292, 2293
<code>\@Block_iii:nnnnn</code>	2308, 2316
<code>\@Cdots</code>	500, 513, 1732
<code>\g_@_Cdots_lines_tl</code>	555, 1176
<code>\@Cell:</code>	377
<code>\@Cell:</code>	124, 292, 496, 497, 498
<code>\@Ddots</code>	502, 515, 1744
<code>\g_@_Ddots_lines_tl</code>	558, 1174
<code>\@Hdotsfor:</code>	506, 518, 1773
<code>\@Hdotsfor_i</code>	1776, 1780, 1784
<code>\g_@_Hdotsfor_lines_tl</code>	560, 1172, 1786
<code>\@Hspace:</code>	505, 1756
<code>\@Iddots</code>	503, 516, 1750
<code>\g_@_Iddots_lines_tl</code>	559, 1175
<code>\@Ldots</code>	499, 512, 517, 1726
<code>\g_@_Ldots_lines_tl</code>	556, 1177
<code>\l_@_NiceArray_bool</code>	54, 583, 609, 639, 648, 698, 987, 1912
<code>\g_@_NiceMatrixBlock_int</code>	50, 2059, 2064, 2067, 2078
<code>\@OnlyMainNiceMatrix:n</code>	509, 2042
<code>\@Vdots</code>	501, 514, 1738
<code>\g_@_Vdots_lines_tl</code>	557, 1173
<code>\@actualization_for_first_and_last_-row:</code>	319, 344, 871, 942
<code>\@actually_draw_Ldots:</code>	1388, 1391, 1832
<code>\@adapt_S_column:</code>	99, 114, 569
<code>\@add_to_empty_cells:</code>	1720, 1730, 1736, 1742, 1748, 1754, 1758
<code>\@adjust_with_col_nodes:</code>	1352, 1424, 1472
<code>\@after_array:</code>	751, 1108
<code>\@after_array_i:</code>	1111, 1117
<code>\@array:</code>	418, 754, 761
<code>\l_@_auto_columns_width_bool</code>	

..... 139, 194, 539, 790, 803, 2054  
 $\backslash\text{@@begin\_of\_row}$ : ..... 298, 312, 850  
 $\backslash\text{l\_@@block\_auto\_columns\_width\_bool}$  ..  
 ..... 580, 804, 2047, 2052, 2062, 2072  
 $\backslash\text{@@cdots}$  ..... 1716, 1735  
 $\backslash\text{@@cell\_with\_light\_syntax:n}$  .... 778, 785  
 $\text{g\_@@cells\_seq}$  ..... 774, 775, 776, 778  
 $\text{g\_@@code\_after\_tl}$  .....  
 ..... 79, 206, 546, 1188, 1189, 2306  
 $\backslash\text{l\_@@code\_for\_first\_col\_tl}$  ..... 161, 864  
 $\backslash\text{l\_@@code\_for\_first\_row\_tl}$  ..... 165, 306  
 $\backslash\text{l\_@@code\_for\_last\_col\_tl}$  ..... 163, 935  
 $\backslash\text{l\_@@code\_for\_last\_row\_tl}$  ..... 167, 309  
 $\text{g\_@@col\_total\_int}$  ..... 300, 301,  
 524, 819, 820, 920, 921, 1122, 2095, 2105, 2215  
 $\text{c\_@@colortbl\_loaded\_bool}$  .... 62, 67, 466  
 $\backslash\text{l\_@@columns\_width\_dim}$  .....  
 ..... 51, 195, 247, 540, 791, 812, 2060, 2066  
 $\backslash\text{@@computations\_for\_large\_nodes}$ : ...  
 ..... 2147, 2162, 2172  
 $\backslash\text{@@computations\_for\_medium\_nodes}$ : ..  
 ..... 2086, 2135, 2146, 2159  
 $\backslash\text{@@compute\_width\_of\_array}$ : .....  
 ..... 2151, 2165, 2167, 2241  
 $\backslash\text{@@create\_col\_node}$ : ..... 826, 833, 837  
 $\backslash\text{@@create\_large\_nodes}$ : .....  
 ..... 1160, 2141, 2143, 2152, 2170  
 $\backslash\text{@@create\_medium\_and\_large\_nodes}$ : ..  
 ..... 1157, 2140, 2153, 2156, 2168  
 $\backslash\text{@@create\_medium\_nodes}$ : .....  
 1158, 1327, 1328, 1831, 2132, 2139, 2154, 2169  
 $\backslash\text{@@create\_nodes}$ : 2137, 2149, 2161, 2164, 2211  
 $\backslash\text{@@create\_row\_of\_col\_nodes}$ : 756, 768, 786  
 $\backslash\text{@@ddots}$  ..... 1718, 1747  
 $\backslash\text{l\_@@ddots\_int}$  ..... 1147, 1549, 1550  
 $\backslash\text{@@define\_com:nnn}$  .....  
 ..... 2405, 2414, 2415, 2416, 2417, 2418  
 $\backslash\text{@@define\_env:n}$  .....  
 ... 1033, 1052, 1053, 1054, 1055, 1056, 1057  
 $\backslash\text{l\_@@delta\_x\_one\_dim}$  ..... 1149, 1552, 1562  
 $\backslash\text{l\_@@delta\_x\_two\_dim}$  ..... 1151, 1594, 1604  
 $\backslash\text{l\_@@delta\_y\_one\_dim}$  ..... 1150, 1554, 1562  
 $\backslash\text{l\_@@delta\_y\_two\_dim}$  ..... 1152, 1596, 1604  
 $\backslash\text{@@dotfill}$ : ..... 1882, 1884, 1924  
 $\backslash\text{l\_@@dotted\_lines\_margin\_dim}$  .....  
 ..... 74, 75, 155, 1646, 1657, 1665  
 $\backslash\text{@@double\_int\_eval:n}$  .... 1836, 1843, 1844  
 $\text{g\_@@dp\_ante\_last\_row\_dim}$  315, 482, 483, 716  
 $\text{g\_@@dp\_last\_row\_dim}$  .....  
 ..... 315, 316, 335, 336, 486, 487, 690, 716  
 $\text{g\_@@dp\_row\_zero\_dim}$  323, 324, 476, 477, 684  
 $\text{c\_@@draft\_bool}$  .....  
 ... 10, 11, 35, 404, 1778, 1849, 1881, 1933  
 $\backslash\text{@@draw\_Cdots:nn}$  ..... 1433  
 $\backslash\text{@@draw\_Ddots:nn}$  ..... 1528  
 $\backslash\text{@@draw\_Hdotsfor:nnn}$  ..... 1788, 1796  
 $\backslash\text{@@draw\_Iddots:nn}$  ..... 1570  
 $\backslash\text{@@draw\_Ldots:nn}$  ..... 1382  
 $\backslash\text{@@draw\_Vdots:nn}$  ..... 1481  
 $\backslash\text{@@draw\_tikz\_line:}$  .....  
 1431, 1477, 1524, 1566, 1608, 1614, 1873, 1988  
 $\backslash\text{@@end\_Cell}$ : ..... 381  
 $\backslash\text{@@end\_Cell}$ : ..... 126, 338, 496, 497, 498  
 $\backslash\text{l\_@@end\_of\_row\_tl}$  .. 151, 152, 159, 763, 764  
 $\text{g\_@@env\_int}$  ..... 49,  
 355, 387, 579, 592, 595, 799, 816, 842,  
 892, 970, 1068, 1081, 1091, 1132, 1184,  
 1254, 1315, 1338, 1344, 1357, 1361, 1370,  
 1376, 1400, 1415, 1448, 1463, 1613, 1724,  
 1859, 1861, 1905, 1906, 1942, 1974, 2107,  
 2110, 2120, 2228, 2245, 2248, 2255, 2283, 2299  
 $\backslash\text{@@error:n}$  ... 17, 239, 242, 246, 255, 258,  
 267, 269, 277, 279, 285, 290, 676, 1113, 1931  
 $\backslash\text{@@error:nn}$  .....  
 ..... 18, 201, 2643, 2651, 2659, 2667,  
 2675, 2683, 2692, 2701, 2710, 2719, 2728, 2736  
 $\backslash\text{@@error:nnn}$  ..... 19, 1876  
 $\backslash\text{@@everycr:}$  ..... 431, 471, 474  
 $\backslash\text{@@everycr_i:}$  ..... 432, 433  
 $\backslash\text{l\_@@exterior\_arraycolsep\_bool}$  .....  
 ..... 134, 243, 641, 650, 1914  
 $\backslash\text{l\_@@extra\_left\_margin\_dim}$  .....  
 ..... 149, 185, 656, 908  
 $\backslash\text{l\_@@extra\_right\_margin\_dim}$  .....  
 ..... 150, 186, 668, 956  
 $\backslash\text{@@extract\_coords:}$  ..... 2260, 2267  
 $\backslash\text{@@fatal:n}$  ..... 20, 58, 571  
 $\backslash\text{@@fatal:nn}$  ..... 21  
 $\backslash\text{l\_@@final\_i\_int}$  .....  
 ..... 1163, 1204, 1209, 1212, 1233, 1238,  
 1244, 1255, 1262, 1345, 1416, 1464, 1801, 1823  
 $\backslash\text{l\_@@final\_j\_int}$  .....  
 ..... 1164, 1205, 1210, 1218, 1224, 1234, 1238,  
 1245, 1256, 1346, 1417, 1465, 1818, 1824, 1826  
 $\backslash\text{l\_@@final\_open\_bool}$  .....  
 ..... 1166, 1211, 1215, 1221, 1227,  
 1231, 1259, 1328, 1366, 1410, 1427, 1458,  
 1475, 1496, 1509, 1543, 1585, 1637, 1652,  
 1683, 1684, 1799, 1819, 1827, 1830, 1856, 1940  
 $\backslash\text{@@find\_extremities\_of\_line:nnnn}$  ...  
 ..... 1199, 1387, 1438, 1486, 1533, 1575  
 $\backslash\text{l\_@@first\_col\_int}$  ..... 84,  
 85, 208, 283, 297, 636, 693, 795, 1916,  
 1994, 2095, 2105, 2175, 2215, 2387, 2393, 2399  
 $\backslash\text{l\_@@first\_row\_int}$  ..... 82, 83, 209,  
 287, 522, 681, 700, 1998, 2088, 2102, 2174,  
 2213, 2385, 2686, 2695, 2704, 2713, 2722, 2739  
 $\backslash\text{@@hdottedline:}$  ..... 504, 1900  
 $\backslash\text{l\_@@hlines\_bool}$  ..... 137, 170, 436  
 $\text{g\_@@ht\_last\_row\_dim}$  .....  
 ..... 317, 333, 334, 484, 485, 690  
 $\text{g\_@@ht\_row\_one\_dim}$  .. 330, 331, 480, 481, 705  
 $\text{g\_@@ht\_row\_zero\_dim}$  .....  
 ..... 325, 326, 478, 479, 684, 705  
 $\backslash\text{@@i:}$  ..... 2088, 2090,  
 2091, 2092, 2093, 2102, 2107, 2111, 2112,  
 2113, 2114, 2120, 2121, 2122, 2123, 2176,  
 2178, 2181, 2182, 2186, 2187, 2213, 2219,  
 2222, 2228, 2231, 2262, 2271, 2276, 2283, 2286  
 $\backslash\text{@@iddots}$  ..... 1719, 1753  
 $\backslash\text{l\_@@iddots\_int}$  ..... 1148, 1591, 1592  
 $\backslash\text{@@if\_not\_empty\_cell:nn}$  ..... 1058  
 $\backslash\text{@@if\_not\_empty\_cell:nnTF}$  .....  
 ..... 1238, 1298, 1809, 1823  
 $\backslash\text{l\_@@impossible\_line\_bool}$  .....  
 ..... 61, 1263, 1324, 1386, 1388,

1437, 1439, 1485, 1487, 1532, 1534, 1574, 1576  
 $\backslash l_{@@\_in\_env\_bool}$  ..... 53, 571, 572  
 $\backslash l_{@@\_initial\_i\_int}$  .....  
     .... 1161, 1202, 1269, 1272, 1293, 1299,  
     1305, 1316, 1323, 1339, 1401, 1449, 1800, 1809  
 $\backslash l_{@@\_initial\_j\_int}$  .....  
     1162, 1203, 1270, 1278, 1284, 1294, 1299,  
     1306, 1317, 1340, 1402, 1450, 1804, 1810, 1812  
 $\backslash l_{@@\_initial\_open\_bool}$  1165, 1271, 1275,  
     1281, 1287, 1291, 1320, 1327, 1354, 1395,  
     1425, 1443, 1473, 1491, 1504, 1538, 1580,  
     1635, 1682, 1798, 1805, 1813, 1830, 1855, 1939  
 $\backslash @_{instruction\_of\_type:n}$  .....  
     .... 405, 407, 1728, 1734, 1740, 1746, 1752  
 $\backslash l_{@@\_inter\_dots\_dim}$  .....  
     .... 72, 73, 1170, 1640, 1647,  
     1658, 1666, 1673, 1678, 1690, 1698, 1887, 1890  
 $\backslash @_j:$  ..... 2095, 2097,  
     2098, 2099, 2100, 2105, 2107, 2111, 2114,  
     2116, 2117, 2120, 2123, 2125, 2126, 2189,  
     2191, 2195, 2197, 2201, 2202, 2215, 2218,  
     2221, 2228, 2231, 2263, 2270, 2275, 2283, 2286  
 $\backslash l_{@@\_l\_dim}$ . 1616, 1617, 1633, 1640, 1646,  
     1657, 1665, 1673, 1678, 1690, 1691, 1698, 1699  
 $\backslash g_{@@\_large\_nodes\_bool}$  .....  
     .... 144, 463, 542, 1156, 1160, 1904  
 $\backslash l_{@@\_large\_nodes\_bool}$  ..... 143, 176, 463  
 $\backslash l_{@@\_last\_col\_bool}$  ..... 2712  
 $\backslash g_{@@\_last\_col\_found\_bool}$  .....  
     .... 91, 554, 746, 818, 918, 1123  
 $\backslash l_{@@\_last\_col\_int}$  .....  
     .... 89, 90, 268, 278, 286, 645, 1043,  
     1045, 2389, 2395, 2401, 2645, 2653, 2661,  
     2669, 2677, 2685, 2694, 2703, 2721, 2730, 2738  
 $\backslash l_{@@\_last\_row\_int}$  ..... 86, 87,  
     210, 288, 308, 440, 587, 594, 601, 670, 674,  
     677, 687, 709, 859, 861, 930, 932, 1125,  
     2002, 2009, 2017, 2027, 2034, 2045, 2397, 2464  
 $\backslash l_{@@\_last\_row\_without\_value\_bool}$  ...  
     .... 88, 589, 672, 1127  
 $\backslash g_{@@\_last\_vdotted\_col\_int}$  543, 545, 551, 553  
 $\backslash @_{ldots}$  ..... 1715, 1729  
 $\backslash g_{@@\_left\_delim\_dim}$  .... 607, 611, 623, 906  
 $\backslash l_{@@\_left\_margin\_dim}$  .....  
     .... 145, 179, 655, 907, 1922, 2206  
 $\backslash l_{@@\_letter\_for\_dotted\_lines\_str}$  ...  
     .... 254, 260, 261, 531, 532, 2630  
 $\backslash l_{@@\_light\_syntax\_bool}$  . 131, 157, 658, 663  
 $\backslash @_{line:nn}$  ..... 1187, 1838  
 $\backslash @_{line\_i:nn}$  ..... 1842, 1847  
 $\backslash @_{line\_with\_light\_syntax:n}$  .... 767, 780  
 $\backslash @_{line\_with\_light\_syntax\_i:n}$  766, 772, 783  
 $\backslash g_{@@\_max\_cell\_width\_dim}$  .....  
     .... 342, 343, 581, 808, 2053, 2079  
 $\backslash g_{@@\_medium\_nodes\_bool}$  142, 462, 1154, 2305  
 $\backslash l_{@@\_medium\_nodes\_bool}$  ..... 141, 175, 462  
 $\backslash @_{msg\_new:nn}$  ..... 22, 33,  
     2431, 2437, 2444, 2450, 2456, 2462, 2470,  
     2475, 2481, 2486, 2491, 2616, 2621, 2628, 2634  
 $\backslash @_{msg\_new:nnn}$  .. 23, 2496, 2528, 2567, 2603  
 $\backslash @_{msg\_redirect\_name:nn}$  .... 24, 249, 2428  
 $\backslash @_{multicolumn:nnn}$  ..... 507, 1762  
  
 $\backslash g_{@@\_multicolumn\_cells\_seq}$  .....  
     .... 520, 1767, 2114, 2123, 2237  
 $\backslash g_{@@\_multicolumn\_sizes\_seq}$  521, 1769, 2238  
 $\backslash l_{@@\_name\_str}$  ..... 140, 203,  
     359, 361, 391, 393, 590, 599, 602, 896, 898,  
     974, 976, 1135, 1139, 2230, 2231, 2285, 2286  
 $\backslash g_{@@\_names\_seq}$  ..... 52, 200, 202, 2614  
 $\backslash l_{@@\_nb\_cols\_int}$  .....  
     .... 2376, 2381, 2384, 2388, 2394, 2400  
 $\backslash l_{@@\_nb\_rows\_int}$  ..... 2375, 2380, 2391  
 $\backslash @_{node\_for\_multicolumn:nn}$  .... 2239, 2265  
 $\backslash l_{@@\_nullify\_dots\_bool}$  .....  
     .... 138, 174, 1729, 1735, 1741, 1747, 1753  
 $\backslash @_{old\_multicolumn}$  ..... 1761, 1764  
 $\backslash l_{@@\_parallelize\_diags\_bool}$  .....  
     .... 135, 136, 171, 1145, 1547, 1589  
 $\backslash l_{@@\_pos\_env\_str}$  .....  
     .... 132, 133, 273, 274, 275, 429, 702, 711  
 $\backslash @_{pre\_array:}$  ..... 448, 606  
 $\backslash c_{@@\_preamble\_first\_col\_tl}$  .... 637, 846  
 $\backslash c_{@@\_preamble\_last\_col\_tl}$  .... 646, 914  
 $\backslash l_{@@\_radius\_dim}$  ..... 76, 77, 1169, 1707  
 $\backslash @_{renew\_NC@rewrite@S:}$  ..... 117, 552  
 $\backslash l_{@@\_renew\_dots\_bool}$  ..... 172, 510, 2421  
 $\backslash @_{renew\_matrix:}$  ..... 237, 2355, 2423  
 $\backslash @_{renewcolumntype:nn}$  ..... 371, 528, 529  
 $\backslash @_{restore\_iRow\_jCol:}$  .... 1114, 1192, 1194  
 $\backslash @_{retrieve\_coords:nn}$  .....  
     1330, 1351, 1393, 1441, 1489, 1502, 1536, 1578  
 $\backslash c_{@@\_revtex\_bool}$  ..... 26, 28, 31, 420  
 $\backslash g_{@@\_right\_delim\_dim}$  .... 608, 612, 631, 954  
 $\backslash l_{@@\_right\_margin\_dim}$  .....  
     .... 146, 181, 667, 955, 1922, 2209  
 $\backslash g_{@@\_row\_total\_int}$  .....  
     .... 523, 1124, 1133, 1140, 2088, 2102, 2213  
 $\backslash g_{@@\_rows\_seq}$  ..... 762, 764, 765, 767  
 $\backslash l_{@@\_save\_iRow\_int}$  ..... 80, 451, 1196  
 $\backslash l_{@@\_save\_jCol\_int}$  ..... 81, 454, 1197  
 $\backslash @_{set\_size:n}$  ..... 2373, 2382  
 $\backslash c_{@@\_siunitx\_loaded\_bool}$  . 92, 96, 101, 552  
 $\backslash l_{@@\_small\_bool}$  .....  
     .... 169, 304, 457, 853, 924, 1167, 1886, 1893  
 $\backslash l_{@@\_stop\_loop\_bool}$  .....  
     1206, 1207, 1235, 1239, 1266, 1267, 1295, 1300  
 $\backslash c_{@@\_table\_collect\_begin\_tl}$  . 109, 111, 124  
 $\backslash c_{@@\_table\_print\_tl}$  ..... 112, 113, 126  
 $\backslash @_{test\_if\_math\_mode:}$  .....  
     .... 55, 570, 997, 1005, 1013, 1021, 1029  
 $\backslash l_{@@\_the\_array\_box}$  ..... 634, 654, 721, 734  
 $\backslash g_{@@\_type\_env\_str}$  ..... 78, 564,  
     566, 988, 989, 995, 996, 1003, 1004, 1011,  
     1012, 1019, 1020, 1027, 1028, 1037, 1191,  
     2409, 2439, 2446, 2465, 2477, 2570, 2623, 2631  
 $\backslash @_{vdots}$  ..... 1717, 1741  
 $\backslash @_{vdottedline:n}$  ..... 547, 1928  
 $\backslash @_{vline:}$  ..... 582, 1992  
 $\backslash @_{vline\_i:}$  .....  
     .... 68, 2003, 2010, 2018, 2028, 2035, 2040  
 $\backslash g_{@@\_width\_first\_col\_dim}$  148, 696, 872, 875  
 $\backslash g_{@@\_width\_last\_col\_dim}$  147, 748, 943, 946  
 $\backslash g_{@@\_x\_final\_dim}$  .....  
     .... 1334, 1347, 1377, 1501, 1514, 1520,

\begin{array}{l} 1522, 1553, 1561, 1595, 1603, 1623, 1672, \\ 1688, 1853, 1870, 1937, 1948, 1970, 1982, 1985 \end{array}	
\g_@@_x_initial_dim ... 1332, 1341, 1362, 1501, 1514, 1517, 1520, 1522, 1553, 1561, 1595, 1603, 1624, 1672, 1686, 1688, 1706, 1709, 1851, 1867, 1935, 1947, 1966, 1979, 1984	
\g_@@_y_final_dim 1335, 1348, 1426, 1428, 1430, 1474, 1476, 1555, 1558, 1597, 1600, 1627, 1677, 1696, 1854, 1871, 1938, 1949, 1971	
\g_@@_y_initial_dim 1333, 1342, 1426, 1428, 1429, 1474, 1476, 1555, 1560, 1597, 1602, 1628, 1677, 1694, 1696, 1706, 1710, 1852, 1868, 1936, 1951, 1957, 1958, 1967	
\\" ..... 783, 2389, 2395, 2401, 2434, 2440, 2447, 2453, 2459, 2472, 2478, 2483, 2488, 2493, 2499, 2500, 2531, 2532, 2570, 2571, 2609, 2610, 2625, 2631	
\{ ..... 1014, 2418, 2433, 2472, 2531, 2636	
\} ..... 1014, 2418, 2433, 2472, 2531, 2636	
\  ..... 1030, 2417	
\u ..... 2465, 2466, 2477, 2623	
<b>A</b>	
\array ..... 428	
\arraycolsep ..... 180, 182, 184, 460, 611, 612, 695, 733, 735, 749, 797, 800, 808, 812, 832, 834, 911, 949, 1918, 1921, 1984, 1985	
\arrayrulewidth ..... 442, 443	
\arraystretch ..... 459	
\AtBeginDocument ..... 63, 93	
\AutoNiceMatrixWithDelims ..... 2378, 2411	
<b>B</b>	
\begin{array}{l} 659, 660, 1039, 1087, 1336, 1359, \\ 1374, 1702, 1864, 1944, 1954, 1963, 1976, \\ 2134, 2145, 2158, 2243, 2297, 2327, 2342, 2383 \end{array}	
\bgroup ..... 366	
\Block ..... 508	
\BNiceArray ..... 2662, 2705	
\BNiceArray ..... 2654, 2696	
\BNiceMatrix ..... 2370	
\bNiceMatrix ..... 2367	
bool commands:	
\bool_do_until:Nn ..... 1207, 1267	
\bool_gset_eq:NN ..... 462, 463	
\bool_gset_false:N ..... 554	
\bool_gset_true:N ..... 542, 918, 1904, 2305	
\bool_if:NTF ..... 35, 101, 304, 404, 420, 436, 457, 466, 510, 552, 571, 580, 583, 609, 639, 641, 648, 650, 658, 663, 672, 698, 746, 853, 924, 1084, 1127, 1145, 1156, 1160, 1167, 1231, 1259, 1291, 1320, 1328, 1354, 1366, 1388, 1395, 1410, 1425, 1427, 1439, 1443, 1458, 1473, 1475, 1487, 1491, 1496, 1504, 1509, 1515, 1519, 1534, 1538, 1543, 1547, 1576, 1580, 1585, 1589, 1635, 1637, 1652, 1682, 1683, 1684, 1729, 1735, 1741, 1747, 1753, 1778, 1849, 1881, 1886, 1893, 1933, 2062, 2072	
\bool_if:nTF ..... 537, 788, 801, 818, 854, 925, 1123, 1154, 1327, 1728, 1734, 1740, 1746, 1752, 1830, 1857, 1910, 2318	
\bool_new:N ..... 10, 26, 53, 54, 61, 62, 88, 91, 92, 131, 134, 135, 137, 138, 139, 141, 142, 143, 144, 2047	
\bool_set:Nn ..... 1500, 1513	
\bool_set_false:N ..... 1060, 1074, 1165, 1166, 1206, 1211, 1266, 1271, 1386, 1437, 1485, 1532, 1574, 1798, 1799, 1855, 1856	
\bool_set_true:N ..... 11, 28, 31, 67, 96, 136, 194, 572, 589, 987, 1082, 1215, 1221, 1227, 1235, 1239, 1263, 1275, 1281, 1287, 1295, 1300, 1324, 1805, 1813, 1819, 1827, 1939, 1940, 2052, 2054, 2712	
\l_tmpa_bool 1060, 1074, 1082, 1084, 1500, 1519	
\l_tmpb_bool ..... 1513, 1515	
box commands:	
\box_clear_new:N ..... 634	
\box_dp:N ..... 324, 336, 477, 483, 487, 743	
\box_ht:N .. 326, 331, 334, 479, 481, 485, 742	
\box_move_down:nn ..... 713	
\box_move_up:nn ..... 704	
\box_set_dp:Nn ..... 743	
\box_set_ht:Nn ..... 742	
\box_use:N ..... 367, 399, 903, 981	
\box_use_drop:N ..... 721, 734, 744	
\box_wd:N ..... 343, 623, 631, 876, 947	
\l_tmpa_box ..... 302, 324, 326, 331, 334, 336, 343, 367, 376, 399, 617, 623, 624, 631, 724, 742, 743, 744, 851, 876, 903, 922, 947, 981	
<b>C</b>	
\Cdots ..... 500	
\cdots ..... 513, 1716	
\cleaders ..... 1888	
\coordinate ..... 799, 816, 840, 2217, 2220, 2268, 2273, 2298	
\crcr ..... 794	
cs commands:	
\cs_generate_variant:Nn 370, 1351, 2084, 2085	
\cs_gset:Npn ..... 1132, 1139, 2077, 2255	
\cs_gset:Npx ..... 1722	
\cs_gset_eq:NN ..... 114, 470	
\cs_if_exist:NTF ..... 450, 453, 573, 576, 592, 599, 1061, 1075, 1120, 1196, 1197, 1356, 1368, 1397, 1412, 1445, 1460, 1905, 1941, 1973, 2064, 2106	
\cs_if_exist_p:N ..... 1859, 1861	
\cs_if_free:NTF ..... 1065, 1251, 1312, 1384, 1435, 1483, 1530, 1572	
\cs_new:Npn ..... 431, 786, 1762, 1773, 1836, 1900, 2042, 2292, 2293	
\cs_new_protected:Nn ..... 292, 312, 338, 371, 1108, 1117, 1194, 1199, 1330, 1352, 1382, 1391, 1433, 1481, 1528, 1570, 1614, 1720, 1756, 1796, 1847, 1928, 2265	
\cs_new_protected:Npn ..... 17, 18, 19, 20, 21, 22, 23, 24, 55, 117, 319, 407, 418, 433, 448, 772, 780, 785, 837, 1033, 1838, 1992, 2086, 2132, 2143, 2156, 2172, 2211, 2241, 2260, 2316, 2373	
\cs_set:Npn ..... 425, 459, 464, 488, 1201, 1241, 1302, 1834, 1884, 2262, 2263	
\cs_set_eq:NN ..... 105, 422, 423, 424, 499, 500, 501, 502, 503, 504, 505, 506, 507, 508, 509, 512, 513, 514, 515, 516,	

\cs_set_protected:Npn .....	517, 518, 525, 526, 527, 529, 1187, 1715, 1716, 1717, 1718, 1719, 1761, 1882, 2040, 2041	
\dots .....	68, 99, 405, 582, 2139, 2140, 2152, 2153, 2168, 2169, 2170, 2355, 2405, 2407	
<b>D</b>		
\Ddots .....	502	
\ddots .....	515, 1718	
\DeclareOption .....	11, 12	
dim commands:		
\dim_abs:N .....	1101	
\dim_add:Nn .....	2207	
\dim_compare:nNnTF .....	1100, 1633	
\dim_compare_p:nNn .....	540, 791, 1501, 1514	
\dim_eval:n .....	2256	
\dim_gadd:Nn .....	1429, 1430, 1686, 1694, 1709, 1710, 1984, 1985	
\dim_gset:Nn .....	323, 325, 330, 333, 335, 342, 477, 479, 481, 483, 485, 487, 611, 612, 623, 631, 807, 811, 872, 943, 1096, 1098, 1341, 1342, 1347, 1348, 1362, 1377, 1517, 1558, 1600, 1867, 1868, 1870, 1871, 1947, 1948, 1949, 1951, 1957, 1966, 1967, 1970, 1971, 1979, 1982, 2246, 2250	
\dim_gset_eq:NN .....	315, 1426, 1428, 1474, 1476, 1522	
\dim_gzero:N .....	316, 317	
\dim_gzero_new:N .....	476, 478, 480, 482, 484, 486, 581, 607, 608, 1332, 1333, 1334, 1335, 2053	
\dim_max:nn .....	324, 326, 331, 334, 336, 343, 874, 945, 1519, 1958, 2085, 2122, 2126	
\dim_min:nn .....	1519, 2084, 2113, 2117	
\dim_new:N .....	51, 72, 74, 76, 145, 146, 147, 148, 149, 150	
\dim_ratio:nn .....	1562, 1604, 1640, 1645, 1656, 1664, 1673, 1678, 1689, 1697	
\dim_set:Nn .....	73, 75, 77, 195, 247, 370, 460, 683, 689, 1169, 1170, 1552, 1554, 1594, 1596, 1617, 1670, 1675, 1887, 1907, 2066, 2093, 2100, 2112, 2116, 2121, 2125, 2178, 2191, 2329	
\dim_set_eq:NN .....	616, 626, 1906, 2091, 2098, 2186, 2201	
\dim_sub:Nn .....	2204	
\dim_use:N .....	1623, 1624, 1627, 1628, 2079, 2181, 2182, 2194, 2196, 2218, 2219, 2221, 2222, 2270, 2271, 2275, 2276	
\dim_zero:N .....	686, 692, 2060	
\dim_zero_new:N .....	1149, 1150, 1151, 1152, 1616, 1851, 1852, 1853, 1854, 1935, 1936, 1937, 1938, 2090, 2092, 2097, 2099	
\c_max_dim .....	1951, 2091, 2093, 2098, 2100	
\g_tmpa_dim .....	807, 811, 814, 825, 831, 1096, 1101, 2246, 2256	
\l_tmpa_dim .....	683, 686, 705, 730, 742, 1670, 1709, 1906, 1907, 1921, 2329, 2338	
\g_tmpb_dim .....	1098, 1101, 2250, 2256	
\l_tmpb_dim .....	689, 692, 715, 737, 743, 1675, 1710	
\c_zero_dim .....	348, 349, 397, 540, 616, 626, 791, 883, 884, 961, 962, 1633, 2227, 2282, 2645, 2653, 2661, 2669, 2677, 2685, 2694, 2703, 2721, 2730, 2738	
<b>E</b>		
\dots .....	517	
\egroup .....	368	
else commands:		
\else: .....	57	
\end .....	664, 665, 1050, 1099, 1349, 1363, 1378, 1712, 1872, 1950, 1959, 1972, 1983, 2138, 2150, 2166, 2251, 2303, 2339, 2351, 2403	
\endarray .....	757, 769	
\endBNiceArray .....	2664, 2707	
\endbNiceArray .....	2656, 2698	
\endBNiceMatrix .....	2371	
\endbNiceMatrix .....	2368	
\endNiceArrayWithDelims .....		
992, 1000, 1008, 1016, 1024, 1032, 2733, 2742		
\endpNiceArray .....	2648, 2689	
\endpNiceMatrix .....	2359	
\endVNiceArray .....	2680, 2725	
\endvNiceArray .....	2672, 2716	
\endVNiceMatrix .....	2365	
\endvNiceMatrix .....	2362	
\everycr .....	474, 490	
exp commands:		
\exp_after:wN .....	121	
\exp_args:NNV .....	764	
\exp_args:NV .....	532, 754, 761, 766	
\exp_not:n .....	2313	
\ExplSyntaxOff .....	1143, 2081, 2258	
\ExplSyntaxOn .....	1129, 2074, 2252	
<b>F</b>		
\fi .....	204	
fi commands:		
\fii: .....	59	
fp commands:		
\fp_to_dim:n .....	1619	
<b>G</b>		
group commands:		
\group_begin: .....	103, 615, 1119	
\group_end: .....	108, 632, 1190	
<b>H</b>		
\halign .....	492, 494	
hbox commands:		
\hbox:n .....	42, 44, 46, 731	
\hbox_overlap_left:n .....	878	
\hbox_overlap_right:n .....	950, 1908	
\hbox_set:Nn .....	617, 624, 724	
\hbox_set:Nw .....	302, 376, 654, 851, 922	
\hbox_set_end: .....	341, 382, 669, 870, 941	
\hbox_to_wd:nn .....	1889, 1919	
\Hdotsfor .....	506	
\hdotsfor .....	518	
\hdottedline .....	504	
\hfil .....	529	
\hfill .....	1897	
\hrule .....	442	
\Hspace .....	505	
\hspace .....	1759	
\hss .....	529, 1894	
<b>I</b>		
\ialign .....	464, 488	

\Iddots . . . . .	503	\int_zero:N . . . . .	208, 209, 278, 283, 286, 287
\iddots . . . . .	37, 516, 1719	\int_zero_new:N . . . . .	1147, 1148, 1161, 1162, 1163, 1164, 2380, 2381
if commands:		\c_one_int . . . . .	253, 295, 297,
\if_mode_math: . . . . .	57	328, 1126, 1387, 1438, 1486, 1533, 1550, 1592	
\ifstandalone . . . . .	576	\g_tmpa_int . . . . .	817, 824, 830, 843
int commands:		\l_tmpa_int . . . . .	1639, 1643, 1654,
\int_add:Nn . . . . .	1209, 1210, 1293, 1294	1662, 1690, 1698, 1703, 1808, 1809, 1822, 1823	
\int_compare:nNnTF . . . . .	295,	\l_tmpb_int . . . . .	1680, 1692, 1700
297, 305, 306, 308, 321, 328, 438, 440, 543,		\c_zero_int . . . . .	305, 306, 321, 636,
587, 636, 645, 670, 674, 681, 687, 693, 700,		681, 693, 700, 856, 927, 1110, 1387, 1438,	
709, 795, 1043, 1078, 1110, 1125, 1212,		1486, 1916, 1930, 1994, 1996, 1998, 2000,	
1214, 1218, 1220, 1224, 1226, 1272, 1274,		2007, 2015, 2023, 2032, 2044, 2385, 2387,	
1278, 1280, 1284, 1286, 1550, 1592, 1765,		2393, 2399, 2686, 2695, 2704, 2713, 2722, 2739	
1802, 1816, 1930, 1994, 1996, 1998, 2000,		iow commands:	
2002, 2007, 2009, 2015, 2017, 2023, 2025,		\iow_now:Nn . . . . .	1129, 1130,
2027, 2032, 2034, 2044, 2045, 2295, 2325,		1137, 1143, 2074, 2075, 2081, 2252, 2253, 2258	
2385, 2387, 2389, 2393, 2395, 2397, 2399, 2401			<b>K</b>
\int_compare:nTF . . . . .	253	\kern . . . . .	46
\int_compare_p:nNn . . . . .	856,	keys commands:	
859, 861, 927, 930, 932, 1916, 2320, 2321		\keys_define:nn . . . . .	
\int_eval:n . . . . .	1045, 1768,	153, 190, 213, 235, 264, 271, 281, 2048, 2419	
1837, 2182, 2186, 2197, 2201, 2275, 2311, 2312		\l_keys_key_tl . . . . .	2493, 2498, 2530, 2569
\int_gadd:Nn . . . . .	1771	\keys_set:nn . . . . .	263, 584, 585, 1038, 2061
\int_gdecr:N . . . . .	1123	\l_keys_value_tl . . . . .	2442, 2605
\int_gincr:N . . . . .	294, 314, 579, 824, 830, 919, 2059		<b>L</b>
\int_gset:Nn . . . . .	300, 522, 553, 817, 920	\Ldots . . . . .	499
\int_gset_eq:NN . . . . .	545, 677, 1122, 1124, 1196, 1197	\ldots . . . . .	512, 1715
\int_gsub:Nn . . . . .	1126	\left . . . . .	620, 628, 727
\int_gzero:N . . . . .	435	\line . . . . .	1187, 2433
\int_gzero_new:N . . . . .	452, 455, 523, 524, 551	\lineskip . . . . .	684, 690
\int_incr:N . . . . .	1549, 1591		<b>M</b>
\int_max:nn . . . . .	301, 921	\makebox . . . . .	399
\int_new:N . . . . .	49, 50, 80, 81, 82, 84, 86, 89	math commands:	
\int_set:Nn . . . . .	83, 85, 87,	\c_math_toggle_token . . . . .	
90, 268, 594, 601, 1202, 1203, 1204, 1205,		303, 340, 619, 621, 627, 629, 657,	
1639, 1643, 1654, 1662, 1680, 1800, 1801,		666, 726, 740, 852, 869, 923, 940, 1892, 1895	
1804, 1808, 1810, 1812, 1818, 1822, 1824,		\mathinner . . . . .	39
1826, 2174, 2175, 2375, 2376, 2645, 2653,		\mkern . . . . .	41, 43, 45, 46
2661, 2669, 2677, 2685, 2686, 2694, 2695,		msg commands:	
2703, 2704, 2713, 2721, 2722, 2730, 2738, 2739		\msg_error:nn . . . . .	17
\int_set_eq:NN . . . . .	451, 454	\msg_error:nnn . . . . .	18, 1261, 1322
\int_step_inline:mn . . . . .	1952	\msg_error:nnnn . . . . .	19, 2323
\int_step_inline:nnn . . . . .	1703, 1833	\msg_fatal:nn . . . . .	20, 21
\int_step_variable:nNn . . . . .	2176, 2189	\msg_new:nn . . . . .	22
\int_step_variable:nnNn . . . . .		\msg_new:nnnn . . . . .	23
. . . . .	2088, 2095, 2102, 2104, 2213, 2215	\msg_redirect_name:nnn . . . . .	25
\int_sub:Nn . . . . .	1233, 1234, 1269, 1270	\msg_warning:nn . . . . .	36
\int_use:N . . . . .	355, 356, 357, 362, 363, 387, 388,	\multicolumn . . . . .	507, 1761, 1775, 1781, 1793
389, 394, 395, 413, 414, 547, 592, 595, 799,		\myfiledate . . . . .	7
816, 842, 843, 892, 893, 899, 970, 971, 972,		\myfileversion . . . . .	8
977, 978, 1062, 1068, 1069, 1070, 1076,			<b>N</b>
1079, 1091, 1092, 1093, 1132, 1133, 1140,		\newcolumntype . . . . .	373, 496, 497, 498, 532
1184, 1244, 1245, 1254, 1255, 1256, 1262,		\NewDocumentCommand . . . . .	262, 1726,
1305, 1306, 1315, 1316, 1317, 1323, 1338,		1732, 1738, 1744, 1750, 1780, 1784, 2290, 2378	
1339, 1340, 1344, 1345, 1346, 1357, 1361,		\NewDocumentEnvironment . . . . .	
1370, 1371, 1376, 1400, 1401, 1402, 1415,		562, 753, 759, 985, 993, 1001, 1009, 1017,	
1416, 1417, 1448, 1449, 1450, 1463, 1464,		1025, 1035, 2057, 2641, 2649, 2657, 2665,	
1465, 1613, 1723, 1724, 1768, 1789, 1790,		2673, 2681, 2690, 2699, 2708, 2717, 2726, 2734	
1859, 1861, 1905, 1906, 1942, 1969, 1974,		\NewExpandableDocumentCommand . . . . .	1612
1981, 2064, 2067, 2078, 2107, 2110, 2120,			
2208, 2228, 2245, 2248, 2249, 2255, 2283,			
2299, 2301, 2302, 2309, 2310, 2464, 2465, 2466			

\NiceArrayWithDelims .....	990, 998, 1006, 1014, 1022, 1030, 2731, 2740
\NiceMatrixLastEnv .....	1612
\NiceMatrixOptions .....	262, 2499
\noalign .....	432, 470, 1902
\node .....	352, 385, 887, 965, 2223, 2278, 2330, 2343, 2350
\normalbaselines .....	456
\nulldelimiterspace .....	616, 626
<b>O</b>	
\omit .....	795, 796, 823, 829
\OnlyMainNiceMatrix .....	509, 2041
<b>P</b>	
\path .....	1865, 2338
\pgfpathcircle .....	1705
\pgfpoint .....	1706
\pgfpointanchor .....	1095, 1097
\pgfusepath .....	1708
\phantom .....	1729, 1735, 1741, 1747, 1753
\pNiceArray .....	2646, 2687
\pNiceMatrix .....	2358
prg commands:	
\prg_do_nothing: .....	105, 114, 470, 1882
\prg_replicate:nn .....	819, 820, 1781, 1793, 2388, 2391, 2394, 2400
\prg_return_false: .....	1072, 1085, 1102
\prg_return_true: .....	1063, 1103
\prg_set_conditional:Npnn .....	1058
\ProcessKeysOptions .....	2430
\ProcessOptions .....	13
\ProvideDocumentCommand .....	37
\ProvidesExplPackage .....	5
<b>Q</b>	
quark commands:	
\q_stop .....	1836, 1843, 1844, 2260, 2267, 2291, 2292, 2373, 2382
<b>R</b>	
\raise .....	42, 44, 46
\relax .....	13, 526, 527
\renewcommand .....	119
\RenewDocumentEnvironment .....	2357, 2360, 2363, 2366, 2369
\RequirePackage .....	1, 3, 4, 14, 15, 16
\right .....	620, 628, 739
<b>S</b>	
\scriptstyle .....	304, 853, 924, 1893
seq commands:	
\seq_gclear_new:N .....	520, 521, 762, 774
\seq_gpop_left:NN .....	765, 776
\seq_gput_left:Nn .....	202, 1767, 1769
\seq_gset_split:Nnn .....	764, 775
\seq_if_in:NnTF .....	200, 2114, 2123
\seq_map_function:NN .....	767, 778
\seq_mapthread_function:NNN .....	2236
\seq_new:N .....	52
\seq_use:Nnnn .....	2614
skip commands:	
\skip_horizontal:N .....	797, 814, 825, 831, 834
\skip_horizontal:n .....	536, 655, 656, 667, 668, 695, 696, 733, 735, 748, 749, 800, 832, 904, 911, 949, 952, 1918
\skip_vertical:n .....	443, 730, 737
\c_zero_skip .....	475, 491
str commands:	
\c_backslash_str .....	2410
\c_colon_str .....	261
\str_gclear:N .....	1191
\str_gset:Nn .....	566, 989, 996, 1004, 1012, 1020, 1028, 1037, 2409
\str_if_empty:NTF .....	359, 391, 564, 590, 896, 974, 988, 995, 1003, 1011, 1019, 1027, 1135, 2230, 2285
\str_if_eq:nnTF .....	193, 245, 702, 711
\str_new:N .....	78, 132, 140, 260
\str_set:Nn .....	133, 199, 254, 273, 274, 275
\str_set_eq:NN .....	203, 261
\l_tmpa_str .....	199, 200, 202, 203
<b>T</b>	
\tabskip .....	475, 491
TEX and L <sup>A</sup> T <sub>E</sub> X 2 <sub><math>\varepsilon</math></sub> commands:	
\@acol .....	424
\@acoll .....	422
\@acolr .....	423
\@addtopreamble .....	582
\@array@array .....	426
\@arrayacol .....	422, 423, 424
\@arrayrule .....	582
\@arstrutbox .....	477, 479, 481, 483, 485, 487
\@currenvir .....	2636
\@halignto .....	425
\@height .....	442
\@ifclassloaded .....	27, 30
\@ifnextchar .....	525
\@ifpackageloaded .....	65, 95
\@mainaux .....	1129, 1130, 1137, 1143, 2074, 2075, 2081, 2252, 2253, 2258
\@temptokena .....	104, 107, 121, 123
\c@iRow ..	305, 308, 314, 321, 328, 356, 362, 388, 394, 413, 438, 440, 451, 452, 522, 674, 677, 856, 861, 893, 899, 927, 932, 971, 977, 1110, 1124, 1126, 1196, 1212, 1723, 1768, 1789, 1969, 1981, 2000, 2002, 2007, 2009, 2015, 2017, 2025, 2027, 2032, 2034, 2044, 2045, 2176, 2301, 2309, 2311, 2320, 2465, 2466
\c@jCol .....	294, 295, 301, 306, 357, 363, 389, 395, 414, 435, 454, 455, 543, 545, 547, 919, 921, 972, 978, 1122, 1123, 1197, 1224, 1284, 1371, 1376, 1723, 1768, 1771, 1790, 1816, 1952, 1996, 2023, 2189, 2208, 2249, 2302, 2310, 2312, 2321
\c@MaxMatrixCols .....	1044
\CT@arc@ .....	68
\CT@everycr .....	468
\CT@row@color .....	470
\ifmeasuring@ .....	198
\NC@find .....	105, 128
\NC@find@W .....	527
\NC@find@w .....	526
\NC@rewrite@S .....	106, 119
\new@ifnextchar .....	525
\p@ .....	42, 44, 46

\pgf@x	1096, 1098, 1341, 1347, 1362, 1377, 1867, 1870, 1947, 1948, 1966, 1970, 1979, 1982, 2117, 2126, 2246, 2250, 2338	
\pgf@y	1342, 1348, 1868, 1871, 1949, 1958, 1967, 1971, 2113, 2122, 2329	
\pgfutil@firstofone	1337, 1343, 1360, 1375, 1866, 1869, 1945, 1955, 1964, 1968, 1977, 1980, 2109, 2119, 2244, 2247, 2328, 2337	
\tikz@library@external@loaded	573, 1120	
\tikz@parse@node	1337, 1343, 1360, 1375, 1866, 1869, 1945, 1955, 1964, 1968, 1977, 1980, 2109, 2119, 2244, 2247, 2328, 2337	
tex commands:		
\tex_the:D	123	
\theiRow	450, 1196	
\thejCol	453, 1197	
\tikz	345, 384, 798, 815, 839, 880, 958	
\tikzset	575, 577, 1121, 1178, 2136, 2148, 2160, 2163	
tl commands:		
\tl_const:Nn	846, 914	
\tl_count:n	253	
\tl_gclear:N	1189	
\tl_gclear_new:N	555, 556, 557, 558, 559, 560	
\tl_gput_left:Nn	2306	
\tl_gput_right:Nn	409, 546, 1786	
\tl_gset:Nn	107, 111, 113	
\tl_if_empty:nTF	266, 276, 284, 782	
\tl_item:Nn	110, 111, 113	
\tl_new:N	79, 109, 112, 151	
\tl_put_left:Nn	637, 642	
\tl_put_right:Nn	646, 651	
\tl_set:Nn	110, 152, 635, 1088	
\tl_set_rescan:Nnn	530, 763	
\tl_use:N	2493, 2498, 2530, 2569	
\g_tmpa_tl	107, 110, 113	
\l_tmpa_tl	110, 111, 635, 637, 642, 646, 651, 754, 761, 765, 766, 776, 777, 1088, 1095, 1097	
token commands:		
\token_to_str:N	2433, 2478, 2499	
U		
\unless	198	
use commands:		
\use:N	412, 595, 602, 1079, 2067	
\use:n	1840, 2041	
\usetikzlibrary	2	
V		
\vbox	46	
\vcenter	620, 628, 728, 2478	
\Vdots	501	
\vdots	514, 1717	
\vline	68, 2040	
\VNiceArray	2678, 2723	
\vNiceArray	2670, 2714	
\VNiceMatrix	2364	
\vNiceMatrix	2361	

## Contents

<b>1</b>	<b>Presentation</b>	<b>1</b>
<b>2</b>	<b>The environments of this extension</b>	<b>2</b>
<b>3</b>	<b>The continuous dotted lines</b>	<b>2</b>
3.1	The option nullify-dots	3
3.2	The command \Hdotsfor	4
3.3	How to generate the continuous dotted lines transparently	5
3.4	Fine tuning of the dotted lines	5
<b>4</b>	<b>The Tikz nodes created by nicematrix</b>	<b>5</b>
<b>5</b>	<b>The code-after</b>	<b>7</b>
<b>6</b>	<b>The environment {NiceArray}</b>	<b>7</b>
<b>7</b>	<b>The exterior rows and columns</b>	<b>8</b>
<b>8</b>	<b>The dotted lines to separate rows or columns</b>	<b>9</b>
<b>9</b>	<b>The width of the columns</b>	<b>10</b>
<b>10</b>	<b>Block matrices</b>	<b>11</b>

<b>11</b>	<b>Advanced features</b>	<b>12</b>
11.1	The option <code>small</code> . . . . .	12
11.2	The counters <code>iRow</code> and <code>jCol</code> . . . . .	12
11.3	The option <code>hlines</code> . . . . .	13
11.4	The option <code>light-syntax</code> . . . . .	13
11.5	Utilisation of the column type <code>S</code> of <code>siunitx</code> . . . . .	14
<b>12</b>	<b>Technical remarks</b>	<b>14</b>
12.1	Definition of new column types . . . . .	14
12.2	Intersections of dotted lines . . . . .	14
12.3	The names of the Tikz nodes created by <code>nicematrix</code> . . . . .	15
12.4	Diagonal lines . . . . .	15
12.5	The “empty” cells . . . . .	16
12.6	The option <code>exterior-arraycolsep</code> . . . . .	16
12.7	The class option <code>draft</code> . . . . .	16
12.8	A technical problem with the argument of <code>\backslash</code> . . . . .	17
12.9	Obsolete environments . . . . .	17
<b>13</b>	<b>Examples</b>	<b>17</b>
13.1	Dotted lines . . . . .	17
13.2	Width of the columns . . . . .	19
13.3	How to highlight cells of the matrix . . . . .	20
13.4	Direct utilisation of the Tikz nodes . . . . .	23
<b>14</b>	<b>Implementation</b>	<b>24</b>
14.1	Declaration of the package and extensions loaded . . . . .	24
14.2	Technical definitions . . . . .	25
14.2.1	Variables for the exterior rows and columns . . . . .	27
14.2.2	The column <code>S</code> of <code>siunitx</code> . . . . .	28
14.3	The options . . . . .	30
14.4	Important code used by <code>{NiceArrayWithDelims}</code> . . . . .	34
14.5	The environment <code>{NiceArrayWithDelims}</code> . . . . .	41
14.6	The environment <code>{NiceMatrix}</code> and its variants . . . . .	51
14.7	How to know whether a cell is “empty” . . . . .	51
14.8	After the construction of the array . . . . .	53
14.9	The actual instructions for drawing the dotted line with Tikz . . . . .	64
14.10	User commands available in the new environments . . . . .	66
14.11	The command <code>\line</code> accessible in code-after . . . . .	68
14.12	The commands to draw dotted lines to separate columns and rows . . . . .	69
14.13	The vertical rules . . . . .	72
14.14	The environment <code>{NiceMatrixBlock}</code> . . . . .	73
14.15	The extra nodes . . . . .	74
14.16	Block matrices . . . . .	79
14.17	How to draw the dotted lines transparently . . . . .	80
14.18	Automatic arrays . . . . .	81
14.19	We process the options . . . . .	81
14.20	Error messages of the package . . . . .	82
14.21	Obsolete environments . . . . .	85
<b>15</b>	<b>History</b>	<b>87</b>
<b>Index</b>		<b>90</b>