

The `zref` package

Heiko Oberdiek
<heiko.oberdiek at googlemail.com>

2010/04/17 v2.12

Abstract

Package `zref` tries to get rid of the restriction in L^AT_EX's reference system that only two properties are supported. The package implements an extensible referencing system, where properties are handled in a more flexible way. It offers an interface for macro programmers for the access to the system and some applications that uses the new reference scheme.

Contents

1	Introduction	3
1.1	Standard L ^A T _E X behaviour	3
1.2	Basic idea	4
1.3	Interfaces	4
2	Interface for programmers	4
2.1	Entities	5
2.2	Property list	5
2.3	Property	6
2.4	Reference generation	6
2.5	Data extraction	7
2.6	Setup	7
2.7	Declared properties	8
2.8	Wrapper for advanced situations	8
2.9	Counter for unique names	8
3	User interface	9
3.1	Module user	9
3.2	Module <code>abspage</code>	10
3.3	Module <code>lastpage</code>	10
3.3.1	Tests for last page	10
3.3.2	Example	10
3.4	Module <code>thepage</code>	11
3.5	Module <code>nextpage</code>	12
3.5.1	Configuration	12
3.5.2	Example	12
3.6	Module <code>totpages</code>	13
3.7	Module <code>marks</code>	13
3.8	Module <code>runs</code>	13
3.9	Module <code>perpage</code>	13
3.10	Module <code>counter</code>	14
3.11	Module <code>titleref</code>	14
3.12	Module <code>savepos</code>	15
3.13	Module <code>dotfill</code>	15
3.14	Module <code>xr</code>	16

4	ToDo	16
5	Example	17
6	Implementation	19
6.1	Package <code>zref</code>	19
6.1.1	Identification	19
6.1.2	Load basic module	19
6.1.3	Process options	19
6.2	Module <code>base</code>	20
6.2.1	Prefixes	20
6.2.2	Identification	20
6.2.3	Utilities	20
6.2.4	Check for ε - <code>TeX</code>	21
6.2.5	Auxiliary file stuff	21
6.2.6	Property lists	21
6.2.7	Properties	23
6.2.8	Reference generation	24
6.2.9	Reference querying and extracting	26
6.2.10	Compatibility with <code>babel</code>	28
6.2.11	Unique counter support	28
6.2.12	Utilities	29
6.2.13	Setup	29
6.3	Module <code>user</code>	30
6.4	Module <code>abspage</code>	30
6.5	Module <code>counter</code>	31
6.6	Module <code>lastpage</code>	31
6.7	Module <code>thepage</code>	32
6.8	Module <code>nextpage</code>	33
6.9	Module <code>totpages</code>	34
6.10	Module <code>marks</code>	35
6.11	Module <code>runs</code>	36
6.12	Module <code>perpage</code>	37
6.13	Module <code>titleref</code>	38
6.13.1	Implementation	38
6.13.2	User interface	40
6.13.3	Patches for section and caption commands	40
6.13.4	Class <code>memoir</code>	41
6.13.5	Class <code>beamer</code>	42
6.13.6	Package <code>titlesec</code>	42
6.13.7	Package <code>longtable</code>	42
6.13.8	Package <code>listings</code>	43
6.13.9	Theorems	43
6.14	Module <code>xr</code>	43
6.15	Module <code>hyperref</code>	50
6.16	Module <code>savepos</code>	50
6.16.1	Identification	50
6.16.2	Availability	50
6.16.3	Setup	51
6.16.4	User macros	51
6.17	Module <code>dotfill</code>	51
7	Test	52
7.1	<code>\zref@localaddprop</code>	52
7.2	Module <code>runs</code>	53
7.3	Module <code>titleref</code>	53

8 Installation	54
8.1 Download	54
8.2 Bundle installation	55
8.3 Package installation	55
8.4 Refresh file name databases	55
8.5 Some details for the interested	55
9 References	56
10 History	56
[2006/02/20 v1.0]	56
[2006/05/03 v1.1]	57
[2006/05/25 v1.2]	57
[2006/09/08 v1.3]	57
[2007/01/23 v1.4]	57
[2007/02/18 v1.5]	57
[2007/04/06 v1.6]	57
[2007/04/17 v1.7]	57
[2007/04/22 v1.8]	57
[2007/05/02 v1.9]	57
[2007/05/06 v2.0]	57
[2007/05/28 v2.1]	57
[2008/09/21 v2.2]	58
[2008/10/01 v2.3]	58
[2009/08/07 v2.4]	58
[2009/12/06 v2.5]	58
[2009/12/07 v2.6]	58
[2009/12/08 v2.7]	58
[2010/03/26 v2.8]	58
[2010/03/29 v2.9]	58
[2010/04/08 v2.10]	58
[2010/04/15 v2.11]	58
[2010/04/17 v2.12]	59
11 Index	59

1 Introduction

Standard L^AT_EX's reference system with \label, \ref, and \pageref supports two properties, the appearance of the counter that is last incremented by \refstepcounter and the page with the \label command.

Unhappily L^AT_EX does not provide an interface for adding another properties. Packages such as hyperref, nameref, or titleref are forced to use ugly hacks to extend the reference system. These ugly hacks are one of the causes for hyperref's difficulty regarding compatibility with other packages.

1.1 Standard L^AT_EX behaviour

References are created by the \label command:

```
\chapter{Second chapter}
\section{First section on page 7} % section 2.1
\label{myref}
```

Now L^AT_EX records the section number 2.1 and the page 7 in the reference. Internally the reference is a list with two entries:

```
\r@myref → {2.1}{7}
```

The length of the list is fixed in the L^AT_EX kernel. An interface for adding new properties is missing.

There are several tries to add new properties:

hyperref uses a list of five properties instead of the standard list with two entries.
This causes many compatibility problems with L^AT_EX and other packages.

titleref stores its title data into the first entry in the list. L^AT_EX is happy because it does only see its list with two entries. The situation becomes more difficult, if more properties are added this way. Then the macros form a nested structure inside the first reference argument for the label. Expandable extractions will then become painful.

1.2 Basic idea

Some time ago Morten Høgholm sent me an experimental cross referencing mechanism as “expl3” code. His idea is:

```
\g_xref_mylabel plist →  
  \xref_dance_key{salsa}\xref_name_key{Morten}...
```

The entries have the following format:

```
\xref_{your key}_key{some text}
```

This approach is much more flexible:

- New properties can easily be added, just use a new key.
- The length of the list is not fixed. A reference can use a subset of the keys.
- The order of the entries does not matter.

Unhappily I am not familiar with the experimental code for L^AT_EX3 that will need some time before its first release. Thus I have implemented it as L^AT_EX 2_E package without disturbing the existing L^AT_EX reference system.

1.3 Interfaces

The package provides a generic *interface for programmers*. Commands of this interface are prefixed by `\zref@`.

Option `user` enables the *user interface*. Here the commands are prefixed by `\z` to avoid name clashes with existing macros.

Then the package provides some *modules*. They are applications for the reference system and can also be considered as examples how to use the reference system.

The modules can be loaded as packages. The package name is prefixed with `zref-`, for example:

```
\RequirePackage{zref-abspage}
```

This is the preferred way if the package is loaded from within other packages to avoid option clashes.

As alternative package `zref` can be used and the modules are given as options:

```
\usepackage[perpage,user]{zref}
```

2 Interface for programmers

The user interface is described in the next section 3.

2.1 Entities

Reference. Internally a reference is a list of key value pairs:

```
\Z@R@myref → \default{2.1}\page{7}
```

The generic format of a entry is:

```
\Z@R@⟨refname⟩ → \⟨propname⟩{⟨value⟩}
```

⟨refname⟩ is the name that denoted references (the name used in \label and \ref). ⟨propname⟩ is the name of the property or key. The property key macro is never executed, it is used in parameter text matching only.

Property. Because the name of a property is used in a macro name that must survive the .aux file, the name is restricted to letters and '@'.

Property list. Often references are used for special purposes. Thus it saves memory if just the properties are used in this reference that are necessary for its purpose.

Therefore this package uses the concept of *property lists*. A property list is a set of properties. The set of properties that is used by the default \label command is the *main property list*.

2.2 Property list

^{exp} means that the implementation of the marked macro is expandable.

```
\zref@newlist {⟨listname⟩}
```

Declares a new empty property list.

```
\zref@addprop {⟨listname⟩} {⟨propname⟩}
```

Adds the property ⟨propname⟩ to the property list ⟨listname⟩. The property and list must exist.

```
\zref@localaddprop {⟨listname⟩} {⟨propname⟩}
```

Local variant of \zref@addprop.

```
\zref@listexists {⟨listname⟩} {⟨then⟩}
```

Executes ⟨then⟩ if the property list ⟨listname⟩ exists or raise an error otherwise.

```
\zref@iflistundefinedexp {⟨listname⟩} {⟨then⟩} {⟨else⟩}
```

Executes ⟨then⟩ if the list exists or ⟨else⟩ otherwise.

```
\zref@iflistcontainsprop {⟨listname⟩} {⟨propname⟩} {⟨then⟩} {⟨else⟩}
```

Executes ⟨then⟩ if the property ⟨propname⟩ is part of property list ⟨listname⟩ or otherwise it runs the ⟨else⟩ part.

2.3 Property

```
\zref@newprop* {\⟨propname⟩} [⟨default⟩] {\⟨value⟩}
```

This command declares and configures a new property with name *⟨propname⟩*.

In case of unknown references or the property does not exist in the reference, the *⟨default⟩* is used as value. If it is not specified here, a global default is used, see `\zref@setdefault`.

The correct values of some properties are not known immediately but at page shipout time. Prominent example is the page number. These properties are declared with the star form of the command.

```
\zref@setcurrent {\⟨propname⟩} {\⟨value⟩}
```

This sets the current value of the property *⟨propname⟩*. It is a generalization of setting L^AT_EX's `\currentlabel`.

```
\zref@getcurrent {\⟨propname⟩} {\⟨value⟩}
```

This returns the current value of the property *⟨propname⟩*. The value may not be correct, especially if the property is bound to a page (start form of `\zref@newprop`) and the right value is only known at shipout time (e.g. property 'page').

```
\zref@propexists {\⟨propname⟩} {\⟨then⟩}
```

Calls *⟨then⟩* if the property *⟨propname⟩* is available or generates an error message otherwise.

```
\zref@ifpropundefinedexp {\⟨propname⟩} {\⟨then⟩} {\⟨else⟩}
```

Calls *⟨then⟩* or *⟨else⟩* depending on the existence of property *⟨propname⟩*.

2.4 Reference generation

```
\zref@label {\⟨refname⟩}
```

This works similar to `\label`. The reference *⟨refname⟩* is created and put into the `.aux` file with the properties of the main property list.

```
\zref@labelbylist {\⟨refname⟩} {\⟨listname⟩}
```

Same as `\zref@label` except that the properties are taken from the specified property list *⟨listname⟩*.

```
\zref@labelbyprops {\⟨refname⟩} {\⟨propnameA⟩,⟨propnameB⟩,...}
```

Same as `\zref@label` except that these properties are used that are given as comma separated list in the second argument.

```
\zref@newlabel {\⟨refname⟩} {...}
```

This is the macro that is used in the `.aux` file. It is basically the same as `\newlabel` apart from the format of the data in the second argument.

2.5 Data extraction

```
\zref@extractdefaultexp {\<refname>} {\<propname>} {\<default>}
```

This is the basic command that references the value of a property *<propname>* for the reference *<refname>*. In case of errors such as undefined reference the *<default>* is used instead.

```
\zref@extractexp {\<refname>} {\<propname>}
```

The command is an abbreviation for `\zref@extractdefault`. As default the default of the property is taken, otherwise the global default.

Example for page references:

LATEX: \pageref{foobar}
zref: \zref@extract{foobar}{page}

Both `\zref@extract` and `\zref@extractdefault` are expandable. That means, these macros can directly be used in expandable calculations, see the example file. On the other side, babel's shorthands are not supported, there are no warnings in case of undefined references.

If an user interface doesn't need expandable macros then it can use `\zref@refused` and `\zref@wrapper@babel` for its user macros.

```
\zref@refused {\<refname>}
```

This command is not expandable. It causes the warnings if the reference *<refname>* is not defined. Use the `\zref@extract` commands inside expandable contexts and mark their use outside by `\zref@refused`, see the example file.

```
\zref@ifrefundefinedexp {\<refname>} {\<then>} {\<else>}
```

A possibility to check whether a reference exists.

```
\zifrefundefined {\<refname>} {\<then>} {\<else>}
```

Macro `\zifrefundefined` calls `\ref@refused` before executing `\zref@ifrefundefined`. Babel shorthands are supported in *<refname>*.

```
\zref@ifrefcontainspropexp {\<refname>} {\<propname>} {\<then>} {\<else>}
```

Test whether a reference provides a property.

2.6 Setup

```
\zref@default
```

Holds the global default for unknown values.

```
\zref@setdefault {\<value>}
```

Sets the global default for unknown values. The global default is used, if a property does not specify an own default and the value for a property cannot be extracted. This can happen if the reference is unknown or the reference does not have the property.

```
\zref@setmainlist {\langle value\rangle}
```

Sets the name of the main property list. The package sets and uses `main`.

2.7 Declared properties

Module	Property	Property list	Default
	<code>default</code>	<code>main</code>	<code><empty></code>
	<code>page</code>	<code>main</code>	<code><empty></code>
<code>abspage, totpages</code>	<code>abspage</code>	<code>main</code>	0
<code>perpage</code>	<code>pagevalue</code>	<code>perpage</code>	0
	<code>page</code>	<code>perpage</code>	<code><empty></code>
	<code>abspage</code>	<code>perpage</code>	0
<code>counter</code>	<code>counter</code>	<code>main</code>	<code><empty></code>
<code>titleref</code>	<code>title</code>	<code>main</code>	<code><empty></code>
<code>savepos</code>	<code>posx</code>	<code>savepos</code>	0
	<code>posy</code>	<code>savepos</code>	0
<code>hyperref</code>	<code>anchor</code>	<code>main</code>	<code><empty></code>
	<code>url</code>		<code><empty></code>
<code>xr</code>	<code>url</code>		<code><empty></code>

2.8 Wrapper for advanced situations

```
\zref@wrapper@babel {...} {\langle name\rangle}
```

This macro helps to add shorthand support. The second argument is protected, then the code of the first argument is called with the protected name appended. Examples are in the sources.

```
\zref@wrapper@immediate {...}
```

There are situations where a label must be written instantly to the `.aux` file, for example after the last page. If the `\zlabel` or `\label` command is put inside this wrapper, immediate writing is enabled. See the implementation for module `lastpage` for an example of its use.

```
\zref@wrapper@unexpanded {...}
```

Assuming someone wants to extract a value for property `bar` and store the result in a macro `\foo` without traces of the expanding macros and without expanding the value. This (theoretical?) problem can be solved by this wrapper:

```
\edef\foo{%
  \zref@wrapper@unexpanded{%
    \zref@extract{someref}{bar}%
  }%
}
```

The `\edef` forces the expansion of `\zref@extract`, but the extraction of the value is prevented by the wrapper that uses ε -TEX' `\unexpanded` for this purpose.

2.9 Counter for unique names

Some modules (`titleref` and `dotfillmin`) need unique names for automatically generated label names.

```
\zref@require@unique
```

This command creates the unique counter `zref@unique` if the counter does not already exist.

```
\thezref@unique
```

This command is used to generate unique label names.

3 User interface

3.1 Module user

The user interface for this package and its modules is enabled by `zref`'s package option `user` or package `zref-user`. The names of user commands are prefixed by `z` in order to avoid name clashes with existing macros of the same functionality. Thus the package does not disturb the traditional reference scheme, both can be used together.

The syntax descriptions contain the following markers that are intended as hints for programmers:

- | | |
|--------|--|
| babel | Babel shorthands are allowed. |
| robust | Robust macro. |
| exp | Expandable version: <ul style="list-style-type: none">• robust, unless the extracted values are fragile,• no babel shorthand support. |

The basic user interface of the package without modules are commands that mimic the standard L^AT_EX behaviour of `\label`, `\ref`, and `\pageref`:

```
\zlabel {\langle refname \rangle}^babel
```

Similar to `\label`. It generates a label with name `\langle refname \rangle` in the new reference scheme.

```
\zref [⟨propname⟩] {\langle refname \rangle}^babel
```

Without optional argument similar to `\ref`, it returns the default reference property. This property is named `default`:

```
\zref{x} ≡ \zref[default]{x}
```

```
\zpageref {\langle refname \rangle}^babel
```

Convenience macro, similar to `\pageref`.

```
\zpageref{x} ≡ \zref[page]{x}
```

```
\zrefused {\langle refname \rangle}^babel
```

Some of the user commands in the modules are expandable. The use of such commands do not cause any undefined reference warnings, because inside of expandable contexts this is not possible. However, if there is a place outside of expandable contexts, `\refused` is strongly recommended. The reference `\langle refname \rangle` is marked as used, undefined ones will generate warnings.

3.2 Module **abspage**

With the help of package `atbegshi` a new counter `abspage` with absolute page numbers is provided. Also a new property `abspage` is defined and added to the main property list. Thus you can reference the absolute page number:

```
Section \zref{foo} is on page \zpageref{foo}.
This is page \zref[abspage]{foo} of \zref[abspage]{LastPage}.
```

The example also makes use of module `lastpage`.

3.3 Module **lastpage**

Provides the functionality of package `lastpage` [3] in the new reference scheme. The label `LastPage` is put at the end of the document. You can refer the last page number with:

```
\zref@extract{LastPage}{page} (+ \zref@refused{LastPage})
```

or

```
\zpageref{LastPage} (module user)
```

Since version 2008/10/01 v2.3 the module defines the list `LastPage`. In addition to the properties of the main list label `LastPage` also stores the properties of this list `LastPage`. The default of this list is empty. The list can be used by the user to add additional properties for label `LastPage`.

3.3.1 Tests for last page

Since version 2010/03/26 v2.8 the macros `\zref@iflastpage` and `\ziflastpage` were added. They test the reference, whether it is a reference of the last page.

```
\zref@iflastpageexp {\<refname>} {\<then>} {\<else>}
```

Macro `\zref@iflastpage` compares the references `\<refname>` with `\<LastPage>`. Basis of the comparison is the value of property `abspage`, because the values are different for different pages. This is not ensured by property `page`. Therefore module `abspage` is loaded by module `lastpage`. If both values of property `abspage` are present and match, then `\<then>` is executed, otherwise code `\<else>` is called. If one or both references are undefined or lack the property `abspage`, then `\<else>` is executed.

Macro `\zref@iflastpage` is expandable, therefore `\zref@refused` should be called on `\<refname>` and `\<LastPage>`.

```
\ziflastpage {\<refname>} {\<then>} {\<else>}
```

Macro `\ziflastpage` has the same function as `\zref@iflastpage`, but adds support for babel shorthands in `\<refname>` and calls `\zref@refused`. However macro `\ziflastpage` is not expandable.

3.3.2 Example

```
1 {*example-lastpage}
2 %<<END_EXAMPLE
3 \NeedsTeXFormat{LaTeX2e}
4 \documentclass{report}
5
6 \newcounter{foo}
7 \renewcommand*\thefoo{\Alph{foo}}
```

```

8
9 \usepackage{zref-lastpage,zref-user}[2010/04/17]
10
11 \makeatletter
12 \zref@newprop{thefoo}{\thefoo}
13 \zref@newprop{valuefoo}{\the\value{foo}}
14 \zref@newprop{chapter}{\thechapter}
15 \zref@addprop{LastPage}{thefoo}
16 \zref@addprop{LastPage}{valuefoo}
17 \zref@addprop{LastPage}{chapter}
18 \makeatother
19
20 \newcommand*\foo{%
21   \stepcounter{foo}%
22   [Current foo: \thefoo]%
23 }
24
25 \begin{document}
26   \chapter{First chapter}
27   Last page is \zref{LastPage}.\\
28   Last chapter is \zref[chapter]{LastPage}.\\
29   Last foo is \zref[thefoo]{LastPage}.\\
30   Last value of foo is \zref[valuefoo]{LastPage}.\\
31   \foo
32   \chapter{Second chapter}
33   \foo\foo\foo
34   \chapter{Last chapter}
35   \foo
36 \end{document}
37 %END_EXAMPLE
38 </example-lastpage>

```

3.4 Module `thepage`

This module `thepage` loads module `abspage`, constructs a reference name using the absolute page number and remembers property `page`. Other properties can be added by adding them to the property list `thepage`.

`\zthepage {\langle absolute page number\rangle}`

Macro `\zthepage` is basically a `\zpageref`. The reference name is yield by the `\langle absolute page number\rangle`. If the reference is not defined, then the default for property `page` is used.

`\zref@thepage@nameexp {\langle absolute page number\rangle}`

Macro `\zref@thepage@name` returns the internal reference name that is constructed using the `\langle absolute page number\rangle`. The internal reference name should not be used directly, because it might change in future versions.

`\zref@thepageexp {\langle absolute page number\rangle}`
`\zref@thepage@refused {\langle absolute page number\rangle}`

Macro `\zref@thepage` returns the page number (`\thepage`) of `\langle absolute page number\rangle`. Because this macro is expandable, `\zref@thepage@refused` is used outside an expandable context to mark the reference as used.

3.5 Module `nextpage`

```
\znextpage
```

Macro `\znextpage` prints `\thepage` of the following page. It gets the current absolute page number by using a label. There are three cases for the next page:

1. The next page is not known yet because of undefined references. Then `\zunknnownnextpagename` is used instead. The default for this macro is the default of property `page`.
2. This page is the last page. Then `\znonextpagename` is used. Its default is empty.
3. The next page is known, then `\thepage` of the next page is used (the value of property `page` of the next page).

3.5.1 Configuration

The behaviour can be configured by the following macros.

```
\zunknnownnextpagename  
\znonextpagename
```

If the next page is not known or available, then `\znextpage` uses these name macros as default. `\zunknnownnextpagename` is used in case of undefined references. Default is the value of property `page` of the next page (`\thepage`). Module `thepage` is used.

Macro `\znonextpagename` is used, if the next page does not exists. That means that the current page is last page. The default is empty.

```
\znextpagesetup {\{unknown\}} {\{no next\}} {\{next\}}
```

According to the case (see `\znextpage`) macro `\znextpage` calls an internal macro with an argument. The argument is either `\thepage` of the next page or one of `\zunknnownnextpagename` or `\znonextpagename`. These internal macro can be changed by `\znextpagesetup`. It expects the definition texts for these three cases of a macro with one argument. The default is

```
\znextpagesetup{\#1}{\#1}{\#1}
```

3.5.2 Example

```
39 <*example-nextpage>  
40 %<<END_EXAMPLE  
41 \documentclass{book}  
42  
43 \usepackage{zref-nextpage}[2010/04/17]  
44 \znextpagesetup  
45 {\thepage}% next page is unknown  
46 {\thepage\ (#1)}% this page is last page  
47 {\thepage\ $\rightarrow$ #1}% next page is known  
48 \renewcommand*\znonextpagename{last page}  
49  
50 \usepackage{fancyhdr}  
51 \pagestyle{fancy}  
52 \fancyhf{}  
53 \fancyhead[LE,RO]{\znextpage}  
54 \fancypagestyle{plain}{%  
55 \fancyhf{}%}
```

```

56 \fancyhead[LE,RO]{\znextpage}%
57 }
58
59 \begin{document}
60 \frontmatter
61 \tableofcontents
62 \mainmatter
63 \chapter{Hello World}
64 \clearpage
65 \section{Last section}
66 \end{document}
67 %END_EXAMPLE
68 </example-nextpage>

```

3.6 Module **totpages**

For the total number of pages of a document you need to know the absolute page number of the last page. Both modules `abspage` and `lastpage` are necessary and automatically enabled.

`\ztotpagesexp`

Prints the total number of pages or 0 if this number is not yet known. It expands to an explicit number and can also be used even in expandable calculations (`\numexpr`) or counter assignments.

3.7 Module **marks**

To Do.

3.8 Module **runs**

Module `runs` counts the L^AT_EX runs since last `.aux` file creation and prints the number in the `.log` file.

`\zrunsexp`

Prints the the total number of L^AT_EX runs including the current one. It expands to an explicit number. Before `begin{document}` the value is zero meaning the `.aux` file is not read yet. If a previous `.aux` file exists, the value found there increased by one is the new number. Otherwise `\zruns` is set to one. L^AT_EX runs where the `.aux` files are not rewritten are not counted (see `\nofiles`).

3.9 Module **perpage**

With `\caddtoreset` or `\numberwithin` a counter can be reset if another counter is incremented. This does not work well if the other counter is the page counter. The page counter is incremented in the output routine that is often called asynchronous somewhere on the next page. A reference mechanism costs at least two L^AT_EX runs, but ensures correct page counter values.

`\zmakeperpage [<reset>] {<counter>}`

At the of a new page counter `<counter>` starts counting with value `<reset>` (default is 1). The macro has the same syntax and semantics as `\MakePerPage` of package `perpage` [5]. Also `perpage` of package `footmisc` [1] can easily be simulated by

```
\zmakeperpage{footnote} % \usepackage[perpage]{footmisc}
```

If footnote symbols are used, some people dislike the first symbol †. It can easily be skipped:

```
\zmakeperpage[2]{footnote}
```

```
\thezpage  
counter zpage
```

If the formatted counter value of the counter that is reset at a new page contains the page value, then you can use `\thezpage`, the page number of the current page. Or counter `zpage` can be used, if the page number should be formatted differently from the current page number. Example:

```
\newcounter{foobar}  
\zmakeperpage{foobar}  
\renewcommand*{\thefoobar}{\thezpage-\arabic{foobar}}  
% or  
\renewcommand*{\thefoobar}{\roman{zpage}-\arabic{foobar}}
```

```
\zunmakeperpage {\langle counter\rangle}
```

The reset mechanism for this counter is deactivated.

3.10 Module counter

This option just add the property `counter` to the main property list. The property stores the counter name, that was responsible for the reference. This is the property `hyperref`'s `\autoref` feature uses. Thus this property `counter` may be useful for a reimplementation of the autoref feature, see the section 4 with the todo list.

3.11 Module titleref

This option makes section and caption titles available to the reference system similar to packages `titleref` or `nameref`.

```
\ztitleref {\langle refname\rangle}^babel
```

Print the section or caption title of reference `\langle refname\rangle`, similar to `\nameref` or `\titleref`.

```
\ztitlerefsetup {key1=value1, key2=value2, ...}
```

This command allows to configure the behaviour of module `titleref`. The following keys are available:

`title=⟨value⟩`

Sets the current title.

`stripperiod=true|false`

Follow package `nameref` that removes a last period. Default: `true`.

`expand=true|false`

Package `\titleref` expands the title first. This way garbage and dangerous commands can be removed, e.g. `\label`, `\index`.... See implementation section for more details. Default is `false`.

`cleanup={...}`

Hook to add own cleanup code, if method `expand` is used. See implementation section for more details.

3.12 Module `savepos`

This option supports a feature that pdf_TE_X provides (and Xe_TE_X). pdf_TE_X is able to tell the current position on the page. The page position is not instantly known. First the page must be constructed by _TE_X's asynchronous output routine. Thus the time where the position is known is the page shipout time. Thus a reference system where the information is recorded in the first run and made available for use in the second run comes in handy.

```
\zsavepos {\<refname>}
```

It generates a reference with name *<refname>* to the location where the command is executed.

```
\zposxexp {\<refname>}  
\zposyexp {\<refname>}
```

Get the position as number. Unit is sp. Horizontal positions by \zposx increase from left to right. Vertical positions by \zposy from bottom to top.

Do not rely on absolute page numbers. Because of problems with the origin the numbers may differ in DVI or PDF mode of pdf_TE_X. Therefore work with relative values by comparisons.

Both \zposx and \zposy are expandable and can be used inside calculations (\setcounter, \addtocounter, package calc, \numexpr). However this property prevents from notifying L_AT_EX that the reference is actually used (the notifying is not expandable). Therefore you should mark the reference as used by \zrefused.

This module uses pdf_TE_X's \pdfsavepos, \pdflastxpos, and \pdflastypos. They are available in PDF mode and since version 1.40.0 also in DVI mode.

3.13 Module `dotfill`

```
\zdotfill
```

This package provides the command \zdotfill that works similar to \dotfill, but can be configured. Especially it suppresses the dots if a minimum number of dots cannot be set.

```
\zdotfillsetup {key1=value1, key2=value2, ...}
```

This command allows to configure the behaviour of \zdotfill. The following keys are available:

`min=<count value>`

If the actual number of dots are smaller than *<count value>*, then the dots are suppressed. Default: 2.

`unit=<dimen value>`

The width of a dot unit is given by *<dimen value>*. Default: 0.44em (same as the unit in \dotfill).

`dot=<value>`

The dot itself is given by *<value>*. Default: . (dot, same as the dot in \dotfill).

3.14 Module `xr`

This package provides the functionality of package `xr`, see [8]. It also supports the syntax of `xr-hyper`.

```
\zexternaldocument* [<prefix>]babel {<external document>} [<url>]
```

See `\externaldocument` for a description of this option. The found labels also get a property `externaldocument` that remembers `<external document>`. The standard reference scheme and the scheme of this package use different name spaces for reference names. If the external document uses both systems. Then one import statement would put the names in one namespace and probably causing problems with multiple references of the same name. Thus the star form only looks for `\newlabel` in the `.aux` files, whereas without star only `\zref@newlabels` are used.

In the star form it tries to detect labels from `hyperref`, `titleref`, and `ntheorem`. If such an extended property from the packages before cannot be found or are empty, they are not included in the imported reference.

Warnings are given if a reference name is already in use and the item is ignored. Unknown properties will automatically be declared.

If the external references contain `anchor` properties, then we need also a url to be able to address the external file. As default the filename is taken with a default extension.

```
\zxrsetup {key1=value1, key2=value2, ...}
```

The following setup options are available:

ext: It sets the default extension.

tozreflabel: The found references are imported as zref labels. This is enabled by default.

toltxlabel: The found references are imported as L^AT_EX labels. Packages `nameref`, `titleref` and class `memoir` are supported.

verbose: List the imported labels in the `.log` file. Default is `false`.

```
\zref@xr@ext
```

If the `<url>` is not specified in `\zref@externaldocument`, then the url will be constructed with the file name and this macro as extension. `\XR@ext` is used if `hyperref` is loaded, otherwise `pdf`.

4 ToDo

Among other things the following issues are left for future work:

- The user land macros are not checked for robustness yet. They can be fragile. If this happens, use `\protect` until a later version of this package. The `\protect` will not disturb, if the protected macro become robust in the future.
- Other applications: `autoref`, `hyperref`, ...

5 Example

```
69 {*example}
70 \documentclass{book}
71
72 \usepackage[ngerman]{babel}%
73
74 \usepackage[savepos,totpages,titleref,dotfill,counter,user]{zref}
75
```

Chapters are wrapped inside `\ChapterStart` and `\ChapterStop`. The first argument #1 of `\ChapterStart` is used to form a label id `chap:#1`. At the end of the chapter another label is set by `\zref@wrapper@immediate`, because otherwise at the end of document a deferred write would not be written, because there is no page for shipout.

Also this example shows how chapter titles can be recorded. A new property `chapttitle` is declared and added to the main property list. In `\ChapterStart` the current value of the property is updated.

```
76 \makeatletter
77 \zref@newprop{chapttitle}{}
78 \zref@addprop{main}{chapttitle}
79
80 \newcommand*{\ChapterStart}[2]{%
81   \cleardoublepage
82   \def\current@chapid{#1}%
83   \zref@setcurrent{chapttitle}{#2}%
84   \chapter{#2}%
85   \zlabel{chap:#1}%
86 }
87 \newcommand*{\ChapterStop}{%
88   \cleardoublepage
89   \zref@wrapper@immediate{%
90     \zref@labelbyprops{chapend:\current@chapid}{abspage}%
91   }%
92 }
```

`\ChapterPages` calculates and returns the number of pages of the referenced chapter.

```
93 \newcommand*{\ChapterPages}[1]{%
94   \zrefused{chap:#1}%
95   \zrefused{chapend:#1}%
96   \number\numexpr
97     \zref@extract{chapend:#1}{abspage}%
98   -\zref@extract{chap:#1}{abspage}%
99   +1\relax
100 }
101 \makeatother
102 \begin{document}
```

As exception we use `\makeatletter` here, because this is just an example file that also should show some of programmer's interface.

```
103 \makeatletter
104
105 \frontmatter
106 \zlabel{documentstart}
107
108 \begin{itemize}
109 \item
110   The frontmatter part has
111   \number\numexpr\zref@extract{chap:first}{abspage}-1\relax^pages.
112 \item
113   Chapter \zref{chap:first} has \ChapterPages{first} page(s).
114 \item
```

```

115 Section \zref{hello} is on the
116 \ifcase\numexpr
117   \zref@extractdefault{hello}{page}{0}%
118   -\zref@extractdefault{chap:first}{page}{0}%
119   +1\relax
120   ??\or first\or second\or third\or forth\fi
121   ~page inside its chapter.
122 \item
123 The document has
124 \zref[abspage]{LastPage} pages.
125 This number is \ifodd\ztotpages odd\else even\fi.
126 \item
127 The last page is labeled with \zpageref{LastPage}.
128 \item
129 The title of chapter \zref{chap:next} is “\zref[chapttitle]{chap:next}”.
130 \end{itemize}
131
132 \tableofcontents
133
134 \mainmatter
135 \ChapterStart{first}{First chapter}
136

```

The user level commands should protect babel shorthands where possible. On the other side, expandable extracting macros are useful in calculations, see above the examples with `\numexpr`.

```

137 \section{Test}
138 \zlabel{a"o}
139 Section \zref{a"o} on page
140 \zref@wrapper@babel\zref@extract{a"o}{page}.
141
142 Text.
143 \newpage
144
145 \section{Hello World}
146 \zlabel{hello}
147
148 \ChapterStop
149
150 \ChapterStart{next}{Next chapter with \emph{umlauts}: "a"o"u"s}
151

```

Here an example follows that makes use of pdf_TE_X’s “`savepos`” feature. The position on the page is not known before the page is constructed and shipped out. Therefore the position is stored in references and are available for calculations in the next L^AT_EX compile run.

```

152 The width of the first column is
153   \the\dimexpr \zposx{secondcol}sp - \zposx{firstcol}sp\relax,\\
154 the height difference of the two baselines is
155   \the\dimexpr \zposy{firstcol}sp - \zposy{secondline}sp\relax:\\
156 \begin{tabular}{ll}
157   \zsavepos{firstcol}Hello&\zsavepos{secondcol}World\\
158   \zsavepos{secondline}Second line&foobar\\
159 \end{tabular}
160

```

With `\zrefused` L^AT_EX is notified, if the references are not yet available and L^AT_EX can generate the rerun hint.

```

161 \zrefused{firstcol}
162 \zrefused{secondcol}
163 \zrefused{secondline}
164
165 \ChapterStop

```

Test for module `\dotfill`.

```

166 \ChapterStart{dotfill}{Test for dotfill feature}
167 \newcommand*{\df{#1}}{%
168   #1&
169   [\makebox[{\#1}]{\dotfill}]&
170   [\makebox[{\#1}]{\zdotfill}]\\
171 }
172 \begin{tabular}{rll}
173 & [\verb|\dotfill|] & [\verb|\zdotfill|]\\
174 \df{0.43em}\\
175 \df{0.44em}\\
176 \df{0.45em}\\
177 \df{0.87em}\\
178 \df{0.88em}\\
179 \df{0.89em}\\
180 \df{1.31em}\\
181 \df{1.32em}\\
182 \df{1.33em}\\
183 \end{tabular}\\
184 \ChapterStop\\
185 \end{document}\\
186 
```

6 Implementation

6.1 Package zref

6.1.1 Identification

```

187 {*package}
188 \NeedsTeXFormat{LaTeX2e}
189 \ProvidesPackage{zref}
190 [2010/04/17 v2.12 New reference scheme for LaTeX2e (HO)]%

```

6.1.2 Load basic module

```
191 \RequirePackage{zref-base}[2010/04/17]
```

Abort package loading if zref-base could not be loaded successfully.

```
192 \@ifundefined{ZREF@baseok}{\endinput}{}%
```

6.1.3 Process options

Known modules are loaded and the release date is checked.

```

193 \def\ZREF@temp#1{%
194   \DeclareOption{#1}{%
195     \AtEndOfPackage{%
196       \RequirePackage{zref-#1}[2010/04/17]%
197     }%
198   }%
199 }
200 \ZREF@temp{abspage}
201 \ZREF@temp{counter}
202 \ZREF@temp{dotfill}
203 \ZREF@temp{hyperref}
204 \ZREF@temp{lastpage}
205 \ZREF@temp{perpage}
206 \ZREF@temp{savepos}
207 \ZREF@temp{titleref}
208 \ZREF@temp{totpages}
209 \ZREF@temp{user}
210 \ZREF@temp{xr}
211 \ProcessOptions\relax
212 
```

6.2 Module base

6.2.1 Prefixes

This package uses the following prefixes for macro names:

\zref@: Macros of the programmer's interface.

\ZREF@: Internal macros.

\Z@L@*listname*: The properties of the list *<listname>*.

\Z@D@*propname*: The default value for property *<propname>*.

\Z@E@*propname*: Extract function for property *<propname>*.

\Z@X@*propname*: Information whether a property value for property *<propname>* is expanded immediately or at shipout time.

\Z@C@*propname*: Current value of the property *<propname>*.

\Z@R@*labelname*: Data for reference *<labelname>*.

\ZREF@org@: Original versions of patched commands.

\z: For macros in user land, defined if module `user` is set.

The following family names are used for keys defined according to the `keyval` package:

ZREF@TR: Setup for module `titleref`.

6.2.2 Identification

```
213 {*base}
214 \NeedsTeXFormat{LaTeX2e}
215 \ProvidesPackage{zref-base}%
216 [2010/04/17 v2.12 Module base for zref (HO)]%
```

6.2.3 Utilities

```
217 \RequirePackage{ltxcmds}[2010/03/01]
```

\ZREF@name Several times the package name is used, thus we store it in \ZREF@name.
218 \def\ZREF@name{zref}

\ZREF@UpdatePdfTeX \ZREF@UpdatePdfTeX is used as help message text in error messages.
219 \def\ZREF@UpdatePdfTeX{Update pdfTeX.}

\ifZREF@found The following switch is usded in list processing.
220 \newif\ifZREF@found

\ZREF@patch Macro \ZREF@patch first checks the existence of the command and safes it.
221 \def\ZREF@patch#1{%
222 \begingroup\expandafter\expandafter\expandafter\expandafter\endgroup
223 \expandafter\ifx\csname #1\endcsname\relax
224 \expandafter\ltx@gobble
225 \else
226 \expandafter\let\csname ZREF@org@#1\expandafter\endcsname
227 \csname #1\endcsname
228 \expandafter\ltx@firstofone
229 \fi
230 }

6.2.4 Check for ε -TeX

The use of ε -TeX should be standard nowadays for L^AT_EX. We test for ε -TeX in order to use its features later.

```

231 \ltx@IfUndefined{eTeXversion}{%
232   \PackageError{ZREF}{name}{%
233     Missing support for eTeX; package is abandoned}%
234 }{%
235   Use a TeX compiler that support eTeX and enable eTeX %
236   in the format}%
237 }{%
238 \endinput
239 }{%
240 \RequirePackage{etexcmds}[2007/09/09]
241 \ifetex@unexpanded
242 \else
243   \PackageError{ZREF}{name}{%
244     Missing e-TeX's \string\unexpanded.\MessageBreak
245     Add \string\RequirePackage{string\etexcmds\string} before %
246     \string\documentclass}%
247 }{%
248   Probably you are using some package (e.g. ConTeXt) that %
249   redefines \string\unexpanded}%
250 }{%
251 \expandafter\endinput
252 \fi

```

6.2.5 Auxiliary file stuff

We are using some commands in the .aux files. However sometimes these auxiliary files are interpreted by L^AT_EX processes that haven't loaded this package (e.g. package *xr*). Therefore we provide dummy definitions.

```

253 \RequirePackage{auxhook}
254 \AddLineBeginAux{%
255   \string\providetoggle\string\zref@newlabel[2]{}}%
256 }

```

`\zref@newlabel` For the implementation of `\zref@newlabel` we call the same internal macro `\@newl@bel` that is used in `\newlabel`. Thus we have for free:

- `\ZR@labelname` is defined.
- L^AT_EX's check for multiple references.
- L^AT_EX's check for changed references.

```

257 \def\zref@newlabel{%
258   \@newl@bel{Z@R}%
259 }

```

6.2.6 Property lists

`\zref@newlist` Property lists are stored as list of property names enclosed in curly braces. `\zref@newlist` creates a new list as empty list. Assignments to property lists are global.

```

260 \def\zref@newlist#1{%
261   \zref@iflistundefined{#1}{%
262     \ifdefinable{Z@L@#1}{%
263       \global\expandafter\let\csname Z@L@#1\endcsname\empty
264       \PackageInfo{zref}{New property list: #1}%
265     }%
266   }{%

```

```

267      \PackageError{ZREF@name}{%
268          Property list '#1' already exists%
269      }{\@ehc
270  }%
271 }

\zref@iflistundefined \zref@iflistundefined checks the existence of the property list #1. If the property list is present, then #2 is executed and #3 otherwise.
272 \def\zref@iflistundefined#1{%
273     \expandafter\ifx\csname Z@L@#1\endcsname\relax
274         \expandafter\ltx@firstoftwo
275     \else
276         \expandafter\ltx@secondoftwo
277     \fi
278 }

\zref@listexists \zref@listexists only executes #2 if the property list #1 exists and raises an error message otherwise.
279 \def\zref@listexists#1{%
280     \zref@iflistundefined{#1}{%
281         \PackageError{ZREF@name}{%
282             Property list '#1' does not exist%
283         }{\@ehc
284     }%
285 }

\zref@iflistcontainsprop \zref@iflistcontainsprop checks, whether a property #2 is already present in a property list #1.
286 \def\zref@iflistcontainsprop#1{%
287     \expandafter\ZREF@iflistcontainsprop\csname Z@L@#1\endcsname
288 }
289 \def\ZREF@iflistcontainsprop#1#2{%
290     \begingroup
291     \ZREF@foundfalse
292     \edef\y{#2}%
293     \expandafter\@tfor\expandafter\x
294     \expandafter:\expandafter=#1\do{%
295         \edef\x{\x}%
296         \ifx\x\y
297             \ZREF@foundtrue
298         \fi
299     }%
300     \expandafter\endgroup
301     \ifZREF@found
302         \expandafter\ltx@firstoftwo
303     \else
304         \expandafter\ltx@secondoftwo
305     \fi
306 }

\zref@listforloop
307 \def\zref@listforloop#1#2{%
308     \expandafter\expandafter\expandafter\@tfor
309     \expandafter\expandafter\expandafter\zref@prop
310     \expandafter\expandafter\expandafter:%
311     \expandafter\expandafter\expandafter=%
312     \csname Z@L@#1\endcsname
313     \do{%
314         #2\zref@prop
315     }%
316 }

```

```

\zref@addprop \zref@addprop adds the property #2 to the property list #1, if the property is
not already in the list. Otherwise a warning is given.
317 \def\zref@addprop#1#2{%
318   \zref@listexists{#1}{%
319     \zref@propexists{#2}{%
320       \zref@iflistcontainsprop{#1}{#2}{%
321         \PackageWarning{\ZREF@name}{%
322           Property '#2' is already in list '#1'}%
323         }%
324       }{%
325         \edef\ZREF@temp{#2}%
326         \expandafter\g@addto@macro\csname Z@L#1\expandafter\endcsname
327         \expandafter{\expandafter{\ZREF@temp}}%
328       }%
329     }%
330   }%
331 }

\zref@localaddprop
332 \def\zref@localaddprop#1#2{%
333   \zref@listexists{#1}{%
334     \zref@propexists{#2}{%
335       \zref@iflistcontainsprop{#1}{#2}{%
336         \PackageWarning{\ZREF@name}{%
337           Property '#2' is already in list '#1'}%
338         }%
339       }{%
340         \expandafter\ZREF@l@addto@macro\csname Z@L#1\endcsname{#2}}%
341       }%
342     }%
343   }%
344 }

\ZREF@l@addto@macro
345 \ifetex@unexpanded
346   \def\ZREF@l@addto@macro#1#2{%
347     \global\let\ZREF@gtemp#1%
348     \g@addto@macro\ZREF@gtemp{#2}%
349     \let#1\ZREF@gtemp
350   }%
351 \else
352   \def\ZREF@l@addto@macro#1#2{%
353     \edef#1{%
354       \etex@unexpanded\expandafter{#1#2}%
355     }%
356   }%
357 \fi

```

6.2.7 Properties

\zref@ifpropundefined \zref@ifpropundefined checks the existence of the property #1. If the property is present, then #2 is executed and #3 otherwise.

```

358 \def\zref@ifpropundefined#1{%
359   \expandafter\ifx\csname Z@E@#1\endcsname\relax
360     \expandafter\ltx@firstoftwo
361   \else
362     \expandafter\ltx@secondoftwo
363   \fi
364 }

```

\zref@propexists Some macros rely on the existence of a property. \zref@propexists only executes #2 if the property #1 exists and raises an error message otherwise.

```

365 \def\zref@propexists#1{%
366   \zref@ifpropundefined{#1}{%
367     \PackageError\ZREF@name{%
368       Property '#1' does not exist}%
369   }{\@ehc}%
370 }%
371 }

```

\zref@newprop A new property is declared by `\zref@newprop`, the property name $\langle propname \rangle$ is given in #1. The property is created and configured. If the star form is given, then the expansion of the property value is delayed to page shipout time, when the reference is written to the `.aux` file.

`\Z@D@propname`: Stores the default value for this property.

`\Z@E@propname`: Extract function.

`\Z@X@propname`: Information whether the expansion of the property value is delayed to shipout time.

`\Z@C@propname`: Current value of the property.

```

372 \def\zref@newprop{%
373   \@ifstar{%
374     \let\ZREF@X\noexpand
375     \ZREF@newprop
376   }{%
377     \let\ZREF@X\empty
378     \ZREF@newprop
379   }%
380 }
381 \def\ZREF@newprop#1{%
382   \PackageInfo{zref}{New property: #1}%
383   \def\ZREF@P{#1}%
384   \ifnextchar[\ZREF@@newprop{\ZREF@@newprop[\zref@default]}%
385 }
386 \def\ZREF@@newprop[#1]{%
387   \global\@namedef{Z@D@\ZREF@P}{#1}%
388   \global\expandafter\let\csname Z@X@\ZREF@P\endcsname\ZREF@X
389   \expandafter\ZREF@@@newprop\csname\ZREF@P\endcsname
390   \expandafter\gdef\csname Z@C@\ZREF@P\endcsname{}%
391   \zref@setcurrent\ZREF@P
392 }
393 \def\ZREF@@@newprop#1{%
394   \expandafter\gdef\csname Z@E@\ZREF@P\endcsname##1##2##3\ZREF@nil{##2}%
395 }

```

\zref@setcurrent `\zref@setcurrent` sets the current value for a property.

```

396 \def\zref@setcurrent#1{%
397   \expandafter\def\csname Z@C@#1\endcsname
398 }

```

\zref@getcurrent `\zref@getcurrent` gets the current value for a property.

```

399 \def\zref@getcurrent#1{%
400   \csname Z@C@#1\endcsname
401 }

```

6.2.8 Reference generation

\zref@label Label macro that uses the main property list.

```

402 \def\zref@label#1{%
403   \zref@labelbylist{#1}\ZREF@mainlist
404 }

```

\zref@labelbylist Label macro that stores the properties, specified in the property list #2.

```
405 \def\zref@labelbylist#1#2{%
406   \@bsphack
407   \zref@listexists{#2}{%
408     \expandafter\expandafter\expandafter\ZREF@label
409     \expandafter\expandafter\expandafter{%
410       \csname Z@L@#2\endcsname
411     }{#1}%
412   }%
413   \@esphack
414 }
```

\zref@labelbyprops The properties are directly specified in a comma separated list.

```
415 \def\zref@labelbyprops#1#2{%
416   \@bsphack
417   \begingroup
418   \edef\l{#2}%
419   \toks@{ }%
420   \for\x:=#2\do{%
421     \zref@ifpropundefined{\x}{%
422       \PackageWarning\ZREF@name{%
423         Property ‘\x’ is not known}%
424     }%
425   }%
426   \toks@\expandafter\expandafter\expandafter{%
427     \expandafter\the\expandafter\toks@\expandafter{\x}%
428   }%
429   }%
430   }%
431   \expandafter\endgroup
432   \expandafter\ZREF@label\expandafter{\the\toks@}{#1}%
433   \@esphack
434 }
```

\ifZREF@immediate The switch \ifZREF@immediate tells us, whether the label should be written immediately or at page shipout time. \ZREF@label need to be notified about this, because it must disable the deferred execution of property values, if the label is written immediately.

```
435 \newif\ifZREF@immediate
```

\zref@wrapper@immediate The argument of \zref@wrapper@immediate is executed inside a group where \write is redefined by adding \immediate before its execution. Also \ZREF@label is notified via the switch \ifZREF@immediate.

```
436 \long\def\zref@wrapper@immediate#1{%
437   \begingroup
438   \ZREF@immediatetrue
439   \let\ZREF@org@write\write
440   \def\write{\immediate\ZREF@org@write}%
441   #1%
442   \endgroup
443 }
```

\ZREF@label \ZREF@label writes the data in the .aux file. #1 contains the list of valid properties, #2 the name of the reference. In case of immediate writing, the deferred execution of property values is disabled. Also 25is made expandable in this case.

```
444 \def\ZREF@label#1#2{%
445   \if@filesw
446   \begingroup
447   \ifZREF@immediate
448     \let\ZREF@org@thepage\thepage
449   \fi
```

```

450     \protected@write\@auxout{%
451         \ifZREF@immediate
452             \let\thepage\ZREF@org@thepage
453         \fi
454         \let\ZREF@temp\empty
455         \atfor\ZREF@P:=#1\do{%
456             \expandafter\ifx
457                 \csname\ifZREF@immediate relax\else Z@X@\ZREF@P\fi\endcsname
458                 \noexpand
459             \expandafter\let\csname Z@C@\ZREF@P\endcsname\relax
460             \fi
461             \toks@\expandafter{\ZREF@temp}%
462             \edef\ZREF@temp{%
463                 \the\toks@
464                 \expandafter\string\csname\ZREF@P\endcsname{%
465                     \expandafter\noexpand\csname Z@C@\ZREF@P\endcsname
466                 }%
467             }%
468             }%
469         }{%
470             \string\zref@newlabel{#2}{\ZREF@temp}%
471         }%
472     \endgroup
473     \fi
474 }
475 \def\ZREF@addtoks#1{%
476     \toks@\expandafter\expandafter\expandafter{%
477         \expandafter\the\expandafter\toks@#1%
478     }%
479 }

```

6.2.9 Reference querying and extracting

Design goal for the extracting macros is that the extraction process is full expandable. Thus these macros can be used in expandable contexts. But there are problems that cannot be solved by full expandable macros:

- In standard L^AT_EX undefined references sets a flag and generate a warning. Both actions are not expandable.
- Babel's support for its shorthand uses commands that use non-expandable assignments. However currently there is hope, that primitives are added to pdft_EX that allows the detection of contexts. Then the shorthand can detect, if they are executed inside \csname and protect themselves automatically.

`\zref@ifrefundefined` If a reference #1 is undefined, then macro `\zref@ifrefundefined` calls #2 and #3 otherwise.

```

480 \def\zref@ifrefundefined#1{%
481     \expandafter\ifx\csname Z@R@#1\endcsname\relax
482         \expandafter\ltx@firstoftwo
483     \else
484         \expandafter\ltx@secondoftwo
485     \fi
486 }

```

`\zifrefundefined` If a reference #1 is undefined, then macro `\zref@ifrefundefined` calls #2 and #3 otherwise. Also the reference is marked used.

```

487 \newcommand*{\zifrefundefined}[1]{%
488     \zref@wrapper@babel\ZREF@ifrefundefined{#1}%
489 }

```

\ZREF@ifrefundefined	
490 \def\ZREF@ifrefundefined#1{%	
491 \zref@refused{#1}%	
492 \zref@ifrefundefined{#1}%	
493 }	
\zref@refused	The problem with undefined references is addressed by the macro <code>\zref@refused</code> . This can be used outside the expandable context. In case of an undefined reference the flag is set to notify L ^A T _E X and a warning is given.
494 \def\zref@refused#1{%	
495 \zref@wrapper@babel\ZREF@refused{#1}%	
496 }	
\ZREF@refused	
497 \def\ZREF@refused#1{%	
498 \zref@ifrefundefined{#1}{%	
499 \protect\G@refundefinedtrue	
500 \@latex@warning{%	
501 Reference '#1' on page \thepage \space undefined%	
502 }%	
503 }{}}	
504 }	
\zref@extract	<code>\zref@extract</code> is an abbreviation for the case that the default of the property is used as default value.
505 \def\zref@extract#1#2{%	
506 \expandafter\expandafter\expandafter\ZREF@extract	
507 \expandafter\expandafter\expandafter{%	
508 \csname Z@D@#2\endcsname	
509 }{#1}{#2}%	
510 }	
511 \def\ZREF@extract#1#2#3{%	
512 \zref@extractdefault{#2}{#3}{#1}%	
513 }	
\zref@ifrefcontainsprop	<code>\zref@ifrefcontainsprop</code> looks, if the reference #1 has the property #2 and calls then #3 and #4 otherwise.
514 \def\zref@ifrefcontainsprop#1#2{%	
515 \zref@ifrefundefined{#1}{%	
516 \ltx@secondoftwo	
517 }{%	
518 \expandafter\ZREF@ifrefcontainsprop	
519 \csname Z@E@#2\expandafter\endcsname	
520 \csname#2\expandafter\expandafter\expandafter\endcsname	
521 \expandafter\expandafter\expandafter{%	
522 \csname Z@R@#1\endcsname	
523 }%	
524 }%	
525 }	
526 \def\ZREF@ifrefcontainsprop#1#2#3{%	
527 \expandafter\ifx\expandafter\ZREF@novalue	
528 #1#3#2\ZREF@novalue\ZREF@nil\@empty	
529 \expandafter\ltx@secondoftwo	
530 \else	
531 \expandafter\ltx@firstoftwo	
532 \fi	
533 }	
534 \def\ZREF@novalue{\ZREF@NOVALUE}	
\zref@extractdefault	The basic extracting macro is <code>\zref@extractdefault</code> with the reference name in #1, the property in #2 and the default value in #3 in case for problems.

```

535 \def\zref@extractdefault#1#2#3{%
536   \zref@ifrefundefined{#1}{%
537     \ZREF@unexpanded{#3}%
538   }{%
539     \expandafter\expandafter\expandafter\ZREF@unexpanded
540     \expandafter\expandafter\expandafter{%
541       \csname Z@E@#2\expandafter\expandafter\expandafter\endcsname
542       \csname Z@R@#1\expandafter\expandafter\endcsname
543       \csname#2\endcsname{#3}\ZREF@nil
544     }%
545   }%
546 }

\zref@wrapper@unexpanded

547 \long\def\zref@wrapper@unexpanded#1{%
548   \let\ZREF@unexpanded\etex@unexpanded
549   #1%
550   \let\ZREF@unexpanded\ltx@firstofone
551 }
552 \let\ZREF@unexpanded\ltx@firstofone

```

6.2.10 Compatibility with babel

```

\zref@wrapper@babel

553 \long\def\zref@wrapper@babel#1#2{%
554   \ifcsname if@safemode@actives\endcsname
555     \expandafter\ltx@firstofone
556   \else
557     \expandafter\ltx@secondoftwo
558   \fi
559   {%
560     \if@safemode@actives
561       \expandafter\ltx@secondoftwo
562     \else
563       \expandafter\ltx@firstoftwo
564     \fi
565   }%
566   \begingroup
567     \csname @safemode@activestrue\endcsname
568     \edef\x{#2}%
569     \expandafter\endgroup
570     \expandafter\ZREF@wrapper@babel\expandafter{\x}{#1}%
571   }%
572 }{%
573   #1{#2}%
574 }%
575 }

576 \long\def\ZREF@wrapper@babel#1#2{%
577   #2{#1}%
578 }

```

6.2.11 Unique counter support

\zref@require@unique Generate the counter `zref@unique` if the counter does not already exist.

```

579 \def\zref@require@unique{%
580   \@ifundefined{c@zref@unique}{%
581     \begingroup
582       \let\@addtoreset\ltx@gobbletwo
583       \newcounter{zref@unique}%
584     \endgroup

```

\thezref@unique \thezref@unique is used for automatically generated unique labelnames.

```
585     \renewcommand*\thezref@unique}{%
586         zref@\number\c@zref@unique
587     }%
588 }{}}%
589 }
```

6.2.12 Utilities

\ZREF@number

```
590 \ltx@ifundefined{numexpr}{%
591     \let\ZREF@number\relax
592 }{%
593     \def\ZREF@number{\the\numexpr#1}%
594 }
```

6.2.13 Setup

\zref@setdefault Standard L^AT_EX prints “??” in bold face if a reference is not known. \zref@default holds the text that is printed in case of unknown references and is used, if the default was not specified during the definition of the new property by \ref@newprop. The global default value can be set by \zref@setdefault.

```
595 \def\zref@setdefault#1{%
596     \def\zref@default{\bf ??}%
597 }
```

\zref@default Now we initialize \zref@default with the same value that L^AT_EX uses for its undefined references.

```
598 \zref@setdefault{%
599     \nfss@text{\reset@font\bfseries ??}%
600 }
```

Main property list.

\zref@setmainlist The name of the default property list is stored in \ZREF@mainlist and can be set by \zref@setmainlist.

```
601 \def\zref@setmainlist#1{%
602     \def\ZREF@mainlist{\#1}%
603 }
604 \zref@setmainlist{main}
```

Now we create the list.

```
605 \zref@newlist\ZREF@mainlist
```

Main properties. The two properties `default` and `page` are created and added to the main property list. They store the data that standard L^AT_EX uses in its references created by \label.

`default` the appearance of the latest counter that is incremented by \refstepcounter

`page` the appearance of the page counter

```
606 \zref@newprop{default}{\@currentlabel}
607 \zref@newprop*{page}{\thepage}
608 \zref@addprop\ZREF@mainlist{default}
609 \zref@addprop\ZREF@mainlist{page}
```

Mark successful loading

```
610 \let\ZREF@baseok\empty
611 </base>
```

6.3 Module user

```

612 < *user>
613 \NeedsTeXFormat{LaTeX2e}
614 \ProvidesPackage{zref-user}%
615 [2010/04/17 v2.12 Module user for zref (HO)]%
616 \RequirePackage{zref-base}[2010/04/17]
617 \Ifundefined{ZREF@baseok}{\endinput}{}%

```

Module `user` enables a small user interface. All macros are prefixed by `\z`.

First we define the pendants to the standard L^AT_EX referencing commands `\label`, `\ref`, and `\pageref`.

- `\zlabel` Similar to `\label` the macro `\zlabel` writes a reference entry in the `.aux` file. The main property list is used. Also we add the babel patch. The `\label` command can also be used inside section titles, but it must not go into the table of contents. Therefore we have to check this situation.

```

618 \newcommand*\zlabel{%
619   \ifx\label\ltx@gobble
620     \expandafter\ltx@gobble
621   \else
622     \expandafter\zref@wrapper@babel\expandafter\zref@label
623   \fi
624 }%

```

- `\zref` Macro `\zref` is the corresponding macro for `\ref`. Also it provides an optional argument in order to select another property.

```

625 \newcommand*\zref[2][default]{%
626   \zref@propexists{#1}{%
627     \zref@wrapper@babel\ZREF@zref{#2}{#1}%
628   }%
629 }%
630 \def\ZREF@zref#1{%
631   \zref@refused{#1}%
632   \zref@extract{#1}%
633 }%

```

- `\zpageref` For macro `\zpageref` we just call `\zref` with property `page`.

```

634 \newcommand*\zpageref{%
635   \zref[page]%
636 }%

```

- `\zrefused` For the following expandible user macros `\zrefused` should be used to notify L^AT_EX in case of undefined references.

```

637 \newcommand*\zrefused{\zref@refused}%
638 </user>

```

6.4 Module `abspage`

```

639 < *abspage>
640 \NeedsTeXFormat{LaTeX2e}
641 \ProvidesPackage{zref-abspage}%
642 [2010/04/17 v2.12 Module abspage for zref (HO)]%
643 \RequirePackage{zref-base}[2010/04/17]
644 \Ifundefined{ZREF@baseok}{\endinput}{}%

```

Module `abspage` adds a new property `abspage` to the `main` property list for absolute page numbers. These are recorded by the help of package `atbegshi`.

```
645 \RequirePackage{atbegshi}%

```

The counter `abspage` must not go in the clear list of `@ckpt` that is used to set counters in `.aux` files of included T_EX files.

```
646 \begingroup

```

```

647 \let\@addtoreset\ltx@gobbletwo
648 \newcounter{abspage}%
649 \endgroup
650 \setcounter{abspage}{0}%
651 \AtBeginShipout{%
652 \stepcounter{abspage}%
653 }%
654 \zref@newprop*{abspage}[0]{\the\c@abspage}%
655 \zref@addprop\ZREF@mainlist{abspage}%
656 </abspage>

```

Note that counter `abspage` shows the previous page during page processing. Before shipout the counter is incremented. Thus the property is correctly written with deferred writing. If the counter is written using `\zref@wrapper@immediate`, then the number is too small by one.

```
656 </abspage>
```

6.5 Module `counter`

```

657 <*counter>
658 \NeedsTeXFormat{LaTeX2e}
659 \ProvidesPackage{zref-counter}%
660 [2010/04/17 v2.12 Module counter for zref (HO)]%
661 \RequirePackage{zref-base}[2010/04/17]
662 \Ifundefined{ZREF@baseok}{\endinput}{}%

```

For features such as `hyperref`'s `\autoref` we need the name of the counter. The property `counter` is defined and added to the main property list.

```

663 \zref@newprop{counter}{}%
664 \zref@addprop\ZREF@mainlist{counter}%

```

`\refstepcounter` is the central macro where we know which counter is responsible for the reference.

```

665 \AtBeginDocument{%
666 \ZREF@patch{refstepcounter}{%
667 \def\refstepcounter#1{%
668 \zref@setcurrent{counter}{#1}%
669 \ZREF@org@refstepcounter{#1}%
670 }%
671 }%
672 }%
673 </counter>

```

6.6 Module `lastpage`

```

674 <*lastpage>
675 \NeedsTeXFormat{LaTeX2e}
676 \ProvidesPackage{zref-lastpage}%
677 [2010/04/17 v2.12 Module lastpage for zref (HO)]%
678 \RequirePackage{zref-base}[2010/04/17]
679 \RequirePackage{zref-abspage}[2010/04/17]
680 \RequirePackage{atveryend}[2009/12/07]
681 \Ifundefined{ZREF@baseok}{\endinput}{}%

```

The module `lastpage` implements the service of package `lastpage` by setting a reference `LastPage` at the end of the document. If module `abspage` is given, also the absolute page number is available, because the properties of the main property list are used.

```

682 \zref@newlist{LastPage}%
683 \AfterLastShipout{%
684 \if@filesw
685 \begingroup
686 \advance\c@page\m@ne
687 \toks@\expandafter\expandafter\expandafter{%
688 \expandafter\Z@L@main
689 \Z@L@LastPage

```

```

690      }%
691      \expandafter\zref@wrapper@immediate\expandafter{%
692          \expandafter\ZREF@label\expandafter{\the\toks@\LastPage}%
693      }%
694      \endgroup
695  \fi
696 }

\zref@iflastpage
697 \def\zref@iflastpage#1{%
698   \ifnum\zref@extractdefault{#1}{abspage}{-1}=%
699     \zref@extractdefault{LastPage}{abspage}{-2} %
700   \expandafter\ltx@firstoftwo
701   \else
702     \expandafter\ltx@secondoftwo
703   \fi
704 }

\ziflastpage
705 \newcommand*\ziflastpage{%
706   \zref@wrapper@babel\ZREF@iflastpage
707 }

ZREF@iflastpage
708 \def\ZREF@iflastpage#1{%
709   \zref@refused{LastPage}%
710   \zref@refused{#1}%
711   \zref@iflastpage{#1}%
712 }

713 </lastpage>

```

6.7 Module `thepage`

```

714 {*thepage}
715 \NeedsTeXFormat{LaTeX2e}
716 \ProvidesPackage{zref-thepage}%
717 [2010/04/17 v2.12 Module thepage for zref (HO)]%
718 \RequirePackage{zref-base}[2010/04/17]
719 \Ifundefined{ZREF@baseok}{\endinput}{}

720 \RequirePackage{atbegshi}
721 \RequirePackage{zref-abspage}[2010/04/17]

722 \zref@newlist{thepage}
723 \zref@addprop{thepage}{page}
724 \AtBeginShipout{%
725   \zref@wrapper@immediate{%
726     \zref@labelbylist{thepage\the\value{abspage}}{thepage}%
727   }%
728 }

```

\zref@thepage@name

```

729 \ltx@IfUndefined{numexpr}{%
730   \def\zref@thepage@name#1{thepage\number#1}%
731 }{%
732   \def\zref@thepage@name#1{thepage\the\numexpr#1}%
733 }

```

\zref@thepage

```

734 \def\zref@thepage#1{%
735   \zref@extract{\zref@thepage@name{#1}}{page}%
736 }

```

```

\zref@thepage@refused

737 \def\zref@thepage@refused#1{%
738   \zref@refused{\zref@thepage@name{#1}}%
739 }%

\zthepage

740 \newcommand*\zthepage[1]{%
741   \zref@thepage@refused{#1}%
742   \zref@thepage{#1}%
743 }

744 </thepage>

```

6.8 Module `nextpage`

```

745 (*nextpage)
746 \NeedsTeXFormat{LaTeX2e}
747 \ProvidesPackage{zref-nextpage}%
748 [2010/04/17 v2.12 Module nextpage for zref (HO)]%
749 \RequirePackage{zref-base}[2010/04/17]
750 \ifundefined{ZREF@baseok}{\endinput}{}

751 \RequirePackage{zref-abspage}[2010/04/17]
752 \RequirePackage{zref-thepage}[2010/04/17]
753 \RequirePackage{zref-lastpage}[2010/04/17]
754 \RequirePackage{uniquecounter}[2009/12/18]

755 \UniqueCounterNew{znexpage}
756
757 \newcommand*\znexpagesetup{%
758   \afterassignment\ZREF@np@setup@i
759   \def\ZREF@np@call@unknown##1%
760 }
761 \def\ZREF@np@setup@i{%
762   \afterassignment\ZREF@np@setup@ii
763   \def\ZREF@np@call@nonext##1%
764 }
765 \def\ZREF@np@setup@ii{%
766   \def\ZREF@np@call@next##1%
767 }
768 \def\ZREF@np@call@unknown##1{#1}
769 \def\ZREF@np@call@nonext##1{#1}
770 \def\ZREF@np@call@next##1{#1}
771 \newcommand*\znexpage{%
772   \UniqueCounterCall{znexpage}{\ZREF@nextpage}%
773 }
774 \newcommand*\znonexpagename{%
775 \newcommand*\zunknnownexpagename{\Z@D@page}
776 \def\ZREF@nextpage##1{%
777   \begingroup
778     \def\ZREF@refname@this{\zref@np##1}%
779     \zref@labelbyprops\ZREF@refname@this{abspage}%
780     \chardef\ZREF@call=0 % unknown
781     \ZREF@ifundefined\ZREF@refname@this{%
782       }{%
783         \edef\ZREF@pagenum@this{%
784           \zref@extractdefault\ZREF@refname@this{abspage}{0}}%
785       }%
786       \edef\ZREF@refname@next{%
787         \zref@thepage@name{%
788           \the\numexpr\ZREF@pagenum@this+1}%
789         }%
790       }%
791     }%
792   }
```

```

791      \ifnum\ZREF@pagenum@this>0 %
792          \ZREF@ifrefundefined{LastPage}{%
793              \zref@ifrefundefined{\ZREF@refname@next}{%
794                  }{%
795                      \chardef\ZREF@call=2 % next page
796                  }{%
797                      }{%
798                          \edef\ZREF@pagenum@last{%
799                              \zref@extractdefault{LastPage}{abspage}{0}%
800                          }{%
801                              \ifnum\ZREF@pagenum@this<\ZREF@pagenum@last\ltx@space
802                                  \ZREF@ifrefundefined{\ZREF@refname@next}{%
803                                      }{%
804                                          \chardef\ZREF@call=2 % next page
805                                      }{%
806                                          \else
807                                              \ifnum\ZREF@pagenum@this=\ZREF@pagenum@this\ltx@space
808                                                  \chardef\ZREF@call=1 % no next page
809                                              \fi
810                                              \fi
811                                              }{%
812                                              \fi
813                                              }{%
814                                              \edef\x{%
815                                                 \endgroup
816                                                 \ifcase\ZREF@call
817                                                     \noexpand\ZREF@np@call@unknown{%
818                                                         \noexpand\zunknnownextpagename
819                                                     }{%
820                                                     \or
821                                                         \noexpand\ZREF@np@call@nonext{%
822                                                             \noexpand\znonextpagename
823                                                         }{%
824                                                         \else
825                                                             \noexpand\ZREF@np@call@next{%
826                                                                 \noexpand\zref@extract{\ZREF@refname@next}{page}{%
827                                                                 }{%
828                                                             \fi
829                                                         }{%
830                                                         \x
831 }{%
832 }{%
833 
```

6.9 Module `totpages`

```

833 {*totpages}
834 \NeedsTeXFormat{LaTeX2e}
835 \ProvidesPackage{zref-totpages}{%
836     [2010/04/17 v2.12 Module totpages for zref (HO)]%
837 \RequirePackage{zref-base}[2010/04/17]
838 \Ifundefined{ZREF@baseok}{\endinput}{}

```

The absolute page number of the last page is the total page number.

```

839 \RequirePackage{zref-abspage}[2010/04/17]
840 \RequirePackage{zref-lastpage}[2010/04/17]

```

`\ztotpages` Macro `\ztotpages` contains the number of pages. It can be used inside expandable calculations. It expands to zero if the reference is not yet available.

```

841 \newcommand*\ztotpages{%
842     \zref@extractdefault{LastPage}{abspage}{0}%
843 }

```

Also we mark the reference `LastPage` as used:

```

844 \AtBeginDocument{%

```

```

845   \zref@refused{LastPage}%
846 }
847 </totpages>

```

6.10 Module marks

```

848 {*marks}
849 \NeedsTeXFormat{LaTeX2e}
850 \ProvidesPackage{zref-marks}%
851 [2010/04/17 v2.12 Module marks for zref (HO)]%
852 \RequirePackage{zref-base}[2010/04/17]
853 \Ifundefined{ZREF@baseok}{\endinput}{}

854 \RequirePackage{kvsetkeys}[2009/07/30]
855 \newcommand*{\zref@marks@register}[3][]{%
856   \edef\ZREF@TempName{\#1}%
857   \edef\ZREF@TempNum{\ZREF@number\#2}%
858   \ifnum\ZREF@TempNum<\ltx@zero %
859     \PackageError{\ZREF@name}{%
860       \string\zref@marks@register\ltx@space is called with invalid}%
861     \MessageBreak
862     marks register number (\ZREF@TempNum)}%
863   }{%
864     Use '0' or the command, defined by \string\newmarks.\MessageBreak
865     \@ehc
866   }%
867 \else
868   \ifx\ZREF@TempName\ltx@empty
869     \edef\ZREF@TempName{\mark\romannumeral\ZREF@TempNum}%
870   \else
871     \edef\ZREF@TempName{\marks\ZREF@TempName}%
872   \fi
873   \ZREF@MARKS@DefineProp{top}%
874   \ZREF@MARKS@DefineProp{first}%
875   \ZREF@MARKS@DefineProp{bot}%
876   \kv@parse{\#3}{%
877     \ifx\kv@value\relax
878       \def\kv@value{top,first,bot}%
879     \fi
880     \edef\ZREF@temp{\expandafter\@car\kv@key X\@nil}%
881     \ifx\ZREF@temp\ZREF@STAR
882       \edef\kv@key{\expandafter\@cdr\kv@key\@nil}%
883       \zref@newlist\kv@key
884     \fi
885     \expandafter\comma@parse\expandafter{\kv@value}{%
886       \ifcase0\ifx\comma@entry\ZREF@NAME@top 1\else
887         \ifx\comma@entry\ZREF@NAME@first 1\else
888           \ifx\comma@entry\ZREF@NAME@bot 1\fi\fi\fi\ltx@space
889       \PackageWarning{\ZREF@name}{%
890         Use 'top', 'first' or 'bot' for the list values}%
891       \MessageBreak
892       in the third argument of \string\zref@marks@register.%\MessageBreak
893       Ignoring unkown value '\comma@entry'%
894     }%
895   }%
896   \else
897     \zref@addprop{\kv@key}{\comma@entry\ZREF@TempName}%
898   \fi
899   \ltx@gobble
900 }%
901   \ltx@gobbletwo
902 }%
903 \fi

```

```

904 }
905 \def\ZREF@STAR{*}
906 \def\ZREF@NAME@top{top}
907 \def\ZREF@NAME@first{first}
908 \def\ZREF@NAME@bot{bot}
909 \def\ZREF@MARKS@DefineProp#1{%
910   \zref@ifpropundefined{#1\ZREF@TempName}{%
911     \ifnum\ZREF@TempNum=\ltx@zero
912       \begingroup
913         \edef\x{\endgroup
914           \noexpand\zref@newprop*{#1\ZREF@TempName}[]{%
915             \expandafter\noexpand\csname#1mark\endcsname
916           }%
917         }%
918       \x
919     \else
920       \begingroup
921         \edef\x{\endgroup
922           \noexpand\zref@newprop*{#1\ZREF@TempName}[]{%
923             \expandafter\noexpand\csname#1marks\endcsname
924             \ZREF@TempNum
925           }%
926         }%
927       \x
928     \fi
929   }{%
930     \PackageWarning{\ZREF@name}{%
931       \string\zref@marks@register\ltx@space does not generate the%
932       \MessageBreak
933       new property '#1\ZREF@TempName', because\MessageBreak
934       it is already defined%
935     }%
936   }%
937 }
938 </marks>

```

6.11 Module runs

This module does not use the label-reference-system. The reference changes with each L^AT_EX run and would force a rerun warning always.

```

939 <*runs>
940 \NeedsTeXFormat{LaTeX2e}
941 \ProvidesPackage{zref-runs}%
942 [2010/04/17 v2.12 Module runs for zref (HO)]%

\zruns

943 \providetoggle{\zruns}{0}%
944 \AtBeginDocument{%
945   \edef\zruns{\number\numexpr\zruns+1}%
946   \begingroup
947     \def\on@line{}%
948     \PackageInfo{zref-runs}{LaTeX runs: \zruns}%
949     \if@filesw
950       \immediate\write\@mainaux{%
951         \string\gdef\string\zruns{\zruns}%
952       }%
953     \fi
954   \endgroup
955 }

956 </runs>

```

6.12 Module `perpage`

```

957 {*perpage}
958 \NeedsTeXFormat{LaTeX2e}
959 \ProvidesPackage{zref-perpage}%
960 [2010/04/17 v2.12 Module perpage for zref (HO)]%
961 \RequirePackage{zref-base}[2010/04/17]
962 \Ifundefined{ZREF@baseok}{\endinput}{}%

```

This module resets a counter at page boundaries. Because of the asynchronous output routine page counter properties cannot be asked directly, references are necessary.

For detecting changed pages module `abspage` is loaded.

```

963 \RequirePackage{zref-abspage}[2010/04/17]
```

We group the properties for the needed references in the property list `perpage`. The property `pagevalue` records the correct value of the page counter.

```

964 \zref@newprop*{pagevalue}[0]{\number\c@page}
965 \zref@newlist{perpage}
966 \zref@addprop{perpage}{abspage}
967 \zref@addprop{perpage}{page}
968 \zref@addprop{perpage}{pagevalue}
```

The page value, known by the reference mechanism, will be stored in counter `zpage`.

```

969 \newcounter{zpage}
```

Counter `zref@unique` helps in generating unique reference names.

```

970 \zref@require@unique
```

In order to be able to reset the counter, we hook here into `\stepcounter`. In fact two nested hooks are used to allow other packages to use the first hook at the beginning of `\stepcounter`.

```

971 \let\ZREF@org@stepcounter\stepcounter
972 \def\stepcounter#1{%
973   \ifcsname @stepcounterhook@#1\endcsname
974     \csname @stepcounterhook@#1\endcsname
975   \fi
976   \ZREF@org@stepcounter{#1}%
977 }
```

`\zmakeperpage` Makro `\zmakeperpage` resets a counter at each page break. It uses the same syntax and semantics as `\MakePerPage` from package `perpage` [5]. The initial start value can be given by the optional argument. Default is one that means after the first `\stepcounter` on a new page the counter starts with one.

```

978 \newcommand*{\zmakeperpage}[1]{%
979   \Ifnextchar[\ZREF@makeperpage@opt{\ZREF@makeperpage[\z@]}{%
980 }}
```

We hook before the counter is incremented in `\stepcounter`, package `perpage` afterwards. Thus a little calculation is necessary.

```

981 \def\ZREF@makeperpage@opt[#1]{%
982   \begingroup
983     \edef\x{\endgroup
984       \noexpand\ZREF@makeperpage[\number\numexpr#1-1\relax]%
985     }%
986   \x
987 }
988 \def\ZREF@makeperpage[#1]#2{%
989   \Ifundefined{@stepcounterhook@#2}{%
990     \expandafter\gdef\csname @stepcounterhook@#2\endcsname{}%
991   }{%
992     \expandafter\gdef\csname ZREF@perpage@#2\endcsname{%
993       \ZREF@perpage@step{#2}{#1}}%
994   }%
```

```

995   \expandafter\g@addto@macro\csname @stepcounterhook@#2\endcsname{%
996     \ifcsname ZREF@perpage@#2\endcsname
997       \csname ZREF@perpage@#2\endcsname
998     \fi
999   }%
1000 }

```

\ZREF@perpage@step The heart of this module follows.

```
1001 \def\ZREF@perpage@step#1#2{%
```

First the reference is generated.

```

1002   \global\advance\c@zref@unique\@ne
1003   \begingroup
1004     \expandafter\zref@labelbylist\expandafter{\thezref@unique}{perpage}%

```

The \expandafter commands are necessary, because \ZREF@temp is also used inside of \zref@labelbylist.

The evaluation of the reference follows. If the reference is not yet known, we use the page counter as approximation.

```

1005   \zref@ifrefundefined\thezref@unique{%
1006     \global\c@zpage=\c@page
1007     \global\let\thezpage\thepage
1008     \expandafter\xdef\csname ZREF@abspage@#1\endcsname{\number\c@abspage}%
1009   }%

```

The reference is used to set \thezpage and counter zpage.

```

1010   \global\c@zpage=\zref@extract\thezref@unique{pagevalue}\relax
1011   \xdef\thezpage{\noexpand\zref@extract{\thezref@unique}{page}}%
1012   \expandafter\xdef\csname ZREF@abspage@#1\endcsname{%
1013     \zref@extractdefault\thezref@unique{abspage}{\number\c@abspage}%
1014   }%
1015 }%

```

Page changes are detected by a changed absolute page number.

```

1016   \expandafter\ifx\csname ZREF@abspage@#1\expandafter\endcsname
1017     \csname ZREF@currentabspage@#1\endcsname
1018   \else
1019     \global\csname c@#1\endcsname=\#2\relax
1020     \global\expandafter\let
1021       \csname ZREF@currentabspage@#1\expandafter\endcsname
1022       \csname ZREF@abspage@#1\endcsname
1023   \fi
1024 \endgroup
1025 }

```

\zunmakeperpage Macro \zunmakeperpage cancels the effect of \zmakeperpage.

```

1026 \newcommand*\zunmakeperpage[1]{%
1027   \global\expandafter\let\csname ZREF@perpage@#1\endcsname\@undefined
1028 }%
1029 
```

6.13 Module titleref

```

1030 {*titleref}
1031 \NeedsTeXFormat{LaTeX2e}
1032 \ProvidesPackage{zref-titleref}%
1033 [2010/04/17 v2.12 Module titleref for zref (HO)]%
1034 \RequirePackage{zref-base}[2010/04/17]
1035 \@ifundefined{ZREF@baseok}{\endinput}{}%
1036 \RequirePackage{gettitledstring}[2009/12/08]

```

6.13.1 Implementation

	1037 \RequirePackage{keyval}
\zref@titleref@current	<p>This module makes section and caption titles available for the reference system. It uses some of the ideas of package <code>nameref</code> and <code>titleref</code>.</p> <p>Later we will redefine the section and caption macros to catch the current title and remember the value in <code>\zref@titleref@current</code>.</p>
	1038 \let\zref@titleref@current\@empty
	Now we can add the property <code>title</code> is added to the main property list.
	1039 \zref@newprop{title}{\zref@titleref@current}% 1040 \zref@addprop{ZREF@mainlist}{title}%
	The title strings go into the <code>.aux</code> file, thus they need some kind of protection. Package <code>titleref</code> uses a protected expansion method. The advantage is that this can be used to cleanup the string and to remove <code>\label</code> , <code>\index</code> and other macros unwanted for referencing. But there is the risk that fragile stuff can break.
	Therefore package <code>nameref</code> does not expand the string. Thus the entries can safely be written to the <code>.aux</code> file. But potentially dangerous macros such as <code>\label</code> remain in the string and can cause problems when using the string in references.
\ifzref@titleref@expand	<p>The switch <code>\ifzref@titleref@expand</code> distinguishes between the both methods. Package <code>nameref</code>'s behaviour is achieved by setting the switch to false, otherwise <code>titleref</code>'s expansion is used. Default is false.</p>
	1041 \newif\ifzref@titleref@expand
\ZREF@titleref@hook	<p>The hook <code>\ZREF@titleref@hook</code> allows to extend the cleanup for the expansion method. Thus unnecessary macros can be removed or dangerous commands removed. The hook is executed before the expansion of <code>\zref@titleref@current</code>.</p>
	1042 \let\ZREF@titleref@hook\@empty
\zref@titleref@cleanup	<p>The hook should not be used directly, instead we provide the macro <code>\zref@titleref@cleanup</code> to add stuff to the hook and prevents that a previous non-empty content is not discarded accidentally.</p>
	1043 \def\zref@titleref@cleanup#1{% 1044 \begingroup 1045 \toks@\expandafter{% 1046 \ZREF@titleref@hook 1047 #1% 1048 }% 1049 \expandafter\endgroup 1050 \expandafter\def\expandafter\ZREF@titleref@hook\expandafter{% 1051 \the\toks@ 1052 }% 1053 }%
\ifzref@titleref@stripperiod	<p>Sometimes a title contains a period at the end. Package <code>nameref</code> removes this. This behaviour is controlled by the switch <code>\ifzref@titleref@stripperiod</code> and works regardless of the setting of option <code>expand</code>. Period stripping is the default.</p>
	1054 \newif\ifzref@titleref@stripperiod 1055 \zref@titleref@stripperiodtrue
\zref@titleref@setcurrent	<p>Macro <code>\zref@titleref@setcurrent</code> sets a new current title stored in <code>\zref@titleref@current</code>. Some cleanup and expansion is performed that can be controlled by the previous switches.</p>
	1056 \def\zref@titleref@setcurrent#1{% 1057 \ifzref@titleref@expand 1058 \GetTitleStringExpand{#1}% 1059 \else 1060 \GetTitleStringNonExpand{#1}% 1061 \fi 1062 \edef\zref@titleref@current{%

```

1063     \detokenize\expandafter{\GetTitleStringResult}%
1064   }%
1065   \ifzref@titleref@stripperiod
1066     \edef\zref@titleref@current{%
1067       \expandafter\ZREF@stripperiod\zref@titleref@current
1068       \empty.\empty\@nil
1069     }%
1070   \fi
1071 }%
1072 \GetTitleStringDisableCommands{%
1073   \ZREF@titleref@hook
1074 }

```

\ZREF@stripperiod If \ZREF@stripperiod is called, the argument consists of space tokens and tokens with catcode 12 (other), because of ϵ - \TeX 's \detokenize.
 1075 \def\ZREF@stripperiod#1.\empty\@nil{#1}%

6.13.2 User interface

\ztitlerefsetup The behaviour of module titleref is controlled by switches and a hook. They can be set by \ztitlerefsetup with a key value interface, provided by package keyval. Also the current title can be given explicitly by the key title.

```

1076 \define@key{ZREF@TR}{expand}[true]{%
1077   \csname zref@titleref@expand#1\endcsname
1078 }%
1079 \define@key{ZREF@TR}{stripperiod}[true]{%
1080   \csname zref@titleref@stripperiod#1\endcsname
1081 }%
1082 \define@key{ZREF@TR}{cleanup}{%
1083   \zref@titleref@cleanup{#1}%
1084 }%
1085 \define@key{ZREF@TR}{title}{%
1086   \def\zref@titleref@current{#1}%
1087 }%
1088 \newcommand*\ztitlerefsetup{%
1089   \setkeys{ZREF@TR}%
1090 }

```

\ztitleref The user command \ztitleref references the title. For safety \label is disabled to prevent multiply defined references.
 1091 \newcommand*\ztitleref{%
 1092 \zref@wrapper@babel\ZREF@titleref
 1093 }%
 1094 \def\ZREF@titleref#1{%
 1095 \begingroup
 1096 \zref@refused{#1}%
 1097 \let\label\ltx@gobble
 1098 \zref@extract{#1}{title}%
 1099 \endgroup
 1100 }

6.13.3 Patches for section and caption commands

The section and caption macros are patched to extract the title data.

Captions of figures and tables.

```

1101 \AtBeginDocument{%
1102   \ZREF@patch{@caption}{%
1103     \long\def\@caption#1[#2]{%
1104       \zref@titleref@setcurrent{#2}%
1105       \ZREF@org@@caption{#1}[{#2}]%
1106     }%
1107   }%

```

Section commands without star. The title version for the table of contents is used because it is usually shorter and more robust.

```

1108  \ZREF@patch{@part}{%
1109    \def\@part[#1]{%
1110      \zref@titleref@setcurrent{#1}%
1111      \ZREF@org@@part[{#1}]%
1112    }%
1113  }%
1114  \ZREF@patch{@chapter}{%
1115    \def\@chapter[#1]{%
1116      \zref@titleref@setcurrent{#1}%
1117      \ZREF@org@@chapter[{#1}]%
1118    }%
1119  }%
1120  \ZREF@patch{@sect}{%
1121    \def\@sect#1#2#3#4#5#6[#7]{%
1122      \zref@titleref@setcurrent{#7}%
1123      \ZREF@org@@sect{#1}{#2}{#3}{#4}{#5}{#6}[{#7}]%
1124    }%
1125  }%

```

The star versions of the section commands.

```

1126  \ZREF@patch{@spart}{%
1127    \def\@spart#1{%
1128      \zref@titleref@setcurrent{#1}%
1129      \ZREF@org@@spart{#1}%
1130    }%
1131  }%
1132  \ZREF@patch{@schapter}{%
1133    \def\@schapter#1{%
1134      \zref@titleref@setcurrent{#1}%
1135      \ZREF@org@@schapter{#1}%
1136    }%
1137  }%
1138  \ZREF@patch{@ssect}{%
1139    \def\@ssect#1#2#3#4#5{%
1140      \zref@titleref@setcurrent{#5}%
1141      \ZREF@org@@ssect{#1}{#2}{#3}{#4}{#5}%
1142    }%
1143  }%

```

6.13.4 Class `memoir`

```

1144  \@ifclassloaded{memoir}{%
1145    \ltx@ifUndefined{ifheadnameref}{}{%
1146      \def\@chapter[#1]{%
1147        \ltx@ifUndefined{ch@pt@c}{%
1148          \zref@titleref@setcurrent{#1}%
1149        }{%
1150          \ifx\ch@pt@c\ltx@empty
1151            \zref@titleref@setcurrent{#2}%
1152          \else
1153            \def\NR@temp{#1}%
1154            \ifx\NR@temp\ltx@empty
1155              \expandafter\zref@titleref@setcurrent
1156              \expandafter{\ch@pt@c}%
1157            \else
1158              \ifheadnameref
1159                \zref@titleref@setcurrent{#1}%
1160              \else
1161                \expandafter\zref@titleref@setcurrent
1162                \expandafter{\ch@pt@c}%
1163              \fi

```

```

1164          \fi
1165          \fi
1166      }%
1167      \ZREF@org@@chapter[{\#1}]{\#2}%
1168  }%
1169  \ZREF@patch{M@sect}{%
1170  \def\M@sect#1#2#3#4#5#6[#7][#8]{%
1171  \ifheadnameref
1172  \zref@titleref@setcurrent{\#8}%
1173  \else
1174  \zref@titleref@setcurrent{\#7}%
1175  \fi
1176  \ZREF@org@M@sect{\#1}{\#2}{\#3}{\#4}{\#5}{\#6}{[\#7]}{[\#8]}%
1177  }%
1178  }%
1179  }%
1180 }{}}%

```

6.13.5 Class beamer

```

1181  \@ifclassloaded{beamer}{%
1182  \ZREF@patch{beamer@section}{%
1183  \long\def\beamer@section[{\#1}]{%
1184  \zref@titleref@setcurrent{\#1}%
1185  \ZREF@org@beamer@section[{\#1}]]%
1186  }%
1187  }%
1188  \ZREF@patch{beamer@subsection}{%
1189  \long\def\beamer@subsection[{\#1}]{%
1190  \zref@titleref@setcurrent{\#1}%
1191  \ZREF@org@beamer@subsection[{\#1}]]%
1192  }%
1193  }%
1194  \ZREF@patch{beamer@subsubsection}{%
1195  \long\def\beamer@subsubsection[{\#1}]{%
1196  \zref@titleref@setcurrent{\#1}%
1197  \ZREF@org@beamer@subsubsection[{\#1}]]%
1198  }%
1199  }%
1200 }{}}%

```

6.13.6 Package titlesec

```

1201  \@ifpackageloaded{titlesec}{%
1202  \ZREF@patch{ttl@sect@i}{%
1203  \def\ttl@sect@i#1#2[#3]{%
1204  \zref@titleref@setcurrent{\#4}%
1205  \ZREF@org@ttl@sect@i{\#1}{\#2}{[\#3]}{\#4}%
1206  }%
1207  }%
1208 }{}}%

```

6.13.7 Package longtable

Package `longtable`: some support for its `\caption`. However `\label` inside the caption is not supported.

```

1209  \@ifpackageloaded{longtable}{%
1210  \ZREF@patch{LT@c@ption}{%
1211  \def\LT@c@ption#1[#2]{%
1212  \ZREF@org@LT@c@ption{\#1}{[\#2]}{\#3}%
1213  \zref@titleref@setcurrent{\#2}%
1214  }%
1215  }%
1216 }{}}%

```

6.13.8 Package `listings`

Package `listings`: support for its caption.

```
1217  \@ifpackageloaded{listings}{%
1218    \ZREF@patch{\lst@MakeCaption}{%
1219      \def\lst@MakeCaption{%
1220        \ifx\lst@label\empty
1221        \else
1222          \expandafter\zref@titleref@setcurrent\expandafter{%
1223            \lst@@caption
1224          }%
1225        \fi
1226        \ZREF@org@\lst@MakeCaption
1227      }%
1228    }%
1229  }{}}%
```

6.13.9 Theorems

```
1230  \ZREF@patch{@opargbegintheorem}{%
1231    \def@opargbegintheorem#1#2#3{%
1232      \zref@titleref@setcurrent{#3}%
1233      \ZREF@org@@opargbegintheorem{#1}{#2}{#3}%
1234    }%
1235  }%
1236  \@ifpackageloaded{amsthm}{%
1237    \begingroup
1238      \edef\x{macro:\string#1\string#2[\string#3]}%
1239      \onelevel@sanitize\x
1240      \def\y#1->#2@nil{#1}%
1241      \edef\z{\expandafter\y\meaning\@begintheorem->\@nil}%
1242      \onelevel@sanitize\z
1243    \expandafter\endgroup
1244    \ifx\x\z
1245      \ZREF@patch{@begintheorem}{%
1246        \def@begintheorem#1#2[#3]{%
1247          \zref@titleref@setcurrent{#3}%
1248          \ZREF@org@begintheorem{#1}{#2}[{#3}]%
1249        }%
1250      }%
1251    \fi
1252  }{}}%
1253 }%
1254 </titleref>
```

6.14 Module `xr`

```
1255 <*xr>
1256 \NeedsTeXFormat{LaTeX2e}
1257 \ProvidesPackage{zref-xr}%
1258 [2010/04/17 v2.12 Module xr for zref (HO)]%
1259 \RequirePackage{zref-base}[2010/04/17]
1260 \@ifundefined{ZREF@baseok}{\endinput}{}%
1261 \RequirePackage{keyval}
1262 \RequirePackage{kvoptions}[2010/02/22]
```

We declare property `url`, because this is added, if a reference is imported and has not already set this field. Or if `hyperref` is used, then this property can be asked.

```
1263 \zref@newprop{url}{}%
1264 \zref@newprop{externaldocument}{}%
```

Most code, especially the handling of the .aux files are taken from David Carlisle's xr package. Therefore I drop the documentation for these macros here.

\zref@xr@ext If the URL is not specied, then assume processed file with a guessed extension. Use the setting of hyperref if available.

```
1265 \providecommand*\zref@xr@ext{%
1266   \ltx@ifundefined{ZREF@ext}{pdf}{\XR@ext}%
1267 }%
```

\ifZREF@xr@zreflabel The use of the star form of \zexternaldocument is remembered in the switch \ifZREF@xr@zreflabel.

```
1268 \newif\ifZREF@xr@zreflabel

1269 \SetupKeyvalOptions{%
1270   family=ZREF@XR,%
1271   prefix=ZREF@xr@%
1272 }
1273 \DeclareBoolOption[true]{tozreflabel}
1274 \DeclareBoolOption[false]{toltxlabel}
1275 \DeclareBoolOption[verbose]
1276 \define@key{ZREF@XR}{ext}{%
1277   \def\zref@xr@{\#1}%
1278 }
```

\zxrsetup

```
1279 \newcommand*\zxrsetup{%
1280   \setkeys{ZREF@XR}%
1281 }%
```

\zexternaldocument In its star form it looks for \newlabel, otherwise for \zref@newlabel. Later we will read .aux files that expects @ to have catcode 11 (letter).

```
1282 \newcommand*\zexternaldocument{%
1283   \zref@ifpropundefined{title}{%
1284     \zref@newprop{title}{}%
1285   }{}%
1286   \zref@ifpropundefined{anchor}{%
1287     \zref@newprop{anchor}{}%
1288     \ltx@ifundefined{@currentHref}{}{\@currentHref}%
1289   }%
1290 }{}%
1291 \zref@ifpropundefined{url}{%
1292   \zref@newprop{url}{}%
1293 }{}%
1294 \begingroup
1295   \csname @safe@actives@true\endcsname
1296   \makeatletter
1297   \@ifstar{%
1298     \ZREF@xr@zreflabelfalse
1299     \@testopt\ZREF@xr@externaldocument{}%
1300   }{%
1301     \ZREF@xr@zreflabeltrue
1302     \@testopt\ZREF@xr@externaldocument{}%
1303   }%
1304 }%
```

If the \include featur was used, there can be several .aux files. These files are read one after another, especially they are not recursively read in order to save read registers. Thus it can happen that the read order of the newlabel commands differs from L^AT_EX's order using \input.

\ZREF@xr@externaldocument It reads the remaining arguments. \newcommand comes in handy for the optional argument.

```

1305 \def\ZREF@xr@externaldocument[#1]#2{%
1306     \def\ZREF@xr@prefix{#1}%
1307     \let\ZREF@xr@filelist\@empty
1308     \edef\ZREF@xr@externalfile{#2}%
1309     \edef\ZREF@xr@file{\ZREF@xr@externalfile.aux}%
1310     \filename@parse{#2}%
1311     \c@testopt\ZREF@xr@graburl{#2}.\zref@xr@ext}%
1312 }%
1313 \def\ZREF@xr@graburl[#1]{%
1314     \edef\ZREF@xr@url{#1}%
1315     \ZREF@xr@checkfile
1316     \endgroup
1317 }%

```

\ZREF@xr@processfile We follow `xr` here, `\IfFileExists` offers a nicer test, but we have to open the file anyway.

```

1318 \def\ZREF@xr@checkfile{%
1319     \openin\@inputcheck\ZREF@xr@file\relax
1320     \ifeof\@inputcheck
1321         \PackageWarning{zref-xr}{%
1322             File '\ZREF@xr@file' not found or empty,\MessageBreak
1323             labels not imported}%
1324     }%
1325     \else
1326         \PackageInfo{zref-xr}{%
1327             Label \ifZREF@xr@zreflabel (zref) \fi import from '\ZREF@xr@file'}%
1328     }%
1329     \def\ZREF@xr@found{0}%
1330     \def\ZREF@xr@ignored@empty{0}%
1331     \def\ZREF@xr@ignored@zref{0}%
1332     \def\ZREF@xr@ignored@ltx{0}%
1333     \ZREF@xr@processfile
1334     \closein\@inputcheck
1335     \begingroup
1336         \let\on@line\@empty
1337         \PackageInfo{zref-xr}{%
1338             Statistics for '\ZREF@xr@file':\MessageBreak
1339             \ZREF@xr@found\space
1340             \ifZREF@xr@zreflabel zref\else LaTeX\fi\space
1341             label(s) found%
1342             \ifnum\ZREF@xr@ignored@empty>0 %
1343                 ,\MessageBreak
1344                 \ZREF@xr@ignored@empty\space empty label(s) ignored%
1345             \fi
1346             \ifnum\ZREF@xr@ignored@zref>0 %
1347                 ,\MessageBreak
1348                 \ZREF@xr@ignored@zref\space duplicated zref label(s) ignored%
1349             \fi
1350             \ifnum\ZREF@xr@ignored@ltx>0 %
1351                 ,\MessageBreak
1352                 \ZREF@xr@ignored@ltx\space duplicated latex label(s) ignored%
1353             \fi
1354         }%
1355     \endgroup
1356     \fi
1357     \ifx\ZREF@xr@filelist\@empty
1358     \else
1359         \edef\ZREF@xr@file{\expandafter\@car\ZREF@xr@filelist\@nil}%
1360         \edef\ZREF@xr@filelist{\expandafter\@cdr\ZREF@xr@filelist\@nil}%
1361         \expandafter\ZREF@xr@checkfile
1362     \fi
1363 }%

```

```

\ZREF@xr@processfile
1364 \def\ZREF@xr@processfile{%
1365   \read\@inputcheck to\ZREF@xr@line
1366   \expandafter\ZREF@xr@processline\ZREF@xr@line..\ZREF@nil
1367   \ifeof\@inputcheck
1368     \else
1369       \expandafter\ZREF@xr@processfile
1370     \fi
1371 }%
1372 \long\def\ZREF@xr@processline#1#2#3\ZREF@nil{%
1373   \def\x{\#1}%
1374   \toks0{\#2}%
1375   \ifZREF@xr@zreflabel
1376     \ifx\x\ZREF@xr@zref@newlabel
1377       \expandafter\ZREF@xr@process@zreflabel\ZREF@xr@line..\ZREF@nil
1378     \fi
1379   \else
1380     \ifx\x\ZREF@xr@newlabel
1381       \expandafter\ZREF@xr@process@label\ZREF@xr@line...[]\ZREF@nil
1382     \fi
1383   \fi
1384   \ifx\x\ZREF@xr@@input
1385     \edef\ZREF@xr@filelist{%
1386       \etex@unexpanded\expandafter{\ZREF@xr@filelist}%
1387       {\filename@area\the\toks@}%
1388     }%
1389   \fi
1390 }%
1391 \def\ZREF@xr@process@zreflabel\zref@newlabel#1#2#3\ZREF@nil{%
1392   \edef\ZREF@xr@refname{Z@R@{\ZREF@xr@prefix#1}}%
1393   \edef\ZREF@xr@found{\the\numexpr\ZREF@xr@found+1\relax}%
1394   \def\x{\#2}%
1395   \edef\ZREF@xr@tempname{$temp$}%
1396   \edef\ZREF@xr@temprefname{Z@R@{\ZREF@xr@tempname}}%
1397   \let\ZREF@xr@list\x
1398   \ifx\ZREF@xr@list\empty
1399     \PackageWarningNoLine{zref-xr}{%
1400       Label '#1' without properties ignored\MessageBreak
1401       in file '\ZREF@xr@file'%
1402     }%
1403     \edef\ZREF@xr@ignored@empty{%
1404       \the\numexpr\ZREF@xr@ignored@empty+1\relax
1405     }%
1406   \else
1407     \expandafter\ZREF@xr@checklist\x\ZREF@nil
1408     \expandafter\let\csname\ZREF@xr@temprefname\endcsname\x
1409     \expandafter\ltx@LocalAppendToMacro
1410     \csname\ZREF@xr@temprefname\expandafter\endcsname
1411     \expandafter{%
1412       \expandafter\externaldocument\expandafter{%
1413         \ZREF@xr@externalfile
1414       }%
1415     }%
1416     \ZREF@xr@urlcheck\ZREF@xr@tempname
1417     \ifZREF@xr@tozreflabel
1418       \@ifundefined{\ZREF@xr@refname}{%
1419         \ifZREF@xr@verbose
1420           \PackageInfo{zref-xr}{%
1421             Import to zref label '\ZREF@xr@tempname#1'
1422           }%

```

```

1423         \fi
1424         \global\expandafter
1425         \let\csname\ZREF@xr@refname\expandafter\endcsname
1426         \csname\ZREF@xr@temprefname\endcsname
1427     }{%
1428         \ZREF@xr@zref@ignorewarning{\ZREF@xr@prefix#1}%
1429     }%
1430     \fi
1431     \ifZREF@xr@toltxlabel
1432         \ZREF@xr@tolabel{\ZREF@xr@tempname}{\ZREF@xr@prefix#1}%
1433     \fi
1434     \fi
1435 }%
1436 \def\ZREF@xr@process@label\newlabel#1#2#3[#4]#5\ZREF@nil{%
1437     \def\ZREF@xr@refname{Z@R@ZREF@xr@prefix#1}%
1438     \edef\ZREF@xr@found{\the\numexpr\ZREF@xr@found+1\relax}%
1439     \def\x{#2}%
1440     \edef\ZREF@xr@tempname{$temp$}%
1441     \edef\ZREF@xr@temprefname{Z@R@ZREF@xr@tempname}%
1442     \expandafter\ZREF@xr@scanparams
1443         \csname\ZREF@xr@temprefname\expandafter\endcsname
1444         \x{}{}{}{}{}{}\\ZREF@nil
1445     \ifx\\#4\\%
1446     \else
1447         % ntheorem knows an optional argument at the end of \newlabel
1448         \zref@ifpropundefined{theotype}{%
1449             \zref@newprop{theotype}{}%
1450         }{}%
1451         \expandafter\ltx@LocalAppendToMacro
1452             \csname\ZREF@xr@temprefname\endcsname{\theotype{#4}}%
1453     \fi
1454     \expandafter\ltx@LocalAppendToMacro
1455         \csname\ZREF@xr@temprefname\expandafter\endcsname\expandafter{%
1456             \expandafter\externaldocument\expandafter{%
1457                 \ZREF@xr@externalfile
1458             }%
1459         }%
1460     \ZREF@xr@urlcheck{\ZREF@xr@prefix#1}%
1461     \ifZREF@xr@tozreflabel
1462         \@ifundefined{\ZREF@xr@refname}{%
1463             \ifZREF@xr@verbose
1464                 \PackageInfo{zref-xr}{%
1465                     Import to zref label '\ZREF@xr@prefix#1'%
1466                 }%
1467             \fi
1468             \global\expandafter
1469             \let\csname\ZREF@xr@refname\expandafter\endcsname
1470             \csname\ZREF@xr@temprefname\endcsname
1471         }{%
1472             \ZREF@xr@zref@ignorewarning{\ZREF@xr@prefix#1}%
1473         }%
1474     \fi
1475     \ifZREF@xr@toltxlabel
1476         \ZREF@xr@tolabel{\ZREF@xr@tempname}{\ZREF@xr@prefix#1}%
1477     \fi
1478 }%
1479 \def\ZREF@xr@zref@newlabel{\zref@newlabel}%
1480 \def\ZREF@xr@newlabel{\newlabel}%
1481 \def\ZREF@xr@input{\@input}%
1482 \def\ZREF@xr@relax{\relax}%

```

```

1483 \def\ZREF@xr@tolabel#1#2{%
1484   \ifZREF@xr@verbose
1485     \PackageInfo{zref-xr}{%
1486       Import to LaTeX label '#2'%
1487     }%
1488   \fi
1489   \expandafter\xdef\csname r@#2\endcsname{%
1490     {%
1491       \ltx@ifundefined{M@TitleReference}{%
1492         \ltx@ifundefined{TR@TitleReference}{%
1493           \zref@extractdefault{#1}{default}{}%
1494         }{%
1495           \noexpand\TR@TitleReference
1496           {\zref@extractdefault{#1}{default}{}%
1497           {\zref@extractdefault{#1}{title}{}%}
1498           }%
1499         }{%
1500           \noexpand\!M@TitleReference
1501           {\zref@extractdefault{#1}{default}{}%
1502           {\zref@extractdefault{#1}{title}{}%}
1503           }%
1504         }{%
1505           {\zref@extractdefault{#1}{page}{}%}
1506         \ltx@ifpackageloaded{nameref}{%
1507           {\zref@extractdefault{#1}{title}{}%}
1508           {\zref@extractdefault{#1}{anchor}{}%}
1509           {\zref@extractdefault{#1}{url}{}%}
1510         }{%
1511       }%
1512     }%

```

\ZREF@xr@zref@ignorewarning

```

1513 \def\ZREF@xr@zref@ignorewarning#1{%
1514   \PackageWarningNoLine{zref-xr}{%
1515     Zref label '#1' is already in use\MessageBreak
1516     in file '\ZREF@xr@file'%
1517   }%
1518   \edef\ZREF@xr@ignored@empty{%
1519     \the\numexpr\ZREF@xr@ignored+1%
1520   }%
1521 }%

```

\ZREF@xr@ltx@ignorewarning

```

1522 \def\ZREF@xr@ltx@ignorewarning#1{%
1523   \PackageWarningNoLine{zref-xr}{%
1524     LaTeX label '#1' is already in use\MessageBreak
1525     in file '\ZREF@xr@file'%
1526   }%
1527   \edef\ZREF@xr@ignored@ltx{%
1528     \the\numexpr\ZREF@xr@ignored@ltx+1%
1529   }%
1530 }%

```

\ZREF@xr@checklist

```

1531 \def\ZREF@xr@checklist#1#2#3\ZREF@nil{%
1532   \ifx\@undefined#1\relax
1533     \expandafter\ZREF@xr@checkkey\string#1\@nil
1534   \fi
1535   \ifx\@#3\%
1536     \else
1537       \ltx@ReturnAfterFi{%
1538         \ZREF@xr@checklist#3\ZREF@nil

```

```

1539      }%
1540      \fi
1541 }%
1542 \def\ZREF@xr@checkkey#1#2\@nil{%
1543   \zref@ifpropundefined{#2}{%
1544     \zref@newprop{#2}{}}%
1545   }{}}%
1546 }%

\ZREF@xr@scanparams

1547 \def\ZREF@xr@scanparams#1#2#3#4#5#6#7\ZREF@nil{%
1548   \let#1\@empty
1549   \ZREF@foundfalse
1550   \ZREF@xr@scantitleref#1#2\TR@TitleReference{}{}\ZREF@nil
1551   \ifZREF@found
1552   \else
1553     \ltx@LocalAppendToMacro#1{\default{#2}}%
1554   \fi
1555   % page
1556   \ltx@LocalAppendToMacro#1{\page{#3}}%
1557   % nameref title
1558   \ifZREF@found
1559   \else
1560     \ifx\\#4\\%
1561     \else
1562       \def\ZREF@xr@temp{#4}%
1563       \ifx\ZREF@xr@temp\ZREF@xr@relax
1564       \else
1565         \ltx@LocalAppendToMacro#1{\title{#4}}%
1566       \fi
1567     \fi
1568   \fi
1569   % anchor
1570   \ifx\\#5\\%
1571   \else
1572     \ltx@LocalAppendToMacro#1{\anchor{#5}}%
1573   \fi
1574   \ifx\\#6\\%
1575   \else
1576     \ltx@LocalAppendToMacro#1{\url{#6}}%
1577   \fi
1578 }%

\ZREF@xr@scantitleref

1579 \def\ZREF@xr@scantitleref#1#2\TR@TitleReference#3#4#5\ZREF@nil{%
1580   \ifx\\#5\\%
1581   \else
1582     \ltx@LocalAppendToMacro#1{%
1583       \default{#3}}%
1584       \title{#4}}%
1585   }%
1586   \ZREF@foundtrue
1587 \fi
1588 }%

\ZREF@xr@urlcheck

1589 \def\ZREF@xr@urlcheck#1{%
1590   \zref@ifrefcontainsprop{#1}{anchor}{%
1591     \zref@ifrefcontainsprop{#1}{url}{%
1592     }{}}%
1593     \expandafter
1594     \ltx@LocalAppendToMacro\csname Z@R@#1\expandafter\endcsname

```

```

1595      \expandafter{%
1596          \expandafter\url\expandafter{\ZREF@xr@url}%
1597      }%
1598  }{%
1599  }{%
1600  }{%
1601 }{%
1602 </xr>

```

6.15 Module `hyperref`

UNFINISHED :-(

```

1603 {*hyperref}
1604 \NeedsTeXFormat{LaTeX2e}
1605 \ProvidesPackage{zref-hyperref}%
1606 [2010/04/17 v2.12 Module hyperref for zref (HO)]%
1607 \RequirePackage{zref-base}[2010/04/17]
1608 \@ifundefined{ZREF@baseok}{\endinput}{}%
1609 \zref@newprop{anchor}[]{%
1610     \ltx@ifundefined{@currentHref}{}{\@currentHref}%
1611 }%
1612 \zref@addprop\ZREF@mainlist{anchor}%
1613 </hyperref>

```

6.16 Module `savepos`

Module `savepos` provides an interface for pdfTeX's `\pdfsavepos`, see the manual for pdfTeX.

6.16.1 Identification

```

1614 {*savepos}
1615 \NeedsTeXFormat{LaTeX2e}
1616 \ProvidesPackage{zref-savepos}%
1617 [2010/04/17 v2.12 Module savepos for zref (HO)]%
1618 \RequirePackage{zref-base}[2010/04/17]
1619 \ifundefined{ZREF@baseok}{\endinput}{}%

```

6.16.2 Availability

First we check, whether the feature is available.

```

1620 \ltx@IfUndefined{\pdfsavepos}{%
1621     \PackageError\ZREF@name{%
1622         string\pdfsavepos\space is not supported.\MessageBreak
1623         It is provided by pdfTeX (1.40) or XeTeX%
1624     }\ZREF@UpdatePdfTeX
1625     \endinput
1626 }{%

```

In PDF mode we are done. However support for DVI mode was added later in version 1.40.0. In earlier versions `\pdfsavepos` is defined, but its execution raises an error. Note that XeTeX also provides `\pdfsavepos`.

```

1627 \RequirePackage{ifpdf}
1628 \ifpdf
1629 \else
1630     \begingroup\expandafter\expandafter\expandafter\endgroup
1631     \expandafter\ifx\csname pdftexversion\endcsname\relax
1632     \else
1633         \ifnum\pdftexversion<140 %
1634             \PackageError\ZREF@name{%
1635                 string\pdfsavepos\space is not supported in DVI mode\MessageBreak

```

```

1636      of this pdfTeX version%
1637      } \ZREF@UpdatePdfTeX
1638      \expandafter\expandafter\expandafter\endinput
1639      \fi
1640      \fi
1641 \fi

```

6.16.3 Setup

```

1642 \zref@newlist{savepos}
1643 \zref@newprop*{posx}[0]{\the\pdflastxpos}
1644 \zref@newprop*{posy}[0]{\the\pdflastypos}
1645 \zref@addprop{savepos}{posx}
1646 \zref@addprop{savepos}{posy}

```

6.16.4 User macros

\zsavepos The current location is stored in a reference with the given name.

```

1647 \def\zsavepos#1{%
1648   @_bsphack
1649   \if@filesw
1650     \pdfsavepos
1651     \zref@labelbylist{#1}{savepos}%
1652   \fi
1653   @_esphack
1654 }

```

\zposx \zposy The horizontal and vertical position are available by \zposx and \zposy. Do not rely on absolute positions. They differ in DVI and PDF mode of pdfTeX. Use differences instead. The unit of the position numbers is sp.

```

1655 \newcommand*{\zposx}[1]{%
1656   \zref@extract{#1}{posx}%
1657 }%
1658 \newcommand*{\zposy}[1]{%
1659   \zref@extract{#1}{posy}%
1660 }%

```

Typically horizontal and vertical positions are used inside calculations. Therefore the extracting macros should be expandable and babel's patch is not applicable.

Also it is in the responsibility of the user to mark used positions by \zrefused in order to notify L^AT_EX about undefined references.

```
1661 </savepos>
```

6.17 Module dotfill

```

1662 {*dotfill}
1663 \NeedsTeXFormat{LaTeX2e}
1664 \ProvidesPackage{zref-dotfill}%
1665 [2010/04/17 v2.12 Module dotfill for zref (HO)]%
1666 \RequirePackage{zref-base}[2010/04/17]
1667 \ifundefined{ZREF@baseok}{\endinput}{}%

```

For measuring the width of \zdotfill we use the features provided by module savepos.

```
1668 \RequirePackage{zref-savepos}[2010/04/17]
```

For automatically generated label names we use the unique counter of module base.

```
1669 \zref@require@unique
```

Configuration is done by the key value interface of package keyval.

```
1670 \RequirePackage{keyval}
```

The definitions of the keys follow.

```

1671 \define@key{ZREF@DF}{unit}{%
1672   \def\ZREF@df@unit{\#1}%
1673 }
1674 \define@key{ZREF@DF}{min}{%
1675   \def\ZREF@df@min{\#1}%
1676 }
1677 \define@key{ZREF@DF}{dot}{%
1678   \def\ZREF@df@dot{\#1}%
1679 }

```

Defaults are set, see user interface.

```

1680 \providecommand\ZREF@df@min{2}
1681 \providecommand\ZREF@df@unit{.44em}
1682 \providecommand\ZREF@df@dot{.}

```

\zdotfillsetup Configuration of \zdotfill is done by \zdotfillsetup.

```

1683 \newcommand*\zdotfillsetup{\setkeys{ZREF@DF}}

```

\zdotfill \zdotfill sets labels at the left and the right to get the horizontal position.
\zsavepos is not used, because we do not need the vertical position.

```

1684 \newcommand*\zdotfill{%
1685   \leavevmode
1686   \global\advance\c@zref@unique\@ne
1687   \begingroup
1688     \def\ZREF@temp{\zref@\number\c@zref@unique}%
1689     \pdfsavepos
1690     \zref@labelbyprops{\thezref@unique L}{posx}%
1691     \setlength{\dimen@}{\ZREF@df@unit}%
1692     \zref@ifrefundefined{\thezref@unique R}{%
1693       \ZREF@dotfill
1694     }{%
1695       \ifnum\numexpr\zposx{\thezref@unique R}-\zposx{\thezref@unique L}\relax
1696         <\dimexpr\ZREF@df@min\dimen@\relax
1697         \hfill
1698       \else
1699         \ZREF@dotfill
1700       \fi
1701     }%
1702     \pdfsavepos
1703     \zref@labelbyprops{\thezref@unique R}{posx}%
1704   \endgroup
1705   \kern\z@%
1706 }

```

\ZREF@dotfill Help macro that actually sets the dots.

```

1707 \def\ZREF@dotfill{%
1708   \cleaders\hb@xt@\dimen@{\hss\ZREF@df@dot\hss}\hfill
1709 }

```

```

1710 </dotfill>

```

7 Test

7.1 \zref@localaddprop

```

1711 <*test1>
1712 \NeedsTeXFormat{LaTeX2e}
1713 \nofiles
1714 \documentclass{article}
1715 \usepackage{zref-base}[2010/04/17]
1716 \usepackage{qstest}
1717 \IncludeTests{*}

```

```

1718 \LogTests{log}{*}{*}
1719
1720 \makeatletter
1721 \begin{qstest}{localaddprop}{localaddprop}
1722   \Expect*{\Z@L@main}*{{default}{page}}%
1723   \zref@newprop{foobar}{FOO}%
1724   \zref@newlist{alist}%
1725   \Expect*{\Z@L@alist}{}
1726   \begingroup
1727     \zref@localaddprop{main}{foobar}%
1728     \Expect*{\Z@L@main}{{default}{page}{foobar}}%
1729     \zref@localaddprop{alist}{page}%
1730     \Expect*{\Z@L@alist}{{page}}%
1731   \endgroup
1732   \Expect*{\Z@L@main}*{{default}{page}}%
1733   \Expect*{\Z@L@alist}{}
1734 \end{qstest}
1735 @@end
1736 </test1>

```

7.2 Module runs

```

1737 {*test-runs}
1738 \NeedsTeXFormat{LaTeX2e}
1739 \documentclass{article}
1740 \usepackage{zref-runs}[2010/04/17]
1741 \usepackage{qstest}
1742 \IncludeTests{*}
1743 \LogTests{log}{*}{*}
1744
1745 \begin{qstest}{zruns-preamble}{zruns-preamble}
1746   \Expect{0}*{\zruns}%
1747 \end{qstest}
1748
1749 \AtBeginDocument{%
1750   \begin{qstest}{zruns-atbegindocument}{zruns-atbegindocument}%
1751     \Expect*{\number\ExpectRuns}*{\zruns}%
1752   \end{qstest}%
1753 }
1754
1755 \begin{document}
1756 \begin{qstest}{zruns-document}{zruns-document}
1757   \Expect*{\number\ExpectRuns}*{\zruns}%
1758 \end{qstest}
1759 \end{document}
1760 </test-runs>

```

7.3 Module titleref

```

1761 {*test-titleref-memoir}
1762 \NeedsTeXFormat{LaTeX2e}
1763 \documentclass{memoir}
1764 \usepackage{zref-titleref}[2010/04/17]
1765 \usepackage{qstest}
1766 \IncludeTests{*}
1767 \LogTests{log}{*}{*}
1768 \begin{document}
1769 \makeatletter
1770 \def\List{}
1771 \def\Label#1{%
1772   \zref@label{#1}%
1773   \g@addto@macro\List{%
1774     \par
1775     #1: [\ztitleref{#1}]%

```

```

1776  }%
1777  \mbox{ }%
1778  \zref@refused{#1}%
1779  \zref@ifrefundefined{#1}{%
1780  }{%
1781  \begingroup
1782  \edef\x{\zref@extract{#1}{title}}%
1783  \Expect{OK/}*{\expandafter\ltx@carthree\x{}{}{}\@nil}%
1784  \endgroup
1785  }%
1786 }%
1787 \def\Test#1{%
1788  \csname#1\endcsname*{OK/#1}%
1789  \Label{#1*}%
1790  \csname#1\endcsname{OK/#1}%
1791  \Label{#1}%
1792  \csname#1\endcsname[OK/#1-toc]%
1793  {WRONG-in-titleref/#1-toc-2}%
1794  \Label{#1-toc}%
1795  \expandafter\ifx\csname#1\endcsname\part
1796  \else
1797  \headnameref{false}
1798  \csname#1\endcsname[OK/#1-th-toc]%
1799  {WRONG-in-titleref/#1-th-toc-2}%
1800  {WRONG-in-titleref/#1-th-toc-3}%
1801  \Label{#1-th-toc}%
1802  \headnameref{true}
1803  \csname#1\endcsname[WRONG-in-titleref/#1-th-head-1]%
1804  [OK/#1-th-head]%
1805  {WRONG-in-titleref/#1-th-head-3}%
1806  \Label{#1-th-head}%
1807 \fi
1808 }%
1809 \begin{qstest}{section}{section}
1810  \@for\x:=part,chapter,section,subsection,subsubsection\do{%
1811  \expandafter\Test\expandafter{\x}%
1812 }%
1813 \end{qstest}
1814 \newpage
1815 \List
1816 \end{document}
1817
1818 </test-titleref-memoir>

```

8 Installation

8.1 Download

Package. This package is available on CTAN¹:

CTAN:macros/latex/contrib/oberdiek/zref.dtx The source file.

CTAN:macros/latex/contrib/oberdiek/zref.pdf Documentation.

Bundle. All the packages of the bundle ‘oberdiek’ are also available in a TDS compliant ZIP archive. There the packages are already unpacked and the documentation files are generated. The files and directories obey the TDS standard.

CTAN:install/macros/latex/contrib/oberdiek.tds.zip

TDS refers to the standard “A Directory Structure for TeX Files” (CTAN:tds/tds.pdf). Directories with `texmf` in their name are usually organized this way.

¹[ftp://ftp.ctan.org/tex-archive/](http://ftp.ctan.org/tex-archive/)

8.2 Bundle installation

Unpacking. Unpack the `oberdiek.tds.zip` in the TDS tree (also known as `texmf` tree) of your choice. Example (linux):

```
unzip oberdiek.tds.zip -d ~/texmf
```

Script installation. Check the directory `TDSScripts/oberdiek/` for scripts that need further installation steps. Package `attachfile2` comes with the Perl script `pdfatfi.pl` that should be installed in such a way that it can be called as `pdfatfi`. Example (linux):

```
chmod +x scripts/oberdiek/pdfatfi.pl  
cp scripts/oberdiek/pdfatfi.pl /usr/local/bin/
```

8.3 Package installation

Unpacking. The `.dtx` file is a self-extracting `docstrip` archive. The files are extracted by running the `.dtx` through plain `TEX`:

```
tex zref.dtx
```

TDS. Now the different files must be moved into the different directories in your installation TDS tree (also known as `texmf` tree):

<code>zref.sty</code>	→ <code>tex/latex/oberdiek/zref.sty</code>
<code>zref-base.sty</code>	→ <code>tex/latex/oberdiek/zref-base.sty</code>
<code>zref-abspage.sty</code>	→ <code>tex/latex/oberdiek/zref-abspage.sty</code>
<code>zref-counter.sty</code>	→ <code>tex/latex/oberdiek/zref-counter.sty</code>
<code>zref-dotfill.sty</code>	→ <code>tex/latex/oberdiek/zref-dotfill.sty</code>
<code>zref-hyperref.sty</code>	→ <code>tex/latex/oberdiek/zref-hyperref.sty</code>
<code>zref-lastpage.sty</code>	→ <code>tex/latex/oberdiek/zref-lastpage.sty</code>
<code>zref-marks.sty</code>	→ <code>tex/latex/oberdiek/zref-marks.sty</code>
<code>zref-nextpage.sty</code>	→ <code>tex/latex/oberdiek/zref-nextpage.sty</code>
<code>zref-perpage.sty</code>	→ <code>tex/latex/oberdiek/zref-perpage.sty</code>
<code>zref-runs.sty</code>	→ <code>tex/latex/oberdiek/zref-runs.sty</code>
<code>zref-savepos.sty</code>	→ <code>tex/latex/oberdiek/zref-savepos.sty</code>
<code>zref-thepage.sty</code>	→ <code>tex/latex/oberdiek/zref-thepage.sty</code>
<code>zref-titleref.sty</code>	→ <code>tex/latex/oberdiek/zref-titleref.sty</code>
<code>zref-totpages.sty</code>	→ <code>tex/latex/oberdiek/zref-totpages.sty</code>
<code>zref-user.sty</code>	→ <code>tex/latex/oberdiek/zref-user.sty</code>
<code>zref-xr.sty</code>	→ <code>tex/latex/oberdiek/zref-xr.sty</code>
<code>zref.pdf</code>	→ <code>doc/latex/oberdiek/zref.pdf</code>
<code>zref-example.tex</code>	→ <code>doc/latex/oberdiek/zref-example.tex</code>
<code>zref-example-lastpage.tex</code>	→ <code>doc/latex/oberdiek/zref-example-lastpage.tex</code>
<code>zref-example-nextpage.tex</code>	→ <code>doc/latex/oberdiek/zref-example-nextpage.tex</code>
<code>test/zref-test1.tex</code>	→ <code>doc/latex/oberdiek/test/zref-test1.tex</code>
<code>test/zref-test-runs.tex</code>	→ <code>doc/latex/oberdiek/test/zref-test-runs.tex</code>
<code>test/zref-test-titleref-memoir.tex</code>	→ <code>doc/latex/oberdiek/test/zref-test-titleref-memoir.tex</code>
<code>zref.dtx</code>	→ <code>source/latex/oberdiek/zref.dtx</code>

If you have a `docstrip.cfg` that configures and enables `docstrip`'s TDS installing feature, then some files can already be in the right place, see the documentation of `docstrip`.

8.4 Refresh file name databases

If your `TEX` distribution (`teTEX`, `mikTEX`, ...) relies on file name databases, you must refresh these. For example, `teTEX` users run `texhash` or `mktexlsr`.

8.5 Some details for the interested

Attached source. The PDF documentation on CTAN also includes the `.dtx` source file. It can be extracted by AcrobatReader 6 or higher. Another option is `pdftk`, e.g. unpack the file into the current directory:

```
pdftk zref.pdf unpack_files output .
```

Unpacking with L^AT_EX. The .dtx chooses its action depending on the format:

plain T_EX: Run docstrip and extract the files.

L^AT_EX: Generate the documentation.

If you insist on using L^AT_EX for docstrip (really, docstrip does not need L^AT_EX), then inform the autodetect routine about your intention:

```
latex \let\install=y\input{zref.dtx}
```

Do not forget to quote the argument according to the demands of your shell.

Generating the documentation. You can use both the .dtx or the .drv to generate the documentation. The process can be configured by the configuration file `ltxdoc.cfg`. For instance, put this line into this file, if you want to have A4 as paper format:

```
\PassOptionsToClass{a4paper}{article}
```

An example follows how to generate the documentation with pdflL^AT_EX:

```
pdflatex zref.dtx
makeindex -s gind.ist zref.idx
pdflatex zref.dtx
makeindex -s gind.ist zref.idx
pdflatex zref.dtx
```

9 References

- [1] Package `footmisc`, Robin Fairbairns, 2004/01/23 v5.3a.[CTAN:macros/latex/contrib/footmisc/footmisc.dtx](#)
- [2] Package `hyperref`, Sebastian Rahtz, Heiko Oberdiek, 2006/08/16 v6.75c.[CTAN:macros/latex/contrib/hyperref/](#)
- [3] Package `lastpage`, Jeff Goldberg, 1994/06/25 v0.1b.[CTAN:macros/latex/contrib/lastpage/](#)
- [4] Package `nameref`, Sebastian Rahtz, Heiko Oberdiek, 2006/02/12 v2.24.[CTAN:macros/latex/contrib/hyperref/nameref.dtx](#)
- [5] Package `perpage`, David Kastrup, 2002/12/20 v1.0.[CTAN:macros/latex/contrib/bigfoot/perpage.dtx](#)
- [6] Package `titleref`, Donald Arsenu, 2001/04/05 v3.1.[CTAN:macros/latex/contrib/misc/titleref.sty](#)
- [7] Package `totpages`, Wilhelm Müller, 1999/07/14 v1.00.[CTAN:macros/latex/contrib/totpages/](#)
- [8] Package `xr`, David Carlisle, 1994/05/28 v5.02.[CTAN:macros/latex-required/tools/xr.pdf](#)
- [9] Package `xr-hyper`, David Carlisle, 2000/03/22 v6.00beta4.[CTAN:macros/latex/contrib/hyperref/xr-hyper.sty](#)

10 History

[2006/02/20 v1.0]

- First version.

[2006/05/03 v1.1]

- Module `perpage` added.
- Module redesign as packages.

[2006/05/25 v1.2]

- Module `dotfillmin` added.
- Module `base`: macros `\zref@require@unique` and `\thezref@unique` added (used by modules `titleref` and `dotfillmin`).

[2006/09/08 v1.3]

- Typo fixes and English cleanup by Per Starback.

[2007/01/23 v1.4]

- Typo in macro name fixed in documentation.

[2007/02/18 v1.5]

- `\zref@getcurrent` added (suggestion of Igor Akkerman).
- Module `savepos` also supports Xe^TE_X.

[2007/04/06 v1.6]

- Fix in modules `abspage` and `base`: Now counter `abspage` and `zref@unique` are not remembered by `\include`.
- Beamer support for module `titleref`.

[2007/04/17 v1.7]

- Package `atbegshi` replaces `everyshi`.

[2007/04/22 v1.8]

- `\zref@wrapper@babel` and `\zref@refused` are now expandable if `babel` is not used or `\if@safec@actives` is already set to true. (Feature request of Josselin Noirel)

[2007/05/02 v1.9]

- Module `titleref`: Some support for `\caption` of package `longtable`, but only if `\label` is given after `\caption`.

[2007/05/06 v2.0]

- Uses package `etexcmds` for accessing ε -T_EX's `\unexpanded`.

[2007/05/28 v2.1]

- Module `titleref` supports caption of package `listings`.
- Fixes in module `titleref` for support of packages `titlesec` and `longtable`.

[2008/09/21 v2.2]

- Module `base`: `\zref@iflistcontainsprop` is documented, but a broken `\zref@listcontainsprop` implemented. Name and implementation fixed (thanks Ohad Kammar).

[2008/10/01 v2.3]

- `\zref@localaddprop` added (feature request of Ohad Kammar).
- Module `lastpage`: list ‘LastPage’ added. Label ‘LastPage’ will use the properties of this list (default is empty) along with the properties of the main list.

[2009/08/07 v2.4]

- Module `runs` added.

[2009/12/06 v2.5]

- Module `lastpage`: Uses package `atveryend`.
- Module `titleref`: Further commands are disabled during string expansion, imported from package `nameref`.

[2009/12/07 v2.6]

- Version date added for package `atveryend`.

[2009/12/08 v2.7]

- Module `titleref`: Use of package `gettitlestring`.

[2010/03/26 v2.8]

- `\zifrefundefined` added.
- Module `lastpage`: Macros `\zref@iflastpage` and `\ziflastpage` added.
- Module `thepage` added.
- Module `nextpage` added.

[2010/03/29 v2.9]

- Module `marks` added (without documentation).
- `\zref@addprop` now adds expanded property to list.
- Useless `\ZREF@ErrorNoLine` removed.

[2010/04/08 v2.10]

- Module `xr` remembers the external document name in property ‘external-document’.

[2010/04/15 v2.11]

- Module `titleref`: Better support of class `memoir`.
- Module `titleref`: Support of theorems.

- Module base: `\zref@newprop` ensures global empty default.
- Module xr: Setup options `tozreflabel` and `toltxlabel` added.

11 Index

Numbers written in italic refer to the page where the corresponding entry is described; numbers underlined refer to the code line of the definition; numbers in roman refer to the code lines where the entry is used.

Symbols	
<code>\@end</code>	1735
<code>\@addtoreset</code>	582, 647
<code>\@auxout</code>	450
<code>\@begintheorem</code>	1241, 1246
<code>\@bsphack</code>	406, 416, 1648
<code>\@caption</code>	1103
<code>\@car</code>	880, 1359
<code>\@cdr</code>	882, 1360
<code>\@chapter</code>	1115, 1146
<code>\@currentHref</code>	1288, 1610
<code>\@currentlabel</code>	606
<code>\@ehc</code>	269, 283, 369, 865
<code>\@empty</code>	263, 377, 454, 528, 610, 1038, 1042, 1068, 1075, 1220, 1307, 1336, 1357, 1398, 1548
<code>\@esphack</code>	413, 433, 1653
<code>\@for</code>	420, 1810
<code>\@ifclassloaded</code>	1144, 1181
<code>\@ifdefinable</code>	262
<code>\@ifnextchar</code>	384, 979
<code>\@ifpackageloaded</code>	1201, 1209, 1217, 1236
<code>\@ifstar</code>	373, 1297
<code>\@ifundefined</code>	192, 580, 617, 644, 662, 681, 719, 750, 838, 853, 962, 989, 1035, 1260, 1418, 1462, 1608, 1619, 1667
<code>\@input</code>	1481
<code>\@inputcheck</code>	1319, 1320, 1334, 1365, 1367
<code>\@latex@warning</code>	500
<code>\@mainaux</code>	950
<code>\@namedef</code>	387
<code>\@ne</code>	1002, 1686
<code>\@newl@bel</code>	258
<code>\@nil</code> ...	880, 882, 1068, 1075, 1240, 1241, 1359, 1360, 1533, 1542, 1783
<code>\@onelevel@sanitize</code>	1239, 1242
<code>\@opargbegintheorem</code>	1231
<code>\@part</code>	1109
<code>\@schapter</code>	1133
<code>\@sect</code>	1121
<code>\@spart</code>	1127
<code>\@ssect</code>	1139
<code>\@testopt</code>	1299, 1302, 1311
<code>\@tfor</code>	293, 308, 455
<code>\@undefined</code>	1027, 1532
<code>\\\</code>	27, 28, 29, 30, 153, 155, 157, 158, 170, 173, 1445, 1535, 1560, 1570, 1574, 1580
<code>_</code>	46, 47
A	
<code>\AddLineBeginAux</code>	254
<code>\advance</code>	686, 1002, 1686
<code>\afterassignment</code>	758, 762
<code>\AfterLastShipout</code>	683
<code>\Alph</code>	7
<code>\anchor</code>	1572
<code>\AtBeginDocument</code>	665, 844, 944, 1101, 1749
<code>\AtBeginShipout</code>	651, 724
<code>\AtEndOfPackage</code>	195
B	
<code>\beamer@section</code>	1183
<code>\beamer@subsection</code>	1189
<code>\beamer@subsubsection</code>	1195
<code>\begin</code> 25, 59, 102, 108, 156, 172, 1721, 1745, 1750, 1755, 1756, 1768, 1809	
<code>\bfseries</code>	599
C	
<code>\c@abspage</code>	654, 1008, 1013
<code>\c@page</code>	686, 964, 1006
<code>\c@zpage</code>	1006, 1010
<code>\c@zref@unique</code> .	586, 1002, 1686, 1688
<code>\ch@pt@c</code>	1150, 1156, 1162
<code>\chapter</code>	26, 32, 34, 63, 84
<code>\ChapterPages</code>	93, 113
<code>\ChapterStart</code>	80, 135, 150, 166
<code>\ChapterStop</code>	87, 148, 165, 184
<code>\chardef</code>	780, 795, 804, 808
<code>\leaders</code>	1708
<code>\cleardoublepage</code>	81, 88
<code>\clearpage</code>	64
<code>\closein</code>	1334
<code>\comma@entry</code> ...	886, 887, 888, 894, 897
<code>\comma@parse</code>	885
<code>\csname</code>	223, 226, 227, 263, 273, 287, 312, 326, 340, 359, 388, 389, 390, 394, 397, 400, 410, 457, 459, 464, 465, 481, 508, 519, 520, 522, 541, 542, 543, 567, 915, 923, 974, 990,

\gdef	390, 394, 951, 990, 992
\GetTitleStringDisableCommands	1072
\GetTitleStringExpand	1058
\GetTitleStringNonExpand	1060
\GetTitleStringResult	1063
H	
\hb@xt@	1708
\headnameref{false}	1797
\headnameref{true}	1802
\hfill	1697, 1708
\hss	1708
I	
\if@filesw	445, 684, 949, 1649
\if@safe@actives	560
\ifcase	116, 816, 886
\ifcsname	554, 973, 996
\ifeof	1320, 1367
\ifetex@unexpanded	241, 345
\ifheadnameref	1158, 1171
\ifnum	698, 791, 801, 807, 858, 911, 1342, 1346, 1350, 1633, 1695
\ifodd	125
\ifpdf	1628
\ifx	223, 273, 296, 359, 456, 481, 527, 619, 868, 877, 881, 886, 887, 888, 1016, 1150, 1154, 1220, 1244, 1357, 1376, 1380, 1384, 1398, 1445, 1532, 1535, 1560, 1563, 1570, 1574, 1580, 1631, 1795
\ifZREF@found	220, 301, 1551, 1558
\ifZREF@immediate	435, 447, 451, 457
\ifzref@titleref@expand	1041, 1057
\ifzref@titleref@stripperiod	1054, 1065
\ifZREF@xr@toltxlabel	1431, 1475
\ifZREF@xr@tozreflabel	1417, 1461
\ifZREF@xr@verbose	1419, 1463, 1484
\ifZREF@xr@zreflabel	1268, 1327, 1340, 1375
\immediate	440, 950
\IncludeTests	1717, 1742, 1766
\item	109, 112, 114, 122, 126, 128
K	
\kern	1705
\kv@key	880, 882, 883, 897
\kv@parse	876
\kv@value	877, 878, 885
L	
\l	418
\Label	1771, 1789, 1791, 1794, 1801, 1806
\label	619, 1097
\leavevmode	1685
\List	1770, 1773, 1815
\LogTests	1718, 1743, 1767
\lst@caption	1223
\lst@label	1220
\lst@MakeCaption	1219
\LT@c@ption	1211
\ltx@carthree	1783
F	
\fancyhead	53, 56
\fancyhf	52, 55
\fancypagestyle	54
\filename@area	1387
\filename@parse	1310
\foo	20, 31, 33, 35
\frontmatter	60, 105
G	
\g@addto@macro	326, 348, 995, 1773
\G@refundefinedtrue	499

\ltx@empty	868, 1150, 1154	\openin	1319
\ltx@firstofone	228, 550, 552, 555		
\ltx@firstoftwo		P	
	. 274, 302, 360, 482, 531, 563, 700	\PackageError	232, 243, 267, 281, 367, 859, 1621, 1634
\ltx@gobble	224, 619, 620, 899, 1097	\PackageInfo	264, 382, 948, 1326, 1337, 1420, 1464, 1485
\ltx@gobbletwo	582, 647, 901	\PackageWarning	321, 336, 422, 889, 930, 1321
\ltx@ifpackageloaded	1506	\PackageWarningNoLine	1399, 1514, 1523
\ltx@ifUndefined		\page	1556
	. 231, 590, 729, 1145, 1147, 1620	\pagestyle	51
\ltx@ifundefined		\par	1774
	. 1266, 1288, 1491, 1492, 1610	\part	1795
\ltx@LocalAppendToMacro		\pdflastxpos	1643
	. 1409, 1451, 1454, 1553,	\pdflastypos	1644
	1556, 1565, 1572, 1576, 1582, 1594	\pdfsavepos	1622, 1635, 1650, 1689, 1702
\ltx@ReturnAfterFi	1537	\pdftexversion	1633
\ltx@secondoftwo	276, 304,	\ProcessOptions	211
	362, 484, 516, 529, 557, 561, 702	\protect	499
\ltx@space	801, 807, 860, 888, 931	\protected@write	450
\ltx@zero	858, 911	\providecommand	
			. 255, 943, 1265, 1680, 1681, 1682
	M	\ProvidesPackage	
\m@ne	686		. 189, 215, 614, 641, 659,
\M@sect	1170		676, 716, 747, 835, 850, 941,
\M@TitleReference	1500		959, 1032, 1257, 1605, 1616, 1664
\mainmatter	62, 134		
\makeatletter		R	
	. 11, 76, 103, 1296, 1720, 1769	\read	1365
\makeatother	18, 101	\refstepcounter	667
\makebox	169, 170	\renewcommand	7, 48, 585
\mbox	1777	\RequirePackage	
\meaning	1241		. 191, 196, 217, 240, 245,
\MessageBreak			253, 616, 643, 645, 661, 678,
	. 244, 861, 864, 891, 893, 932,		679, 680, 718, 720, 721, 749,
	933, 1322, 1338, 1343, 1347,		751, 752, 753, 754, 837, 839,
	1351, 1400, 1515, 1524, 1622, 1635		840, 852, 854, 961, 963, 1034,
	N		1036, 1037, 1259, 1261, 1262,
\NeedsTeXFormat	3, 188, 214,		1607, 1618, 1627, 1666, 1668, 1670
	613, 640, 658, 675, 715, 746,	\reset@font	599
	834, 849, 940, 958, 1031, 1256,	\rightarrowarrow	47
	1604, 1615, 1663, 1712, 1738, 1762	\romannumeral	869
\newcommand	20, 80, 87,		
	93, 167, 487, 618, 625, 634, 637,	S	
	705, 740, 757, 771, 774, 775,	\section	65, 137, 145
	841, 855, 978, 1026, 1088, 1091,	\setcounter	650
	1279, 1282, 1655, 1658, 1683, 1684	\setkeys	1089, 1280, 1683
\newcounter	6, 583, 648, 969	\setlength	1691
\newif	220, 435, 1041, 1054, 1268	\SetupKeyvalOptions	1269
\newlabel	1436, 1447, 1480	\space	501, 1339,
\newmarks	864		1340, 1344, 1348, 1352, 1622, 1635
\newpage	143, 1814	\stepcounter	21, 652, 971, 972
\nfss@text	599		
\nofiles	1713	T	
\NR@temp	1153, 1154	\tableofcontents	61, 132
\number	96,	\Test	1787, 1811
	111, 586, 591, 730, 945, 964,	\the	13, 153, 155, 427,
	984, 1008, 1013, 1688, 1751, 1757		432, 463, 477, 593, 654, 692,
\numexpr	96, 111,		726, 732, 788, 1051, 1387, 1393,
	116, 593, 732, 788, 945, 984,		1404, 1438, 1519, 1528, 1643, 1644
	1393, 1404, 1438, 1519, 1528, 1695	\thechapter	14
	O	\thefoo	7, 12, 22
\on@line	947, 1336		

\theotype 1452
 \thepage 45,
 46, 47, 448, 452, 501, 607, 1007
 \thezpage 14, 1007, 1011
 \thezref@unique
 9, 585, 1004, 1005, 1010,
 1011, 1013, 1690, 1692, 1695, 1703
 \title 1565, 1584
 \toks@ 419, 426,
 427, 432, 461, 463, 476, 477,
 687, 692, 1045, 1051, 1374, 1387
 \TR@TitleReference .. 1495, 1550, 1579
 \ttl@sect@i 1203

U

\unexpanded 244, 249
 \UniqueCounterCall 772
 \UniqueCounterNew 755
 \url 1576, 1596
 \usepackage 9, 43, 50, 72, 74,
 1715, 1716, 1740, 1741, 1764, 1765

V

\value 13, 726
 \verb 173

W

\write 439, 440, 950

X

\x 293, 295, 296, 420, 421, 423,
 427, 568, 570, 814, 830, 913,
 918, 921, 927, 983, 986, 1238,
 1239, 1244, 1373, 1376, 1380,
 1384, 1394, 1397, 1407, 1408,
 1439, 1444, 1782, 1783, 1810, 1811
 \XR@ext 1266

Y

\y 292, 296, 1240, 1241

Z

\z 1241, 1242, 1244
 \z@ 979, 1705
 \Z@D@page 775
 \Z@L@alist 1725, 1730, 1733
 \Z@L@LastPage 689
 \Z@L@main 688, 1722, 1728, 1732
 \zdotfill 15, 170, 173, 1684
 \zdotfillsetup 15, 1683
 \zexternaldocument 16, 1282
 \ziflastpage 10, 705
 \zifrefundefined 7, 487
 \zlabel 9, 85, 106, 138, 146, 618
 \zmakeperpage 13, 978
 \znexpage 12, 53, 56, 771
 \znexpagesetup 12, 44, 757
 \znonextpagename 48, 774, 822
 \zpageref 9, 127, 634
 \zposx 15, 153, 1655, 1695
 \zposy 15, 155, 1655
 \zref 9, 27, 28, 29,
 30, 113, 115, 124, 129, 139, 625, 635

\ZREF@@@newprop 389, 393
 \ZREF@@@makeperpage 979, 984, 988
 \ZREF@@@newprop 384, 386
 \ZREF@@@perpage@step 993, 1001
 \zref@addprop
 5, 15, 16, 17, 78, 317, 608,
 609, 655, 664, 723, 897, 966,
 967, 968, 1040, 1612, 1645, 1646
 \ZREF@addtoks 475
 \ZREF@baseok 610
 \ZREF@call 780, 795, 804, 808, 816
 \zref@default 7, 384, 596, 598
 \ZREF@df@dot 1678, 1682, 1708
 \ZREF@df@min 1675, 1680, 1696
 \ZREF@df@unit 1672, 1681, 1691
 \ZREF@dotfill 1693, 1699, 1707
 \ZREF@extract 506, 511
 \zref@extract 7, 97,
 98, 111, 140, 505, 632, 735, 826,
 1010, 1011, 1098, 1656, 1659, 1782
 \zref@extractdefault .. 7, 117, 118,
 512, 535, 698, 699, 784, 799,
 842, 1013, 1493, 1496, 1497,
 1501, 1502, 1505, 1507, 1508, 1509
 \ZREF@foundfalse 291, 1549
 \ZREF@foundtrue 297, 1586
 \zref@getcurrent 6, 399
 \ZREF@gtemp 347, 348, 349
 \ZREF@iflastpage 706, 708, 708
 \zref@iflastpage 10, 697, 711
 \ZREF@iflistcontainsprop ... 287, 289
 \zref@iflistcontainsprop
 5, 286, 320, 335
 \zref@iflistundefined 5, 261, 272, 280
 \zref@ifpropundefined
 6, 358, 366, 421,
 910, 1283, 1286, 1291, 1448, 1543
 \ZREF@ifrefcontainsprop ... 518, 526
 \zref@ifrefcontainsprop
 7, 514, 1590, 1591
 \ZREF@ifrefundefined
 488, 490, 781, 792, 802
 \zref@ifrefundefined .. 7, 480, 492,
 498, 515, 536, 793, 1005, 1692, 1779
 \ZREF@immediatetrue 438
 \ZREF@l@addto@macro 340, 345
 \ZREF@label 408, 432, 444, 692
 \zref@label 6, 402, 622, 1772
 \zref@labelbylist
 6, 403, 405, 726, 1004, 1651
 \zref@labelbyprops
 6, 90, 415, 779, 1690, 1703
 \zref@listexists 5, 279, 318, 333, 407
 \zref@listforloop 307
 \zref@localaddprop .. 5, 332, 1727, 1729
 \ZREF@mainlist 403, 602,
 605, 608, 609, 655, 664, 1040, 1612
 \ZREF@makeperpage@opt 979, 981
 \ZREF@MARKS@DefineProp
 873, 874, 875, 909
 \zref@marks@register 855, 860, 892, 931

\ZREF@name 218,
 232, 243, 267, 281, 321, 336,
 367, 422, 859, 889, 930, 1621, 1634
 \ZREF@NAME@bot 888, 908
 \ZREF@NAME@first 887, 907
 \ZREF@NAME@top 886, 906
 \zref@newlabel
 6, 255, 257, 470, 1391, 1479
 \zref@newlist 5, 260,
 605, 682, 722, 883, 965, 1642, 1724
 \ZREF@newprop 375, 378, 381
 \zref@newprop 6,
 12, 13, 14, 77, 372, 606, 607,
 654, 663, 914, 922, 964, 1039,
 1263, 1264, 1284, 1287, 1292,
 1449, 1544, 1609, 1643, 1644, 1723
 \ZREF@nextpage 772, 776
 \ZREF@nil 394, 528, 543, 1366, 1372,
 1377, 1381, 1391, 1407, 1436,
 1444, 1531, 1538, 1547, 1550, 1579
 \ZREF@NOVALUE 534
 \ZREF@novalue 527, 528, 534
 \ZREF@np@call@next 766, 770, 825
 \ZREF@np@call@nonext .. 763, 769, 821
 \ZREF@np@call@unknown .. 759, 768, 817
 \ZREF@np@setup@i 758, 761
 \ZREF@np@setup@ii 762, 765
 \ZREF@number 590, 857
 \ZREF@org@@begintheorem 1248
 \ZREF@org@@caption 1105
 \ZREF@org@@chapter 1117, 1167
 \ZREF@org@@opargbegintheorem .. 1233
 \ZREF@org@@part 1111
 \ZREF@org@@schapter 1135
 \ZREF@org@@sect 1123
 \ZREF@org@@spart 1129
 \ZREF@org@@ssect 1141
 \ZREF@org@beamer@section 1185
 \ZREF@org@beamer@subsection ... 1191
 \ZREF@org@beamer@subsubsection 1197
 \ZREF@org@lst@MakeCaption 1226
 \ZREF@org@LT@c@option 1212
 \ZREF@org@M@sect 1176
 \ZREF@org@refstepcounter 669
 \ZREF@org@stepcounter 971, 976
 \ZREF@org@thepage 448, 452
 \ZREF@org@ttl@sect@i 1205
 \ZREF@org@write 439, 440
 \ZREF@P ... 383, 387, 388, 389, 390,
 391, 394, 455, 457, 459, 464, 465
 \ZREF@pagenum@last 798, 801
 \ZREF@pagenum@this
 783, 788, 791, 801, 807
 \ZREF@patch 221, 666,
 1102, 1108, 1114, 1120, 1126,
 1132, 1138, 1169, 1182, 1188,
 1194, 1202, 1210, 1218, 1230, 1245
 \zref@prop 309, 314
 \zref@propexists 6, 319, 334, 365, 626
 \ZREF@refname@next . 786, 793, 802, 826
 \ZREF@refname@this . 778, 779, 781, 784
 \ZREF@refused 495, 497
 \zref@refused ... 7, 491, 494, 631,
 637, 709, 710, 738, 845, 1096, 1778
 \zref@require@unique 9, 579, 970, 1669
 \zref@setcurrent . 6, 83, 391, 396, 668
 \zref@setdefault 7, 595, 598
 \zref@setmainlist 8, 601
 \ZREF@STAR 881, 905
 \ZREF@stripperiod 1067, 1075
 \ZREF@temp 193, 200,
 201, 202, 203, 204, 205, 206,
 207, 208, 209, 210, 325, 327,
 454, 461, 462, 470, 880, 881, 1688
 \ZREF@TempName 856, 868,
 869, 871, 897, 910, 914, 922, 933
 \ZREF@TempNum
 857, 858, 862, 869, 911, 924
 \zref@thepage 11, 734, 742
 \zref@thepage@name
 11, 729, 735, 738, 787
 \zref@thepage@refused 737, 741
 \ZREF@titleref 1092, 1094
 \zref@titleref@cleanup .. 1043, 1083
 \zref@titleref@current
 1038, 1039, 1062, 1066, 1067, 1086
 \ZREF@titleref@hook
 1042, 1046, 1050, 1073
 \zref@titleref@setcurrent
 1056, 1104,
 1110, 1116, 1122, 1128, 1134,
 1140, 1148, 1151, 1155, 1159,
 1161, 1172, 1174, 1184, 1190,
 1196, 1204, 1213, 1222, 1232, 1247
 \zref@titleref@stripperiodtrue 1055
 \ZREF@unexpanded 537, 539, 548, 550, 552
 \ZREF@UpdatePdfTeX ... 219, 1624, 1637
 \ZREF@wrapper@babel 570, 576
 \zref@wrapper@babel 8, 140,
 488, 495, 553, 622, 627, 706, 1092
 \zref@wrapper@immediate
 8, 89, 436, 691, 725
 \zref@wrapper@unexpanded 8, 547
 \ZREF@X 374, 377, 388
 \zref@xr@ 1277
 \ZREF@xr@input 1384, 1481
 \ZREF@xr@checkfile .. 1315, 1318, 1361
 \ZREF@xr@checkkey 1533, 1542
 \ZREF@xr@checklist 1407, 1531
 \zref@xr@ext 16, 1265, 1311
 \ZREF@xr@externaldocument
 1299, 1302, 1305
 \ZREF@xr@externalfile
 1308, 1309, 1413, 1457
 \ZREF@xr@file ... 1309, 1319, 1322,
 1327, 1338, 1359, 1401, 1516, 1525
 \ZREF@xr@filelist
 1307, 1357, 1359, 1360, 1385, 1386
 \ZREF@xr@found . 1329, 1339, 1393, 1438
 \ZREF@xr@graburl 1311, 1313
 \ZREF@xr@ignored 1519
 \ZREF@xr@ignored@empty
 1330, 1342, 1344, 1403, 1404, 1518

\ZREF@xr@ignored@ltx
.... 1332, 1350, 1352, 1527, 1528
\ZREF@xr@ignored@zref 1331, 1346, 1348
\ZREF@xr@line .. 1365, 1366, 1377, 1381
\ZREF@xr@list 1397, 1398
\ZREF@xr@ltx@ignorewarning 1522
\ZREF@xr@newlabel 1380, 1480
\ZREF@xr@prefix . 1306, 1392, 1428,
1432, 1437, 1460, 1465, 1472, 1476
\ZREF@xr@process@label .. 1381, 1436
\ZREF@xr@process@zreflabel 1377, 1391
\ZREF@xr@processfile 1318, 1364
\ZREF@xr@processline 1366, 1372
\ZREF@xr@refname
1392, 1418, 1425, 1437, 1462, 1469
\ZREF@xr@relax 1482, 1563
\ZREF@xr@scanparams 1442, 1547
\ZREF@xr@scantitleref ... 1550, 1579
\ZREF@xr@temp 1562, 1563
\ZREF@xr@tempname ... 1395, 1396,
1416, 1421, 1432, 1440, 1441, 1476
\ZREF@xr@tempprefname
..... 1396, 1408, 1410,
1426, 1441, 1443, 1452, 1455, 1470
\ZREF@xr@tolabel ... 1432, 1476, 1483
\ZREF@xr@url 1314, 1596
\ZREF@xr@urlcheck ... 1416, 1460, 1589
\ZREF@xr@zref@ignorewarning
..... 1428, 1472, 1513
\ZREF@xr@zref@newlabel .. 1376, 1479
\ZREF@xr@zreflabelfalse 1298
\ZREF@xr@zreflabeltrue 1301
\ZREF@zref 627, 630
\zrefused . 9, 94, 95, 161, 162, 163, 637
\zruns 13, 943, 1746, 1751, 1757
\zsavepos 15, 157, 158, 1647
\zthepage 11, 740
\ztitleref 14, 1091, 1775
\ztitlerefsetup 14, 1076
\ztotpages 13, 125, 841
\zunkownnextpagename ... 12, 775, 818
\zunmakeperpage 14, 1026
\zxrsetup 16, 1279