

A new implementation of L^AT_EX's `tabular` and `array` environment*

Frank Mittelbach David Carlisle[†]

Printed April 6, 2018

This file is maintained by the L^AT_EX Project team.
Bug reports can be opened (category `tools`) at
<https://latex-project.org/bugs.html>.

Abstract

This article describes an extended implementation of the L^AT_EX `array`- and `tabular`-environments. The special merits of this implementation are further options to format columns and the fact that fragile L^AT_EX-commands don't have to be `\protect`'ed any more within those environments.

The major part of the code for this package dates back to 1988—so does some of its documentation.

1 Introduction

This new implementation of the `array`- and `tabular`-environments is part of a larger project in which we are trying to improve the L^AT_EX-code in some aspects and to make L^AT_EX even easier to handle.

The reader should be familiar with the general structure of the environments mentioned above. Further information can be found in [3] and [1]. The additional options which can be used in the preamble as well as those which now have a slightly different meaning are described in table 1.

`\extrarowheight` Additionally we introduce a new parameter called `\extrarowheight`. If it takes a positive length, the value of the parameter is added to the normal height of every row of the table, while the depth will remain the same. This is important for tables with horizontal lines because those lines normally touch the capital letters. For example, we used `\setlength{\extrarowheight}{1pt}` in table 1.

We will discuss a few examples using the new preamble options before dealing with the implementation.

- If you want to use a special font (for example `\bfseries`) in a flushed left column, this can be done with `>\bfseries`1. You do not have to begin every entry of the column with `\bfseries` any more.

*This file has version number v2.4f, last revised 2017/11/07.

[†]David kindly agreed on the inclusion of the `\newcolumntype` implementation, formerly in `newarray.sty` into this package

Unchanged options	
<code>l</code>	Left adjusted column.
<code>c</code>	Centered adjusted column.
<code>r</code>	Right adjusted column.
<code>p{width}</code>	Equivalent to <code>\parbox[t]{width}</code> .
<code>@{decl.}</code>	Suppresses inter-column space and inserts <code>decl.</code> instead.
New options	
<code>m{width}</code>	Defines a column of width <code>width</code> . Every entry will be centered in proportion to the rest of the line. It is somewhat like <code>\parbox{width}</code> .
<code>b{width}</code>	Coincides with <code>\parbox[b]{width}</code> .
<code>>{decl.}</code>	Can be used before an <code>l</code> , <code>r</code> , <code>c</code> , <code>p</code> , <code>m</code> or a <code>b</code> option. It inserts <code>decl.</code> directly in front of the entry of the column.
<code><{decl.}</code>	Can be used after an <code>l</code> , <code>r</code> , <code>c</code> , <code>p{...}</code> , <code>m{...}</code> or a <code>b{...}</code> option. It inserts <code>decl.</code> right after the entry of the column.
<code> </code>	Inserts a vertical line. The distance between two columns will be enlarged by the width of the line in contrast to the original definition of L ^A T _E X.
<code>!{decl.}</code>	Can be used anywhere and corresponds with the <code> </code> option. The difference is that <code>decl.</code> is inserted instead of a vertical line, so this option doesn't suppress the normally inserted space between columns in contrast to <code>@{...}</code> .
<code>w{align}{width}</code>	Sets the cell content in a box of the specified <code>width</code> aligned according to the <code>align</code> parameter which could be either <code>l</code> , <code>c</code> or <code>r</code> . Works essentially like <code>\makebox[width][align]{cell}</code> so silently overprints if the cell content is wider than the specified width. If that is not desired use <code>W</code> instead.
<code>W{align}{width}</code>	Like <code>w</code> but spits out an overfull box warning (and an overfullrule marker in draft mode) when the cell content is too wide to fit. This also means that the alignment is different if there is too much material, because it then always protrudes to the right!

Table 1: The preamble options.

- In columns which have been generated with `p`, `m` or `b`, the default value of `\parindent` is `0pt`. This can be changed with `>\setlength{\parindent}{1cm}}p`.
- The `>`- and `<`-options were originally developed for the following application: `>{$}c<{$}` generates a column in math mode in a `tabular`-environment. If you use this type of a preamble in an `array`-environment, you get a column in LR mode because the additional `$`'s cancel the existing `$`'s.
- One can also think of more complex applications. A problem which has been mentioned several times in T_EXhax can be solved with `>\centerdotes}c<\endcenterdotes}`. To center decimals at their decimal points you (only?)

have to define the following macros:

```
{\catcode'\.\active\gdef.{\egroup\setbox2\hbox\bgroup}}
\def\centerdotes{\catcode'\.\active\setbox0\hbox\bgroup}
\def\endcenterdotes{\egroup\ifvoid2 \setbox2\hbox{0}\fi
\ifdim \wd0>\wd2 \setbox2\hbox to\wd0{\unhbox2\hfill}\else
\setbox0\hbox to\wd2{\hfill\unhbox0}\fi
\catcode'\.12 \box0.\box2}
```

Warning: The code is bad, it doesn't work with more than one dot in a cell and doesn't work when the tabular is used in the argument of some other command. A much better version is provided in the `dcolumn.sty` by David Carlisle.

- Using `c!\hspace{1cm}c` you get space between two columns which is enlarged by one centimeter, while `c@{\hspace{1cm}}c` gives you exactly one centimeter space between two columns.
- A declaration like `w{1}{3cm}` (or even shorter `w1{3cm}`) works like an 1 column except that the width will always be 3cm regardless of the cell content. Same with `w{c}` or `w{r}`. This means that it is easy to set up tables in which all columns have predefined widths.

1.1 Defining new column specifiers

`\newcolumnntype` Whilst it is handy to be able to type

```
>{\some declarations}{c}<{\some more declarations}}
```

if you have a one-off column in a table, it is rather inconvenient if you often use columns of this form. The new version allows you to define a new column specifier, say `x`, which will expand to the primitives column specifiers.¹ Thus we may define

```
\newcolumnntype{x}{>{\some declarations}{c}<{\some more declarations}}
```

One can then use the `x` column specifier in the preamble arguments of all `array` or `tabular` environments in which you want columns of this form.

It is common to need math-mode and LR-mode columns in the same alignment. If we define:

```
\newcolumnntype{C}{>{\$}c<{\$}}
\newcolumnntype{L}{>{\$}l<{\$}}
\newcolumnntype{R}{>{\$}r<{\$}}
```

Then we can use `C` to get centred LR-mode in an `array`, or centred math-mode in a `tabular`.

The example given above for 'centred decimal points' could be assigned to a `d` specifier with the following command.

```
\newcolumnntype{d}{>{\centerdotes}c<{\endcenterdotes}}
```

¹This command was named `\newcolumn` in the `newarray.sty`. At the moment `\newcolumn` is still supported (but gives a warning). In later releases it will vanish.

The above solution always centres the dot in the column. This does not look too good if the column consists of large numbers, but to only a few decimal places. An alternative definition of a `d` column is

```
\newcolumnntype{d}[1]{>{\rightdots{#1}}r<{\endrightdots}}
```

where the appropriate macros in this case are:²

```
\def\coldot{.}% Or if you prefer, \def\coldot{\cdot}
{\catcode'\.=\active
 \gdef.{\egroup\setbox2=\hbox to \dimen0 \bgroup$\coldot}}
\def\rightdots#1{%
 \setbox0=\hbox{#1}\dimen0=#1\wd0
 \setbox0=\hbox{$\coldot$}\advance\dimen0 \wd0
 \setbox2=\hbox to \dimen0 {}%
 \setbox0=\hbox\bgroup\mathcode'\.=8000 $}
\def\endrightdots{\hfil\egroup\box0\box2}
```

Note that `\newcolumnntype` takes the same optional argument as `\newcommand` which declares the number of arguments of the column specifier being defined. Now we can specify `d{2}` in our preamble for a column of figures to at most two decimal places.

A rather different use of the `\newcolumnntype` system takes advantage of the fact that the replacement text in the `\newcolumnntype` command may refer to more than one column. Suppose that a document contains a lot of `tabular` environments that require the same preamble, but you wish to experiment with different preambles. Lamport's original definition allowed you to do the following (although it was probably a mis-use of the system).

```
\newcommand{\X}{clr}
\begin{tabular}{\X} ...
```

`array.sty` takes great care **not** to expand the preamble, and so the above does not work with the new scheme. With the new version this functionality is returned:

```
\newcolumnntype{X}{clr}
\begin{tabular}{X} ...
```

The replacement text in a `\newcolumnntype` command may refer to any of the primitives of `array.sty` see table 1 on page 2, or to any new letters defined in other `\newcolumnntype` commands.

`\showcols` A list of all the currently active `\newcolumnntype` definitions is sent to the terminal and log file if the `\showcols` command is given.

1.2 Special variations of `\hline`

The family of `tabular` environments allows vertical positioning with respect to the baseline of the text in which the environment appears. By default the environment appears centered, but this can be changed to align with the first or last line in the environment by supplying a `t` or `b` value to the optional position argument. However, this does not work when the first or last element in the environment is a `\hline` command—in that case the environment is aligned at the horizontal rule.

²The package `dcolumn.sty` contains more robust macros based on these ideas.

Here is an example:

Tables	with no hline commands used	versus	Tables
			<code>\begin{tabular}[t]{l}</code>
			<code>with no\\ hline \\ commands \\ used</code>
			<code>\end{tabular}</code>
tables	with some hline commands	used.	<code>\begin{tabular}[t]{ l }</code>
			<code>\hline</code>
			<code>with some \\ hline \\ commands \\</code>
			<code>\hline</code>
			<code>\end{tabular}</code>

`\firsthline` Using `\firsthline` and `\lasthline` will cure the problem, and the tables will
`\lasthline` align properly as long as their first or last line does not contain extremely large
objects.

Tables	with no line commands used	versus	Tables
			<code>\begin{tabular}[t]{l}</code>
			<code>with no\\ line \\ commands \\ used</code>
			<code>\end{tabular}</code>
tables	with some line commands	used.	<code>\begin{tabular}[t]{ l }</code>
			<code>\firsthline</code>
			<code>with some \\ line \\ commands \\</code>
			<code>\lasthline</code>
			<code>\end{tabular}</code>

`\extratabsurround` The implementation of these two commands contains an extra dimension, which
is called `\extratabsurround`, to add some additional space at the top and the
bottom of such an environment. This is useful if such tables are nested.

2 Final Comments

2.1 Handling of rules

There are two possible approaches to the handling of horizontal and vertical rules in tables:

1. rules can be placed into the available space without enlarging the table, or
2. rules can be placed between columns or rows thereby enlarging the table.

`array.sty` implements the second possibility while the default implementation in the \LaTeX kernel implements the first concept. Both concepts have their merits but one has to be aware of the individual implications.

- With standard \LaTeX adding rules to a table will not affect the width or height of the table (unless double rules are used), e.g., changing a preamble from `l|l` to `l|l|l` does not affect the document other than adding rules to the table. In contrast, with `array.sty` a table that just fit the `\textwidth` might now produce an overfull box.

- With standard L^AT_EX modifying the width of rules could result in ugly looking tables because without adjusting the `\tabcolsep`, etc. the space between rule and column could get too small (or too large). In fact even overprinting of text is possible. In contrast, with `array.sty` modifying any such length usually works well as the actual visual white space (from `\tabcolsep`, etc.) does not depend on the width of the rules.
- With standard L^AT_EX boxed tabulars actually have strange corners because the horizontal rules end in the middle of the vertical ones. This looks very unpleasant when a large `\arrayrulewidth` is chosen. In that case a simple table like

```
\setlength{\arrayrulewidth}{5pt}
\begin{tabular}{|l|}
  \hline A \\\hline
\end{tabular}
```

will produce something like



2.2 Comparisons with older versions of `array.sty`

There are some differences in the way version 2.1 treats incorrect input, even if the source file does not appear to use any of the extra features of the new version.

- A preamble of the form `{wx*{0}{abc}yz}` was treated by versions prior to 2.1 as `{wx}`. Version 2.1 treats it as `{wxyz}`
- An incorrect positional argument such as `[Q]` was treated as `[c]` by `array.sty`, but is now treated as `[t]`.
- A preamble such as `{cc*{2}}` with an error in a `*`-form will generate different errors in the new version. In both cases the error message is not particularly helpful to the casual user.
- Repeated `<` or `>` constructions generated an error in earlier versions, but are now allowed in this package. `>{\decs1}>{\decs2}` is treated the same as `>{\decs2}\decs1}`.
- The `\extracolsep` command does not work with the old versions of `array.sty`, see the comments in `array.bug`. With version 2.1 `\extracolsep` may again be used in `@`-expressions as in standard L^AT_EX, and also in `!`-expressions (but see the note below).

Prior to version 2.4f the space added by the optional argument to `\` was added inside an `m`-cell if the last column was of type `m`. As a result that cell was vertically centered with that space inside, resulting in a strange offset. Since 2.4f, this space is now added after centering the cell.

A similar problem happened when `\extrarowheight` was used. For that reason `m`-cells now manually position the cell content which allows to ignore this extra space request during the vertical alignment.

2.3 Bugs and Features

- Error messages generated when parsing the column specification refer to the preamble argument **after** it has been re-written by the `\newcolumnntype` system, not to the preamble entered by the user. This seems inevitable with any system based on pre-processing and so is classed as a **feature**.
- The treatment of multiple `<` or `>` declarations may seem strange at first. Earlier implementations treated `>\{decs1\}>\{decs2\}` the same as `>\{decs1\}\{decs2\}`. However this did not give the user the opportunity of overriding the settings of a `\newcolumnntype` defined using these declarations. For example, suppose in an `array` environment we use a `C` column defined as above. The `C` specifies a centred text column, however `>\bfseries C`, which re-writes to `>\bfseries>\$<\$` would not specify a bold column as might be expected, as the preamble would essentially expand to `\hfil\bfseries $ \hfil` and so the column entry would not be in the scope of the `\bfseries`! The present version switches the order of repeated declarations, and so the above example now produces a preamble of the form `\hfil$ \bfseries $ \hfil`, and the dollars cancel each other out without limiting the scope of the `\bfseries`.
- The use of `\extracolsep` has been subject to the following two restrictions. There must be at most one `\extracolsep` command per `@`, or `!` expression and the command must be directly entered into the `@` expression, not as part of a macro definition. Thus `\newcommand{\ef}{\extracolsep{\fill}} ...@{\ef}` does not work with this package. However you can use something like `\newcolumnntype{e}{@{\extracolsep{\fill}}}` instead.
- As noted by the L^AT_EX book, for the purpose of `\multicolumn` each column with the exception of the first one consists of the entry and the *following* inter-column material. This means that in a tabular with the preamble `|1|1|1|1|` input such as `\multicolumn{2}{|c|}` in anything other than the first column is incorrect.

In the standard `array`/`tabular` implementation this error is not so noticeable as that version contains negative spacing so that each `|` takes up no horizontal space. But since in this package the vertical lines take up their natural width one sees two lines if two are specified.

3 The documentation driver file

The first bit of code contains the documentation driver file for T_EX, i.e., the file that will produce the documentation you are currently reading. It will be extracted from this file by the `docstrip` program.

```

1 \(*driver)
2 \NeedsTeXFormat{LaTeX2e}[1995/12/01]
3 \documentclass{ltxdoc}
4
5 \AtBeginDocument{\DeleteShortVerb{\|}} % undo the default is not used
6
7 \usepackage{array}
```

```

8
9 % Allow large table at bottom
10 \renewcommand{\bottomfraction}{0.7}
11
12 \EnableCrossrefs
13 %\DisableCrossrefs % Say \DisableCrossrefs if index is ready
14
15 \RecordChanges % Gather update information
16
17 \CodelineIndex % Index code by line number
18
19 %\OnlyDescription % comment out for implementation details
20 %\OldMakeindex % use if your MakeIndex is pre-v2.9
21 \begin{document}
22 \DocInput{array.dtx}
23 \end{document}
24 </driver>

```

4 The construction of the preamble

It is obvious that those environments will consist mainly of an `\halign`, because \TeX typesets tables using this primitive. That is why we will now take a look at the algorithm which determines a preamble for a `\halign` starting with a given user preamble using the options mentioned above.

The current version is defined at the top of the file looking something like this

```

25 (*package)
26 %\NeedsTeXFormat{LaTeX2e}[1994/05/13]
27 %\ProvidesPackage{array}[\filedate\space version\fileversion]

```

The most interesting macros of this implementation are without doubt those which are responsible for the construction of the preamble for the `\halign`. The underlying algorithm was developed by LAMPORT (resp. KNUTH, see texhax V87#??), and it has been extended and improved.

The user preamble will be read token by token. A token is a single character like `c` or a block enclosed in `{...}`. For example the preamble of `\begin{tabular}{l c | c @{\hspace{1cm}}}` consists of the token `l`, `c`, `|`, `|`, `@` and `\hspace{1cm}`.

The currently used token and the one, used before, are needed to decide on how the construction of the preamble has to be continued. In the example mentioned above the `l` causes the preamble to begin with `\hskip\tabcolsep`. Furthermore `# \hfil` would be appended to define a flush left column. The next token is a `c`. Because it was preceded by an `l` it generates a new column. This is done with `\hskip \tabcolsep & \hskip \tabcolsep`. The column which is to be centered will be appended with `\hfil # \hfil`. The token `|` would then add a space of `\hskip \tabcolsep` and a vertical line because the last tokens was a `c`. The following token `|` would only add a space `\hskip \doublerulesep` because it was preceded by the token `|`. We will not discuss our example further but rather take a look at the general case of constructing preambles.

The example shows that the desired preamble for the `\halign` can be constructed as soon as the action of all combinations of the preamble tokens are specified. There are 18 such tokens so we have $19 \cdot 18 = 342$ combinations if we count the beginning of the preamble as a special token. Fortunately, there

are many combinations which generate the same spaces, so we can define **token** classes. We will identify a **token** within a class with a number, so we can insert the formatting (for example of a column). Table 2 lists all **token** classes and their corresponding numbers.

token	\@chclass	\@chnum	token	\@chclass	\@chnum
c	0	0	Start	4	—
l	0	1	@-arg	5	—
r	0	2	!	6	—
p-arg	0	3	@	7	—
t-arg	0	4	<	8	—
b-arg	0	5	>	9	—
	1	0	p	10	3
!-arg	1	1	t	10	4
<-arg	2	—	b	10	5
>-arg	3	—			

Table 2: Classes of preamble tokens

```

\@chclass The class and the number of the current token are saved in the count registers
\@chnum   \@chclass and \@chnum, while the class of the previous token is stored in the
\@lastchclass count register \@lastchclass. All of the mentioned registers are already allo-
cated in latex.tex, which is the reason why the following three lines of code are
commented out. Later throughout the text I will not mention it again explicitly
whenever I use a % sign. These parts are already defined in latex.tex.
28 % \newcount \@chclass
29 % \newcount \@chnum
30 % \newcount \@lastchclass

\@addtopreamble We will save the already constructed preamble for the \halign in the global macro
\@preamble. This will then be enlarged with the command \@addtopreamble.
31 \def\@addtopreamble#1{\xdef\@preamble{\@preamble #1}}
```

4.1 The character class of a token

```

\@testpach With the help of \@lastchclass we can now define a macro which determines the
class and the number of a given preamble token and assigns them to the registers
\@chclass and \@chnum.
32 \def\@testpach{\@chclass

First we deal with the cases in which the token (#1) is the argument of !, @, < or
>. We can see this from the value of \@lastchclass:
33 \ifnum \@lastchclass=6 \@ne \@chnum \@ne \else
34 \ifnum \@lastchclass=7 5 \else
35 \ifnum \@lastchclass=8 \tw@ \else
36 \ifnum \@lastchclass=9 \thr@@

Otherwise we will assume that the token belongs to the class 0 and assign the
corresponding number to \@chnum if our assumption is correct.
37 \else \z@
```

If the last token was a p, m or a b, \@chnum already has the right value. This is the reason for the somewhat curious choice of the token numbers in class 10.

```
38   \ifnum \@lastchclass = 10 \else
```

Otherwise we will check if \@nextchar is either a c, l or an r. Some applications change the catcodes of certain characters like “@” in `amstex.sty`. As a result the tests below would fail since they assume non-active character tokens. Therefore we evaluate \@nextchar once thereby turning the first token of its replacement text into a char. At this point here this should have been the only char present in \@nextchar which put into via a \def.

```
39   \edef\@nextchar{\expandafter\string\@nextchar}%
40   \@chnum
41   \if \@nextchar c\z@ \else
42     \if \@nextchar l\@ne \else
43       \if \@nextchar r\tw@ \else
```

If it is a different token, we know that the class was not 0. We assign the value 0 to \@chnum because this value is needed for the |-token. Now we must check the remaining classes. Note that the value of \@chnum is insignificant here for most classes.

```
44   \z@ \@chclass
45   \if\@nextchar |\@ne \else
46     \if \@nextchar !6 \else
47       \if \@nextchar @7 \else
48         \if \@nextchar <8 \else
49           \if \@nextchar >9 \else
```

The remaining permitted tokens are p, m and b (class 10).

```
50   10
51   \@chnum
52   \if \@nextchar m\thr@@\else
53     \if \@nextchar p4 \else
54       \if \@nextchar b5 \else
```

Now the only remaining possibility is a forbidden token, so we choose class 0 and number 0 and give an error message. Then we finish the macro by closing all \if's.

```
55   \z@ \@chclass \z@ \@preamerr \z@ \fi \fi \fi \fi
56   \fi \fi \fi \fi \fi \fi \fi \fi \fi \fi \fi \fi
```

4.2 Multiple columns (*-form)

`\@xexpast` Now we discuss the macro that deletes all forms of type $\ast\{N\}\{String\}$ from a user preamble and replaces them with N copies of *String*. Nested \ast -expressions are dealt with correctly, that means \ast -expressions are not substituted if they are in explicit braces, as in $\mathcal{O}\{\ast\}$.

This macro is called via `\@xexpast\preamble*0x\@@`. The \ast -expression $\ast0x$ is being used to terminate the recursion, as we shall see later, and `\@@` serves as an argument delimiter. `\@xexpast` has four arguments. The first one is the part of the user preamble before the first \ast -expression while the second and third ones are the arguments of the first \ast -expression (that is N and *String* in the notation mentioned above). The fourth argument is the rest of the preamble.

```
57 \def\@xexpast#1*#2#3#4\@@{%
```

The number of copies of *String* (#2) that are to be produced will be saved in a count register.

```
58 \tempcnta #2
```

We save the part of the preamble which does not contain a **-form* (#1) in a PLAIN \TeX token register. We also save *String* (#3) using a \LaTeX token register.

```
59 \toks@={#1}\temptokena={#3}%
```

Now we have to use a little trick to produce N copies of *String*. We could try `\def\@tempa{#1}` and then N times `\edef\@tempa{\@tempa#3}`. This would have the undesired effect that all macros within #1 and #3 would be expanded, although, for example, constructions like `@{...}` are not supposed to be changed. That is why we `\let` two control sequences to be equivalent to `\relax`.

```
60 \let\the@toksz\relax \let\the@toks\relax
```

Then we ensure that `\@tempa` contains `{\the@toksz\the@toks...\the@toks}` (the macro `\the@toks` exactly N times) as substitution text.

```
61 \def\@tempa{\the@toksz}%
62 \ifnum\@tempcnta >0 \@whilenum\@tempcnta >0\do
63   {\edef\@tempa{\@tempa\the@toks}\advance \@tempcnta \m@ne}%
```

If N was greater than zero we prepare for another call of `\@expast`. Otherwise we assume we have reached the end of the user preamble, because we had appended `*0x\@@` when we first called `\@expast`. In other words: if the user inserts `*{0}{...}` in his preamble, \LaTeX ignores the rest of it.

```
64 \let \@tempb \@expast \else
65 \let \@tempb \@exnoop \fi
```

Now we will make sure that the part of the user preamble, which was already dealt with, will be saved again in `\@tempa`.

```
66 \def\the@toksz{\the\toks@}\def\the@toks{\the\@temptokena}%
67 \edef\@tempa{\@tempa}%
```

We have now evaluated the first **-expression*, and the user preamble up to this point is saved in `\@tempa`. We will put the contents of `\@tempa` and the rest of the user preamble together and work on the result with `\@tempb`. This macro either corresponds to `\@expast`, so that the next **-expression* is handled, or to the macro `\@exnoop`, which only ends the recursion by deleting its argument.

```
68 \expandafter \@tempb \@tempa #4\@@}
```

`\@exnoop` So the first big problem is solved. Now it is easy to specify `\@exnoop`. Its argument is delimited by `\@@` and it simply expands to nothing.

```
69 % \def\@exnoop#1\@@{}
```

5 The insertion of declarations ($>$, $<$, $!$, $@$)

The preamble will be enlarged with the help of `\xdef`, but the arguments of $>$, $<$, $!$ and $@$ are not supposed to be expanded during the construction (we want an implementation that doesn't need a `\protect`). So we have to find a way to inhibit the expansion of those arguments.

We will solve this problem with token registers. We need one register for every $!$ and $@$, while we need two for every c , l , r , m , p or b . This limits the number

of columns of a table because there are only 256 token registers. But then, who needs tables with more than 100 columns?

One could also find a solution which only needs two or three token registers by proceeding similarly as in the macro `\xexpast` (see page 10). The advantage of our approach is the fact that we avoid some of the problems that arise with the other method³.

So how do we proceed? Let us assume that we had `!{foo}` in the user preamble and say we saved `foo` in token register 5. Then we call `\@addtopreamble{\the@toks5}` where `\the@toks` is defined in a way that it does not expand (for example it could be equivalent to `\relax`). Every following call of `\@addtopreamble` leaves `\the@toks5` unchanged in `\@preamble`. If the construction of the preamble is completed we change the definition of `\the@toks` to `\the\toks` and expand `\@preamble` for the last time. During this process all parts of the form `\the@toks⟨Number⟩` will be substituted by the contents of the respective token registers.

As we can see from this informal discussion the construction of the preamble has to take place within a group, so that the token registers we use will be freed later on. For that reason we keep all assignments to `\@preamble` global; therefore the replacement text of this macro will remain the same after we leave the group.

`\count@` We further need a `count` register to remember which token register is to be used next. This will be initialized with `-1` if we want to begin with the token register 0. We use the PLAIN \TeX scratch register `\count@` because everything takes place locally. All we have to do is insert `\the@toks \the \count@` into the preamble. `\the@toks` will remain unchanged and `\the\count@` expands into the saved number.

`\prepnext@tok` The macro `\prepnext@tok` is in charge of preparing the next token register. For that purpose we increase `\count@` by 1:

```
70 \def\prepnext@tok{\advance \count@ \@ne
```

Then we locally delete any contents the token register might have.

```
71 \toks\count@{}}
```

`\save@decl` During the construction of the preamble the current token is always saved in the macro `\@nextchar` (see the definition of `\@mkpream` on page 14). The macro `\save@decl` saves it into the next free token register, i.e. in `\toks\count@`.

```
72 \def\save@decl{\toks\count@ \expandafter{\@nextchar}}
```

The reason for the use of `\relax` is the following hypothetical situation in the preamble: `..\the\toks1\the\toks2..` \TeX expands `\the\toks2` first in order to find out if the digit 1 is followed by other digits. E.g. a 5 saved in the token register 2 would lead \TeX to insert the contents of token register 15 instead of 1 later on.

The example above referred to an older version of `\save@decl` which inserted a `\relex` inside the token register. This is now moved to the places where the actual token registers are inserted (look for `\the@toks`) because the old version would still make `@` expressions to moving arguments since after expanding the second register while looking for the end of the number the contents of the token register is added so that later on the whole register will be expanded. This serious bug

³Maybe there are also historical reasons.

was found after nearly two years international use of this package by Johannes Braams.

How does the situation look like, if we want to add another column to the preamble, i.e. if we have found a `c`, `l`, `r`, `p`, `m` or `b` in the user preamble? In this case we have the problem of the `token` register from `>{..}` and `<{..}` having to be inserted at this moment because formatting instructions like `\hfil` have to be set around them. On the other hand it is not known yet, if any `<{..}` instruction will appear in the user preamble at all.

We solve this problem by adding two `token` registers at a time. This explains, why we have freed the `token` registers in `\prepnext@tok`.

```
\insert@column We now define the macro \insert@column which will do this work for us.
\@sharp      73 \def\insert@column{%
Here, we assume that the count register \@tempcnta has saved the value \count@-
1.
      74   \the@toks \the \@tempcnta
Next follows the # sign which specifies the place where the text of the column shall
be inserted. To avoid errors during the expansions in \@addtopreamble we hide
this sign in the command \@sharp which is temporarily occupied with \relax
during the build-up of the preamble. To remove unwanted spaces before and after
the column text, we set an \ignorespaces in front and a \unskip afterwards.
      75   \ignorespaces \@sharp \unskip
Then the second token register follows whose number should be saved in \count@.
We make sure that there will be no further expansion after reading the number,
by finishing with \relax. The case above is not critical since it is ended by
\ignorespaces.
      76   \the@toks \the \count@ \relax}
```

5.1 The separation of columns

```
\@addamp In the preamble a & has to be inserted between any two columns; before the first
column there should not be a &. As the user preamble may start with a | we have
to remember somehow if we have already inserted a # (i.e. a column). This is done
with the boolean variable \if@firstamp that we test in \@addamp, the macro that
inserts the &.
      77 %   \newif \if@firstamp
      78 %   \def\@addamp{\if@firstamp \@firstampfalse
      79 %               \else \@addtopreamble &\fi}

\@acol We will now define some abbreviations for the extensions, appearing most often
\@acolampacol in the preamble build-up. Here \col@sep is a dimen register which is set equiv-
\col@sep alent to \arraycolsep in an array-environment, otherwise it is set equivalent to
\tabcolsep.
      80 \newdimen\col@sep
      81 \def\@acol{\@addtopreamble{\hspace\col@sep}}
      82 %   \def\@acolampacol{\@acol\@addamp\@acol}
```

5.2 The macro `\@mkpream`

`\@mkpream` Now we can define the macro which builds up the preamble for the `\halign`. First we initialize `\@preamble`, `\@lastchclass` and the boolean variable `\if@firstamp`.

```
83 \def\@mkpream#1{\gdef\@preamble{}\@lastchclass 4 \@firstamptrue
```

During the build-up of the preamble we cannot directly use the `#` sign; this would lead to an error message in the next `\@addtopreamble` call. Instead, we use the command `\@sharp` at places where later a `#` will be. This command is at first given the meaning `\relax`; therefore it will not be expanded when the preamble is extended. In the macro `\@array`, shortly before the `\halign` is carried out, `\@sharp` is given its final meaning.

In a similar way, we deal with the commands `\@startpbox` and `\@endpbox`, although the reason is different here: these macros expand in many tokens which would delay the build-up of the preamble.

```
84 \let\@sharp\relax \let\@startpbox\relax \let\@endpbox\relax
```

Two more are needed to deal with the code that handles struts for extra space after a row from `\\[<space>]` (`\do@row@strut`) and code that manages m-cells depending on their heights (`\align@mcell`).

```
85 \let\do@row@strut\relax
```

```
86 \let\align@mcell\relax
```

Now we remove possible `*`-forms in the user preamble with the command `\@xexpast`. As we already know, this command saves its result in the macro `\@tempa`.

```
87 \@xexpast #1*0x\@@
```

Afterwards we initialize all registers and macros, that we need for the build-up of the preamble. Since we want to start with the token register 0, `\count@` has to contain the value `-1`.

```
88 \count@\m@ne
```

```
89 \let\the@toks\relax
```

Then we call up `\prepnext@tok` in order to prepare the token register 0 for use.

```
90 \prepnext@tok
```

To evaluate the user preamble (without stars) saved in `\@tempa` we use the \LaTeX -macro `\@tfor`. The strange appearing construction with `\expandafter` is based on the fact that we have to put the replacement text of `\@tempa` and not the macro `\@tempa` to this \LaTeX -macro.

```
91 \expandafter \@tfor \expandafter \@nextchar
```

```
92 \expandafter :\expandafter =\@tempa \do
```

The body of this loop (the group after the `\do`) is executed for one token at a time, whereas the current token is saved in `\@nextchar`. At first we evaluate the current token with the already defined macro `\@testpach`, i.e. we assign to `\@chclass` the character class and to `\@chnum` the character number of this token.

```
93 {\@testpach
```

Then we branch out depending on the value of `\@chclass` into different macros that extend the preamble respectively.

```
94 \ifcase \@chclass \@classz \or \@classi \or \@classii
```

```
95 \or \@save@decl \or \or \@classv \or \@classvi
```

```
96 \or \@classvii \or \@classviii \or \@classix
```

```
97 \or \@classx \fi
```

Two cases deserve our special attention: Since the current `token` cannot have the character class 4 (start) we have skipped this possibility. If the character class is 3, only the content of `\@nextchar` has to be saved into the current `token` register; therefore we call up `\save@decl` directly and save a macro name. After the preamble has been extended we assign the value of `\@chclass` to the counter `\@lastchclass` to assure that this information will be available during the next run of the loop.

```
98    \@lastchclass\@chclass}%
```

After the loop has been finished space must still be added to the created preamble, depending on the last `token`. Depending on the value of `\@lastchclass` we perform the necessary operations.

```
99    \ifcase\@lastchclass
```

If the last class equals 0 we add a `\hskip \col@sep`.

```
100   \@acol \or
```

If it equals 1 we do not add any additional space so that the horizontal lines do not exceed the vertical ones.

```
101   \or
```

Class 2 is treated like class 0 because a `<{...}` can only directly follow after class 0.

```
102   \@acol \or
```

Most of the other possibilities can only appear if the user preamble was defective. Class 3 is not allowed since after a `>{...}` there must always follow a `c`, `l`, `r`, `p`, `m` or `b`. We report an error and ignore the declaration given by `{...}`.

```
103   \@preamerr \thr@@ \or
```

If `\@lastchclass` is 4 the user preamble has been empty. To continue, we insert a `#` in the preamble.

```
104   \@preamerr \tw@ \@addtopreamble\@sharp \or
```

Class 5 is allowed again. In this case (the user preamble ends with `@{...}`) we need not do anything.

```
105   \or
```

Any other case means that the arguments to `@`, `!`, `<`, `>`, `p`, `m` or `b` have been forgotten. So we report an error and ignore the last token.

```
106   \else \@preamerr \@ne \fi
```

Now that the build-up of the preamble is almost finished we can insert the `token` registers and therefore redefine `\the@toks`. The actual insertion, though, is performed later.

```
107   \def\the@toks{\the\toks{}}
```

6 The macros `\@classz` to `\@classx`

The preamble is extended by the macros `\@classz` to `\@classx` which are called by `\@mkpream` depending on `\@lastchclass` (i.e. the character class of the last token).

`\@classx` First we define `\@classx` because of its important rôle. When it is called we find that the current token is `p`, `m` or `b`. That means that a new column has to start.

```
108 \def\@classx{%
```

Depending on the value of `\@lastchclass` different actions must take place:

```
109 \ifcase \@lastchclass
```

If the last character class was 0 we separate the columns by `\hskip\col@sep` followed by `&` and another `\hskip\col@sep`.

```
110 \acolampacol \or
```

If the last class was class 1 — that means that a vertical line was drawn, — before this line a `\hskip\col@sep` was inserted. Therefore there has to be only a `&` followed by `\hskip\col@sep`. But this `&` may be inserted only if this is not the first column. This process is controlled by `\if@firstamp` in the macro `\addamp`.

```
111 \addamp \@acol \or
```

Class 2 is treated like class 0 because `<{...}` can only follow after class 0.

```
112 \acolampacol \or
```

Class 3 requires no actions because all things necessary have been done by the preamble token `>`.

```
113 \or
```

Class 4 means that we are at the beginning of the preamble. Therefore we start the preamble with `\hskip\col@sep` and then call `\@firstampfalse`. This makes sure that a later `\addamp` inserts the character `&` into the preamble.

```
114 \@acol \@firstampfalse \or
```

For class 5 tokens only the character `&` is inserted as a column separator. Therefore we call `\addamp`.

```
115 \addamp
```

Other cases are impossible. For an example `\@lastchclass = 6`—as it might appear in a preamble of the form `...!p...—p` would have been taken as an argument of `!` by `\@testpach`.

```
116 \fi}
```

`\@classz` If the character class of the last token is 0 we have `c`, `l`, `r` or an argument of `m`, `b` or `p`. In the first three cases the preamble must be extended the same way as if we had class 10. The remaining two cases do not require any action because the space needed was generated by the last token (i.e. `m`, `b` or `p`). Since `\@lastchclass` has the value 10 at this point nothing happens when `\@classx` is called. So the macro `\@chclassz` may start like this:

```
117 \def\@classz{\@classx
```

According to the definition of `\insert@column` we must store the number of the token register in which a preceding `>{...}` might have stored its argument into `\@tempcnta`.

```
118 \@tempcnta \count@
```

To have `\count@ = \@tempcnta + 1` we prepare the next token register.

```
119 \prepnext@tok
```

Now the preamble must be extended with the column whose format can be determined by `\@chnum`.

```
120 \addtopreamble{\ifcase \@chnum
```


If `\@chnum` has the value 0 a centered column has to be generated. So we begin with stretchable space.

```
121      \hfil
```

The command `\d@llarbegin` follows expanding into `\begin@group` (in the `tabular`-environment) or into `$`. Doing this (provided an appropriate setting of `\d@llarbegin`) we achieve that the contents of the columns of an `array`-environment are set in math mode while those of a `tabular`-environment are set in LR mode.

```
122      \d@llarbegin
```

Now we insert the contents of the two token registers and the symbol for the column entry (i.e. `#` or more precise `\@sharp`) using `\insert@column`.

```
123      \insert@column
```

We end this case with `\d@llarend` and `\hfil` where `\d@llarend` again is either `$` or `\endgroup`. The strut to enforce a regular row height is placed between the two.

```
124      \d@llarend \do@row@strut \hfil \or
```

The templates for 1 and r (i.e. `\@chnum` 1 or 2) are generated the same way. Since one `\hfil` is missing the text is moved to the relevant side. The `\kern\z@` is needed in case of an empty column entry. Otherwise the `\unskip` in `\insert@column` removes the `\hfil`. Changed to `\hskip1sp` so that it interacts better with `\@bsphack`.

```
125      \hskip1sp\d@llarbegin \insert@column \d@llarend \do@row@strut \hfil \or
```

```
126      \hfil\hskip1sp\d@llarbegin \insert@column \d@llarend \do@row@strut \or
```

The templates for p, m and b mainly consist of a box. In case of m it is generated by `\vcenter`. This command is allowed only in math mode. Therefore we start with a `$`.

```
127 %    $\vcenter
```

```
128      \setbox\mcell@box\vbox
```

The part of the templates which is the same in all three cases (p, m and b) is built by the macros `\@startpbox` and `\@endpbox`. `\@startpbox` has an argument: the width of the column which is stored in the current token (i.e. `\@nextchar`). Between these two macros we find the well known `\insert@column`. The strut is placed after the box

```
129      \@startpbox{\@nextchar}\insert@column \@endpbox
```

```
130      \align@mcell
```

```
131 %$
```

```
132      \do@row@strut \or
```

The templates for p and b are generated in the same way though we do not need the `$` characters because we use `\vtop` or `\vbox`.

```
133      \vtop \@startpbox{\@nextchar}\insert@column \@endpbox\do@row@strut \or
```

```
134      \vbox \@startpbox{\@nextchar}\insert@column \@endpbox\do@row@strut
```

Other values for `\@chnum` are impossible. Therefore we end the arguments to `\@addtopreamble` and `\ifcase`. Before we come to the end of `\@classz` we have to prepare the next token register.

```
135      \fi}\prepnext@tok}
```

`\mcell@box` When dealing with m-cells we need a box to measure the cell height.

```
136 \newbox\mcell@box
```

`\align@mccll` M-cells are supposed to be vertically centered within the table row. In the original implementation that was done using `\vcenter` but the issue with that approach is that it centers the material based on the math-axis. In most situations that comes out quit right, but if, for example, an m-cell has only a single line worth of material inside it will be positioned differently to a l, c or r cell or to a p or b cell with the same content.

For that reason the new implementation does the centering manually: First we check the height of the cell and if that is less or equal to `\ht\@arstrutbox` we assume that this is a single line cell. In that case we don't do any vertical manœuvre and simply output the box, i.e., make it behave like a single line p-cell.

```
137 \def\align@mccll{%
138   \ifdim \ht\mccll@box > \ht\@arstrutbox
```

Otherwise we realign vertically by lowering the box. The question is how much do we need to move down? If there is any `\arraystretch` in place then the first line will have some unusual height and we don't want to consider that when finding the middle point. So we subtract from the cell height the height of that strut. But of course we want to include the normal height of the first line (which would be something like `\ht\strutbox`) so we need to add that. On the other hand, when centering around the mid-point of the cell, we also need to account for the depth of the last line (which is nominally something like `\dp\strutbox`). Both together equals `\baselineskip` so that is what we add and then lower the cell by half of the resulting value.

```
139   \begingroup
140     \dimen@ \ht\mccll@box
141     \advance \dimen@ - \ht\@arstrutbox
142     \advance \dimen@ \baselineskip
143     \lower .5 \dimen@ \box\mccll@box
144   \endgroup
145   \else % assume one line and align at baseline
146     \box\mccll@box
147   \fi}
```

`\@classix` In case of class 9 (`>`-token) we first check if the character class of the last token was 3. In this case we have a user preamble of the form `..>{...}>{...}..` which is not allowed. We only give an error message and continue. So the declarations defined by the first `>{...}` are ignored.

```
148 \def\@classix{\ifnum \@lastchclass = \thr@@
149   \@preamerr \thr@@ \fi
```

Furthermore, we call up `\@class10` because afterwards always a new column is started by c, l, r, p, m or b.

```
150   \@classx}
```

`\@classviii` If the current token is a `<` the last character class must be 0. In this case it is not necessary to extend the preamble. Otherwise we output an error message, set `\@chclass` to 6 and call `\@classvi`. By doing this we achieve that `<` is treated like `!`.

```
151 \def\@classviii{\ifnum \@lastchclass > \z@
152   \@preamerr 4 \@chclass 6 \@classvi \fi}
```

`\@arrayrule` There is only one incompatibility with the original definition: the definition of `\@arrayrule`. In the original a line without width⁴ is created by multiple insertions of `\hskip .5\arrayrulewidth`. We only insert a vertical line into the preamble. This is done to prevent problems with T_EX's main memory when generating tables with many vertical lines in them (especially in the case of floats).

```
153 \def\@arrayrule{\@addtopreamble \vline}
```

`\@classvii` As a consequence it follows that in case of class 7 (`@` token) the preamble need not to be extended. In the original definition `\@lastchclass = 1` is treated by inserting `\hskip .5\arrayrulewidth`. We only check if the last token was of class 3 which is forbidden.

```
154 \def\@classvii{\ifnum \@lastchclass = \thr@@
```

If this is true we output an error message and ignore the declarations stored by the last `>{...}`, because these are overwritten by the argument of `@`.

```
155 \preamerr \thr@@ \fi}
```

`\@classvi` If the current token is a regular `!` and the last class was 0 or 2 we extend the preamble with `\hskip\col@sep`. If the last token was of class 1 (for instance `|`) we extend with `\hskip \doublerulesep` because the construction `!{...}` has to be treated like `|`.

```
156 \def\@classvi{\ifcase \@lastchclass
```

```
157 \acol \or
```

```
158 \@addtopreamble{\hskip \doublerulesep}\or
```

```
159 \acol \or
```

Now `\@preamerr...` should follow because a user preamble of the form `..>{...}!` is not allowed. To save memory we call `\@classvii` instead which also does what we want.

```
160 \@classvii
```

If `\@lastchclass` is 4 or 5 nothing has to be done. Class 6 to 10 are not possible. So we finish the macro.

```
161 \fi}
```

`\@classii` In the case of character classes 2 and 3 (i.e. the argument of `<` or `>`) we only have to store the current token (`\@nextchar`) into the corresponding token register since the preparation and insertion of these registers are done by the macro `\@classz`. This is equivalent to calling `\save@decl` in the case of class 3. To save command identifiers we do this call up in the macro `\@mkpream`.

`\@classiii`

Class 2 exhibits a more complicated situation: the token registers have already been inserted by `\@classz`. So the value of `\count@` is too high by one. Therefore we decrease `\count@` by 1.

```
162 \def\@classii{\advance \count@ \m@ne
```

Next we store the current token into the correct token register by calling `\save@decl` and then increase the value of `\count@` again. At this point we can save memory once more (at the cost of time) if we use the macro `\prepnext@tok`.

```
163 \save@decl\prepnext@tok}
```

⁴So the space between `cc` and `c|c` is equal.

`\@classv` If the current token is of class 5 then it is an argument of a `@` token. It must be stored into a token register.

```
164 \def\@classv{\save@decl
```

We extend the preamble with a command which inserts this token register into the preamble when its construction is finished. The user expects that this argument is worked out in math mode if it was used in an `array`-environment. Therefore we surround it with `\dollar...`'s.

```
165 \@addtopreamble{\dollarbegin\the@toks\the\count@\relax\dollarend}%
```

Finally we must prepare the next token register.

```
166 \prepnext@tok}
```

`\@classi` In the case of class 0 we were able to generate the necessary space between columns by using the macro `\@classx`. Analogously the macro `\@classvi` can be used for class 1.

```
167 \def\@classi{\@classvi
```

Depending on `\@chnum` a vertical line

```
168 \ifcase \@chnum \@arrayrule \or
```

or (in case of `!{...}`) the current token — stored in `\@nextchar` — has to be inserted into the preamble. This corresponds to calling `\@classv`.

```
169 \@classv \fi}
```

`\@startpbox` In `\@classz` the macro `\@startpbox` is used. The width of the parbox is passed as an argument. `\vcenter`, `\vtop` or `\vbox` are already in the preamble. So we start with the braces for the wanted box.

```
170 \def\@startpbox#1{\bgroup
```

The argument is the width of the box. This information has to be assigned to `\hsize`. Then we assign default values to several parameters used in a parbox.

```
171 \setlength\hsize{#1}\@arrayparboxrestore
```

Our main problem is to obtain the same distance between succeeding lines of the parbox. We have to remember that the distance between two parboxes should be defined by `\@arstrut`. That means that it can be greater than the distance in a parbox. Therefore it is not enough to set a `\@arstrut` at the beginning and at the end of the parbox. This would dimension the distance between first and second line and the distance between the two last lines of the parbox wrongly. To prevent this we set an invisible rule of height `\@arstrutbox` at the beginning of the parbox. This has no effect on the depth of the first line. At the end of the parbox we set analogously another invisible rule which only affects the depth of the last line. It is necessary to wait inserting this strut until the paragraph actually starts to allow for things like `\parindent` changes via `>{...}`.

```
172 \everypar{%
173 \vrule \@height \ht\@arstrutbox \@width \z@
174 \everypar{}}%
175 }
```

`\@endpbox` If there are any declarations defined by `>{...}` and `<{...}` they now follow in the macro `\@classz` — the contents of the column in between. So the macro `\@endpbox` must insert the `specialstrut` mentioned earlier and then close the group opened by `\@startpbox`.

```
176 \def\@endpbox{\@finalstrut\@arstrutbox \egroup\hfil}
```

7 Building and calling `\halign`

`\@array` After we have discussed the macros needed for the evaluation of the user preamble we can define the macro `\@array` which uses these macros to create a `\halign`. It has two arguments. The first one is a position argument which can be `t`, `b` or `c`; the second one describes the wanted preamble, e.g. it has the form `|c|c|c|`.

```
177 \def\@array[#1]#2{%
```

First we define a `strut` whose size basically corresponds to a normal `strut` multiplied by the factor `\arraystretch`. This `strut` is then inserted into every row and enforces a minimal distance between two rows. Nevertheless, when using horizontal lines, large letters (like accented capital letters) still collide with such lines. Therefore at first we add to the height of a normal `strut` the value of the parameter `\extrarowheight`.

```
178 \@tempdima \ht \strutbox
179 \advance \@tempdima by\extrarowheight
180 \setbox \@arstrutbox \hbox{\vrule
181     \@height \arraystretch \@tempdima
182     \@depth \arraystretch \dp \strutbox
183     \@width \z@}%
```

Then we open a group, in which the user preamble is evaluated by the macro `\@mkpream`. As we know this must happen locally. This macro creates a preamble for a `\halign` and saves its result globally in the control sequence `\@preamble`.

```
184 \begingroup
185 \@mkpream{#2}%
```

We again redefine `\@preamble` so that a call up of `\@preamble` now starts the `\halign`. Thus also the arguments of `>`, `<`, `@` and `!`, saved in the token registers are inserted into the preamble. The `\tabskip` at the beginning and end of the preamble is set to `0pt` (in the beginning by the use of `\ialign`). Also the command `\@arstrut` is build in, which inserts the `\@arstrutbox`, defined above. Of course, the opening brace after `\ialign` has to be implicit as it will be closed in `\endarray` or another macro.

The `\noexpand` in front of `\ialign` does no harm in standard L^AT_EX and was added since some experimental support for using text glyphs in math redefines `\halign` with the result that it becomes expandable with disastrous results in cases like this. In the kernel definition for this macro the problem does not surface because there `\protect` is set (which is not necessary in this implementation as there is no arbitrary user input that can get expanded) and the experimental code made the redefinition robust. Whether this is the right approach is open to question; consider the `\noexpand` a courtesy to allow an unsupported redefinition of a T_EX primitive for the moment (as people rely on that experimental code).

```
186 \xdef\@preamble{\noexpand \ialign \@halignto
187     \bgroup \@arstrut \@preamble
188     \tabskip \z@ \cr}%
```

What we have not explained yet is the macro `\@halignto` that was just used. Depending on its replacement text the `\halign` becomes a `\halign to <dimen>`. Now we close the group again. Thus `\@startpbox` and `\@endpbox` as well as all token registers get their former meaning back.

```
189 \endgroup
```

To support the `delarray.sty` package we include a hook into this part of the code which is a no-op in the main package.

```
190 \arrayleft
```

Now we decide depending on the position argument in which box the `\halign` is to be put. (`\vcenter` may be used because we are in math mode.)

```
191 \if #1t\vtop \else \if#1b\vbox \else \vcenter \fi \fi
```

Now another implicit opening brace appears; then definitions which shall stay local follow. While constructing the `\@preamble` in `\@mkpream` the `#` sign must be hidden in the macro `\@sharp` which is `\let` to `\relax` at that moment (see definition of `\@mkpream` on page 14). All these now get their actual meaning.

```
192 \bgroup
```

```
193 \let \@sharp ##\let \protect \relax
```

With the above defined struts we fix down the distance between rows by setting `\lineskip` and `\baselineskip` to `0pt`. Since there have to be set `$`'s around every column in the array-environment the parameter `\mathsurround` should also be set to `0pt`. This prevents additional space between the rows. The PLAIN \TeX -macro `\m@th` does this.

```
194 \lineskip \z@
```

```
195 \baselineskip \z@
```

```
196 \m@th
```

Beside, we have to assign a special meaning (which we still have to specify) to the line separator `\`. We also have to redefine the command `\par` in such a way that empty lines in `\halign` cannot do any damage. We succeed in doing so by choosing something that will disappear when expanding. After that we only have to call up `\@preamble` to start the wanted `\halign`.

```
197 \let\\\@arraycr \let\tabularnewline\\\let\par\@empty \@preamble}
```

`\arraybackslash` Restore `\` for use in array and tabular environment (after `\raggedright` etc.).

```
198 \def\arraybackslash{\let\\\tabularnewline}
```

`\extrarowheight` The `dimen` parameter used above also needs to be allocated. As a default value we use `0pt`, to ensure compatibility with standard \LaTeX .

```
199 \newdimen \extrarowheight
```

```
200 \extrarowheight=0pt
```

`\@arstrut` Now the insertion of `\@arstrutbox` through `\@arstut` is easy since we know exactly in which mode \TeX is while working on the `\halign` preamble.

```
201 \def\@arstrut{\unhcopy\@arstrutbox}
```

8 The line separator `\`

`\@arraycr` In the macro `\@array` the line separator `\` is `\let` to the command `\@arraycr`. Its definition starts with a special brace which I have directly copied from the original definition. It is necessary, because the `\futurlet` in `\@ifnextchar` might expand a following `&` token in a construction like `\ &`. This would otherwise end the alignment template at a wrong time. On the other hand we have to be careful to avoid producing a real group, i.e. `{}`, because the command will also be used for the array environment, i.e. in math mode. In that case an extra `{}` would

produce an ord atom which could mess up the spacing. For this reason we use a combination that does not really produce a group at all but modifies the master counter so that a & will not be considered belonging to the current `\halign` while we are looking for a * or [. For further information see [2, Appendix D].

```
202 \def\@arraycr{\relax\iffalse{\fi\ifnum 0='}\fi}
```

Then we test whether the user is using the star form and ignore a possible star (I also disagree with this procedure, because a star does not make any sense here).

```
203 \ifstar \@arraycr \@arraycr}
```

`\@arraycr` In the command `\@arraycr` we test if an optional argument exists.

```
204 \def\@arraycr{\ifnextchar [%
```

If it does, we branch out into the macro `\@argarraycr` if not we close the special brace (mentioned above) and end the row of the `\halign` with a `\cr`.

```
205 \@argarraycr {\ifnum 0='{}\fi\cr}}
```

`\@argarraycr` If additional space is requested by the user this case is treated in the macro `\@argarraycr`. First we close the special brace and then we test if the additional space is positive.

```
206 \def\@argarraycr[#1]{\ifnum0='{}\fi\ifdim #1>\z@
```

If this is the case we create an invisible vertical rule with depth `\dp\@arstrutbox + \wanted space`. Thus we achieve that all vertical lines specified in the user preamble by a | are now generally drawn. Then the row ends with a `\cr`.

If the space is negative we end the row at once with a `\cr` and move back up with a `\vskip`.

While testing these macros I found out that the `\endtemplate` created by `\cr` and & is something like an `\outer` primitive and therefore it should not appear in incomplete `\if` statements. Thus the following solution was chosen which hides the `\cr` in other macros when T_EX is skipping conditional text.

```
207 \expandafter\@argarraycr\else
```

```
208 \expandafter\@yargarraycr\fi{#1}}
```

`\@xargarraycr` The following macros were already explained above.

`\@yargarraycr`

```
209 \def\@xargarraycr#1{\unskip\gdef\do@row@strut
```

```
210 {\@tempdima #1\advance\@tempdima \dp\@arstrutbox
```

```
211 \vrule \@depth\@tempdima \@width\z@\global\let\do@row@strut\relax}\cr}
```

```
212 \let\do@row@strut\relax
```

```
213 \def\@yargarraycr#1{\cr\noalign{\vskip #1}}
```

9 Spanning several columns

`\multicolumn` If several columns should be held together with a special format the command `\multicolumn` must be used. It has three arguments: the number of columns to be covered; the format for the result column and the actual column entry.

```
214 \long\def\multicolumn#1#2#3{%
```

First we combine the given number of columns into a single one; then we start a new block so that the following definition is kept local.

```
215 \multispan{#1}\begingroup
```

Since a `\multicolumn` should only describe the format of a result column, we redefine `\@addamp` in such a way that one gets an error message if one uses more than one `c`, `l`, `r`, `p`, `m` or `b` in the second argument. One should consider that this definition is local to the build-up of the preamble; an `array`- or `tabular`-environment in the third argument of the `\multicolumn` is therefore worked through correctly as well.

```
216 \def\@addamp{\if@firstamp \@firstampfalse \else
217             \@preamerr 5\fi}%
```

Then we evaluate the second argument with the help of `\@mkpream`. Now we still have to insert the contents of the token register into the `\@preamble`, i.e. we have to say `\xdef\@preamble{\@preamble}`. This is achieved shorter by writing:

```
218 \@mkpream{#2}\@addtopreamble\@empty
```

After the `\@preamble` is created we forget all local definitions and occupations of the token registers.

```
219 \endgroup
```

In the special situation of `\multicolumn` `\@preamble` is not needed as preamble for a `\halign` but it is directly inserted into our table. Thus instead of `\sharp` there has to be the column entry (`#3`) wanted by the user.

```
220 \def\@sharp{#3}%
```

Now we can pass the `\@preamble` to `TeX`. For safety we start with an `\@arstrut`. This should usually be in the template for the first column however we do not know if this template was overwritten by our `\multicolumn`. We also add a `\null` at the right end to prevent any following `\unskip` (for example from `\[...]`) to remove the `\tabcolsep`.

```
221 \@arstrut \@preamble
222 \null
223 \ignorespaces}
```

10 The Environment Definitions

After these preparations we are able to define the environments. They only differ in the initialisations of `\dollar...`, `\colsep` and `\@halignto`.

<code>\@halignto</code> <code>\dollarbegin</code> <code>\dollarend</code>	<code>\dollar</code> has to be locally assigned since otherwise nested <code>tabular</code> and <code>array</code> environments (via <code>\multicolumn</code>) are impossible. For 25 years or so <code>\@halignto</code> was set globally (to save space on the save stack, but that was a mistake: if there is a tabular in the output routine (e.g., in the running header) then that tabular is able overwrite the <code>\@halignto</code> setting of a tabular in the main text resulting in a very weird error. When the new font selection scheme is in force we have to we surround all <code>\halign</code> entries with braces. See remarks in TUGboat 10#2. Actually we are going to use <code>\begingroup</code> and <code>\endgroup</code> . However, this is only necessary when we are in text mode. In math the surrounding dollar signs will already serve as the necessary extra grouping level. Therefore we switch the settings of <code>\dollarbegin</code> and <code>\dollarend</code> between groups and dollar signs.
---	---

```
224 \let\dollarbegin\begingroup
225 \let\dollarend\endgroup
```


`\array` Our new definition of `\array` then reads:

```

226 \def\array{\colsep\arraycolsep
227   \def\dollarbegin{$}\let\dollarend\dollarbegin\def\@halignto{}%

```

Since there might be an optional argument we call another macro which is also used by the other environments.

```

228   \@tabarray}

```

`\@tabarray` This macro tests for a optional bracket and then calls up `\@array` or `\@array[c]` (as default).

```

229 \def\@tabarray{\ifnextchar[{\@array}{\@array[c]}}

```

`\tabular` The environments `tabular` and `tabular*` differ only in the initialisation of the command `\@halignto`. Therefore we define

```

230 \def\tabular{\def\@halignto{}\@tabular}

```

and analogously for the star form. We evaluate the argument first using `\setlength` so that users of the `calc` package can write code like `\begin{tabular*}{(\columnwidth-1cm)/2}...`

```

231 \expandafter\def\csname tabular*\endcsname#1{%
232     \setlength\dimen@{#1}%
233     \edef\@halignto{to\the\dimen@}\@tabular}

```

`\@tabular` The rest of the job is carried out by the `\@tabular` macro:

```

234 \def\@tabular{%

```

First of all we have to make sure that we start out in `hmode`. Otherwise we might find our table dangling by itself on a line.

```

235   \leavevmode

```

It should be taken into consideration that the macro `\@array` must be called in math mode. Therefore we open a `box`, insert a `$` and then assign the correct values to `\colsep` and `\dollar`...

```

236   \hbox \bgroup $\colsep\tabcsep \let\dollarbegin\begin\group
237                               \let\dollarend\endgroup

```

Now everything `tabular` specific is done and we are able to call the `\@tabarray` macro.

```

238   \@tabarray}

```

`\endarray` When the processing of `array` is finished we have to close the `\halign` and afterwards the surrounding `box` selected by `\@array`. To save token space we then redefine `\@preamble` because its replacement text isn't longer needed.

```

239 \def\endarray{\crrc \egroup \egroup \gdef\@preamble{}}

```

`\endtabular` To end a `tabular` or `tabular*` environment we call up `\endarray`, close the math mode and then the surrounding `\hbox`.

```

240 \def\endtabular{\endarray $\egroup}
241 \expandafter\let\csname endtabular*\endcsname=\endtabular

```

11 Last minute definitions

If this file is used as a package file we should `\let` all macros to `\relax` that were used in the original but are no longer necessary.

```
242 \let\ampacol=\relax      \let\expast=\relax
243 \let\arrayclassiv=\relax \let\arrayclassz=\relax
244 \let\@tabclassiv=\relax  \let\@tabclassz=\relax
245 \let\arrayacol=\relax    \let\@tabacol=\relax
246 \let\@tabularcr=\relax   \let\@endpbox=\relax
247 \let\argtabularcr=\relax \let\@x@tabularcr=\relax
```

`\@preamerr` We also have to redefine the error routine `\@preamerr` since new kind of errors are possible. The code for this macro is not perfect yet; it still needs too much memory.

```
248 \def\@preamerr#1{\def\@tempd{...} at wrong position: }%
249   \PackageError{array}{%
250     \ifcase #1 Illegal pream-token (\@nextchar): ‘c’ used\or %0
251     Missing arg: token ignored\or %1
252     Empty preamble: ‘1’ used\or %2
253     >\@tempd token ignored\or %3
254     <\@tempd changed to !{...}\or %4
255     Only one column-spec. allowed.\fi}\@ehc} %5
```

12 Defining your own column specifiers⁵

`\newcolumn` In `newarray.sty` the macro for specifying new columns was named `\newcolumn`. When the functionality was added to `array.sty` the command was renamed `\newcolumntype`. Initially both names were supported, but now (In versions of this package distributed for L^AT_EX 2_ε) the old name is not defined.

```
256 \newcolumn{ncols}
```

`\newcolumntype` As described above, the `\newcolumntype` macro gives users the chance to define letters, to be used in the same way as the primitive column specifiers, ‘c’ ‘p’ etc.

```
257 \def\newcolumntype#1{%
```

`\NC@char` was added in V2.01 so that active characters, like `@` in AMS^L_AT_EX may be used. This trick was stolen from `array.sty` 2.0h. Note that we need to use the possibly active token, `#1`, in several places, as that is the token that actually appears in the preamble argument.

```
258   \edef\NC@char{\string#1}%
```

First we check whether there is already a definition for this column. Unlike `\newcommand` we give a warning rather than an error if it is defined. If it is a new column, add `\NC@do {column}` to the list `\NC@list`.

```
259   \ifundefined{NC@find@\NC@char}%
260     {\@tfor\next:=<>clrbp@!!\do{\if\noexpand\next\NC@char
261       \PackageWarning{array}{%
```

⁵The code and the documentation in this section was written by David. So far only the code from `newarray` was plugged into `array` so that some parts of the documentation still claim that this is `newarray` and even worse, some parts of the code are unnecessarily doubled. This will go away in a future release. For the moment we thought it would be more important to bring both packages together.

```

262             {Redefining primitive column \NC@char}\fi}%
263     \NC@list\expandafter{\the\NC@list\NC@do#1}}%
264     {\PackageWarning{array}{Column \NC@char\space is already defined}}%

```

Now we define a macro with an argument delimited by the new column specifier, this is used to find occurrences of this specifier in the user preamble.

```

265     \namedef{NC@find@\NC@char}##1#1{\NC@{##1}}%

```

If an optional argument was not given, give a default argument of 0.

```

266     \ifnextchar[{\newcol@\NC@char}]{\newcol@\NC@char}[0]}

```

\newcol@ We can now define the macro which does the rewriting, **\@reargdef** takes the same arguments as **\newcommand**, but does not check that the command is new. For a column, say ‘D’ with one argument, define a command **\NC@rewrite@D** with one argument, which recursively calls **\NC@find** on the user preamble after replacing the first token or group with the replacement text specified in the **\newcolumnstype** command. **\NC@find** will find the next occurrence of ‘D’ as it will be **\let** equal to **\NC@find@D** by **\NC@do**.

```

267 \def\newcol@#1[#2]#3{\expandafter\@reargdef
268     \csname NC@rewrite@#1\endcsname[#2]{\NC@find#3}}

```

\NC@ Having found an occurrence of the new column, save the preamble before the column in **\@temptokena**, then check to see if we are at the end of the preamble. (A dummy occurrence of the column specifier will be placed at the end of the preamble by **\NC@do**.)

```

269 \def\NC@#1{%
270     \@temptokena\expandafter{\the\@temptokena#1}\futurelet\next\NC@ifend}

```

\NC@ifend We can tell that we are at the end as **\NC@do** will place a **\relax** after the dummy column.

```

271 \def\NC@ifend{%

```

If we are at the end, do nothing. (The whole preamble will now be in **\@temptokena**.)

```

272     \ifx\next\relax

```

Otherwise set the flag **\if@tempswa**, and rewrite the column. **\expandafter** introduced in V2.01

```

273     \else\@tempswatrue\expandafter\NC@rewrite\fi}

```

\NC@do If the user has specified ‘C’ and ‘L’ as new columns, the list of rewrites (in the token register **\NC@list**) will look like **\NC@do * \NC@do C \NC@do L**. So we need to define **\NC@do** as a one argument macro which initialises the rewriting of the specified column. Let us assume that ‘C’ is the argument.

```

274 \def\NC@do#1{%

```

First we let **\NC@rewrite** and **\NC@find** be **\NC@rewrite@C** and **\NC@find@C** respectively.

```

275     \expandafter\let\expandafter\NC@rewrite
276         \csname NC@rewrite@\string#1\endcsname
277     \expandafter\let\expandafter\NC@find
278         \csname NC@find@\string#1\endcsname

```

Clear the token register `\@temptokena` after putting the present contents of the register in front of the token `\NC@find`. At the end we place the tokens ‘`C\relax`’ which `\NC@ifend` will use to detect the end of the user preamble.

```
279 \expandafter\@temptokena\expandafter{\expandafter}%
280 \expandafter\NC@find\the\@temptokena#1\relax}
```

\showcols This macro is useful for debugging `\newcolumnntype` specifications, it is the equivalent of the primitive `\show` command for macro definitions. All we need to do is locally redefine `\NC@do` to take its argument (say ‘`C`’) and then `\show` the (slightly modified) definition of `\NC@rewrite@C`. Actually as the list always starts off with `\NC@do *` and we do not want to print the definition of the `*`-form, define `\NC@do` to throw away the first item in the list, and then redefine itself to print the rest of the definitions.

```
281 \def\showcols{\def\NC@do#1{\let\NC@do\NC@show}\the\NC@list}}
```

\NC@show If the column ‘`C`’ is defined as above, then `\show\NC@rewrite@C` would output `\long macro: ->\NC@find >{\$}c<{\$}`. We want to strip the `\long macro: ->` and the `\NC@find`. So first we use `\meaning` and then apply the macro `\NC@strip` to the tokens so produced and then `\typeout` the required string.

```
282 \def\NC@show#1{%
283 \typeout{Column #1\expandafter\expandafter\expandafter\NC@strip
284 \expandafter\meaning\csname NC@rewrite@#1\endcsname\@@}}
```

\NC@strip Delimit the arguments to `\NC@strip` with ‘`:`’, ‘`->`’, a space, and `\@@` to pull out the required parts of the output from `\meaning`.

```
285 \def\NC@strip#1:#2->#3 #4\@@{#2 -> #4}
```

\NC@list Allocate the token register used for the rewrite list.

```
286 \newtoks\NC@list
```

12.1 The `*`-form

We view the `*`-form as a slight generalisation of the system described in the previous subsection. The idea is to define a `*` column by a command of the form:

```
\newcolumnntype{*}[2]{%
\count@=#1\ifnum\count@>0
\advance\count@ by -1 #2*{\count@}{#2}\fi}
```

\NC@rewrite@* This does not work however as `\newcolumnntype` takes great care not to expand anything in the preamble, and so the `\if` is never expanded. `\newcolumnntype` sets up various other parts of the rewrite correctly though so we can define:

```
287 \newcolumnntype{*}[2]{}
```

Now we must correct the definition of `\NC@rewrite@*`. The following is probably more efficient than a direct translation of the idea sketched above, we do not need to put a `*` in the preamble and call the rewrite recursively, we can just put `#1` copies of `#2` into `\@temptokena`. (Nested `*` forms will be expanded when the whole rewrite list is expanded again, see `\@mkpream`)

```
288 \long\@namedef{NC@rewrite@*}#1#2{%
```

Store the number.

```
289 \count@#1\relax
```

Put #1 copies of #2 in the token register.

```
290 \loop
```

```
291 \ifnum\count@>\z@
```

```
292 \advance\count@\m@ne
```

```
293 \@temptokena\expandafter{\the\@temptokena#2}%
```

```
294 \repeat
```

\NC@do will ensure that \NC@find is \let equal to \NC@find@*.

```
295 \NC@find}
```

12.2 Modifications to internal macros of array.sty

\@xexpast These macros are used to expand *-forms in array.sty. \let them to \relax to save space.

```
296 \let\@xexpast\relax
```

```
297 \let\@xexnoop\relax
```

\save@decl We do not assume that the token register is free, we add the new declarations to the front of the register. This is to allow user preambles of the form, >{foo}>{bar}... Users are not encouraged to enter such expressions directly, but they may result from the rewriting of \newcolumnntype's.

```
298 \def\save@decl{\toks \count@ = \expandafter\expandafter\expandafter
```

```
299 {\expandafter\@nextchar\the\toks\count@}}
```

\@mkpream The main modification to \@mkpream is to replace the call to \@xexpast (which expanded *-forms) by a loop which expands all \newcolumnntype specifiers.

```
300 \def\@mkpream#1{\gdef\@preamble{}\@lastchclass 4 \@firststamptrue
```

```
301 \let\@sharp\relax \let\@startpbox\relax \let\@endpbox\relax
```

```
302 \let\do@row@strut\relax
```

```
303 \let\align@mcell\relax
```

Now we remove possible *-forms and user-defined column specifiers in the user preamble by repeatedly executing the list \NC@list until the re-writes have no more effect. The expanded preamble will then be in the token register \@temptokena. Actually we need to know at this point that this is not \toks0.

```
304 \@temptokena{#1}\@tempswatrue
```

```
305 \@whiles\if@tempswa\fi{\@tempswafalse\the\NC@list}%
```

Afterwards we initialize all registers and macros, that we need for the build-up of the preamble.

```
306 \count@\m@ne
```

```
307 \let\the@toks\relax
```

```
308 \prepnext@tok
```

Having expanded all tokens defined using \newcolumnntype (including *), we evaluate the remaining tokens, which are saved in \@temptokena. We use the L^AT_EX-macro \@tfor to inspect each token in turn.

```
309 \expandafter \@tfor \expandafter \@nextchar
```

```
310 \expandafter : \expandafter = \the \@temptokena \do
```

`\@testpatch` does not take an argument since `array.sty` 2.0h.

```

311   {\@testpatch
312   \ifcase \@chclass \@classz \or \@classi \or \@classii
313   \or \save@decl \or \or \@classv \or \@classvi
314   \or \@classvii \or \@classviii

```

In `newarray.sty` class 9 is equivalent to class 10.

```

315   \or \@classx
316   \or \@classx \fi
317   \@lastchclass\@chclass}%
318   \ifcase\@lastchclass
319   \@acol \or
320   \or
321   \@acol \or
322   \@preamerr \thr@@ \or
323   \@preamerr \tw@ \@addtopreamble\@sharp \or
324   \or
325   \else \@preamerr \@ne \fi
326   \def\the@toks{\the\toks}}

```

`\@classix` `array.sty` does not allow repeated `>` declarations for the same column. This is allowed in `newarray.sty` as documented in the introduction. Removing the test for this case makes class 9 equivalent to class 10, and so this macro is redundant. It is `\let` to `\relax` to save space.

```

327 \let\@classix\relax

```

`\@classviii` In `newarray.sty` explicitly allow class 2, as repeated `<` expressions are accepted by this package.

```

328 \def\@classviii{\ifnum \@lastchclass >\z@\ifnum\@lastchclass=\tw@\else
329   \@preamerr 4\@chclass 6 \@classvi \fi\fi}

```

`\@classv` Class 5 is `@`-expressions (and is also called by class 1) This macro was incorrect in Version 1. Now we do not expand the `@`-expression, but instead explicitly replace an `\extracolsep` command by an assignment to `\tabskip` by a method similar to the `\newcolumntype` system described above. `\d@llarbegin` `\d@llarend` were introduced in V2.01 to match `array.sty` 2.0h.

```

330 \def\@classv{\save@decl
331   \expandafter\NC@ecs\@nextchar\extracolsep{}\extracolsep\@@@
332   \@addtopreamble{\d@llarbegin\the@toks\the\count@\relax\d@llarend}%
333   \prepnext@tok}

```

`\NC@ecs` Rewrite the first occurrence of `\extracolsep{1in}` to `\tabskip1in\relax`. As a side effect discard any tokens after a second `\extracolsep`, there is no point in the user entering two of these commands anyway, so this is not really a restriction.

```

334 \def\NC@ecs#1\extracolsep#2#3\extracolsep#4\@@@{\def\@tempa{#2}%
335   \ifx\@tempa\@empty\else\toks\count@={#1\tabskip#2\relax#3}\fi}
336 \end{ncols}

```

12.3 Support for the `delarray.sty`

The `delarray.sty` package extends the `array` syntax by supporting the notation of delimiters. To this end we extend the array parsing mechanism to include a hook which can be used by this (or another) package to do some additional parsing.

`\@tabarray` This macro tests for an optional bracket and then calls up `\@array` or `\@array[c]` (as default).

```

337 (*package)
338 \def\@tabarray{\ifnextchar[\{\@array\}\@array[c]\}}

```

`\@array` This macro tests could then test an optional delimiter before the left brace of the main preamble argument. Here in the main package it simply is let to be `\@array`.

```

339 \let\@array\@array

```

`\endarray` We have to declare the hook we put into `\@array` above. A similar hook `\@arrayright` will be inserted into the `\endarray` to gain control. Both defaults to empty.

```

340 \def\endarray{\crcr \egroup \egroup \@arrayright \gdef\@preamble{}}
341 \let\@arrayleft\@empty
342 \let\@arrayright\@empty

```

12.4 Support for `\firstline` and `\lastline`

The Companion [1, p.137] suggests two additional commands to control the alignments in case of tabulars with horizontal lines. They are now added to this package.

`\extratabsurround` The extra space around a table when `\firstline` or `\lastline` are used.

```

343 \newlength{\extratabsurround}
344 \setlength{\extratabsurround}{2pt}

```

`\backup@length` This register will be used internally by `\firstline` and `\lastline`.

```

345 \newlength{\backup@length}

```

`\firstline` This code can probably be improved but for the moment it should serve.

We start by producing a single tabular row without any visible content that will produce the external reference point in case `[t]` is used.

```

346 \newcommand{\firstline}{%
347   \multicolumn{1}{%

```

Within this row we calculate `\backup@length` to be the height plus depth of a standard line. In addition we have to add the width of the `\hline`, something that was forgotten in the original definition.

```

348   \global\backup@length\ht\@arstrutbox
349   \global\advance\backup@length\dp\@arstrutbox
350   \global\advance\backup@length\arrayrulewidth

```

Finally we do want to make the height of this first line be a bit larger than usual, for this we place the standard array strut into it but raised by `\extratabsurround`

```

351   \raise\extratabsurround\copy\@arstrutbox

```

Having done all this we end the line and back up by the value of `\backup@length` and then finally place our `\hline`. This should place the line exactly at the right place but keep the reference point of the whole tabular at the baseline of the first row.

```

352   }\[-\backup@length\hline
353 }

```

`\lasthline` For `\lasthline` the situation is even worse and I got it completely wrong initially.

The problem in this case is that if the optional argument `[b]` is used we do want the reference point of the tabular be at the baseline of the last row but at the same time do want the the depth of this last line increased by `\extratabsurround` without changing the placement `\hline`.

We start by placing the rule followed by an invisible row.

```
354 \newcommand{\lasthline}{\hline\multicolumn1c{%
```

We now calculate `\backup@length` to be the height and depth of two lines plus the width of the rule.

```
355 \global\backup@length2\ht\@arstrutbox
356 \global\advance\backup@length2\dp\@arstrutbox
357 \global\advance\backup@length\arrayrulewidth
```

This will bring us back to the baseline of the second last row:

```
358 }\\[-\backup@length]%
```

Thus if we now add another invisible row the reference point of that row will be at the baseline of the last row (and will be the reference for the whole tabular). Since this row is invisible we can enlarge its depth by the desired amount.

```
359 \multicolumn1c{%
360 \lower\extratabsurround\copy\@arstrutbox
361 }%
362 }
```

12.5 Getting the spacing around rules right

Beside a larger functionality `array.sty` has one important difference to the standard `tabular` and `array` environments: horizontal and vertical rules make a table larger or wider, e.g., `\doublerulesep` really denotes the space between two rules and isn't measured from the middle of the rules.

`\@xhline` For vertical rules this is implemented by the definitions above, for horizontal rules we have to take out the backspace.

```
363 \CheckCommand*\@xhline{\ifx\reserved@a\hline
364 \vskip\doublerulesep
365 \vskip-\arrayrulewidth
366 \fi
367 \ifnum0='{ \fi}}
368 \renewcommand*\@xhline{\ifx\reserved@a\hline
369 \vskip\doublerulesep
370 \fi
371 \ifnum0='{ \fi}}
372 \end{package}
```

12.6 Implementing column types `w` and `W`

In TugBoat 38/2 an extension was presented that implemented two additional column types `w` and `W`. These have now been added to the package itself.

`\ar@cellbox` For `w` and `W` column types we need a box to temporarily hold the cell content.

```
373 \newsavebox\ar@cellbox
```


`\newcolumntype w` The `w` column type has two arguments: the first holds the alignment which is either `l`, `c`, or `r` and the second is the nominal width of the column.

```
374 \newcolumntype{w}[2]{%
```

Before the cell content we start an `lrbox`-environment to collect the cell material into the previously allocated box `\ar@cellbox`.

```
375 >{\begin{lrbox}\ar@cellbox}%
```

Then comes a specifier for the cell content. We use `c`, but that doesn't matter as in the end we will always put a box of a specific width (`#2`) into the cells of that column, so `l` or `r` would give the same result. There is only a difference if there are also very wide `\multicolumn` rows overwriting the setting in which case `c` seems to be slightly better.

```
376 c%
```

At the end of the cell we end the `lrbox` environment so that all of the cell content is now in box `\ar@cellbox`. As a final step we put that box into a `\makebox` using the optional arguments of that command to achieve the correct width and the desired alignment within that width.

```
377 <{\end{lrbox}}%
```

```
378 \makebox[#2][#1]{\usebox\ar@cellbox}}}
```

`\newcolumntype W` The `W` is similar but in this case we want a warning if the cell content is too wide.

```
379 \newcolumntype{W}[2]
```

```
380 {>{\begin{lrbox}\ar@cellbox}%
```

```
381 c%
```

```
382 <{\end{lrbox}}%
```

```
383 \let\hss\hfil
```

```
384 \makebox[#2][#1]{\unhbox\ar@cellbox}}}
```

This is a bit sneaky, as it temporarily disables `\hss`, but given that we know what goes into that box it should be sufficient.

Index

Numbers written in *italic* refer to the page where the corresponding entry is described; numbers underlined refer to the code line of the definition; numbers in roman refer to the code lines where the entry is used.

Symbols	<code>\@addtopreamble</code> ...	<code>\@arrayleft</code> ... 190 , 341
<code>\@@</code> 57 , 68 , 69 , 87 , 284 , 285	31 , 79 , 81 , 104 ,	<code>\@arrayparboxrestore</code>
<code>\@@@</code> ... 331 , 334	120 , 153 , 158 ,	... 171
<code>\@@array</code> ... 338 , 339	165 , 218 , 323 , 332	<code>\@arrayright</code> ... 340
<code>\@@endpbox</code> ... 246	<code>\@ampacol</code> ... 242	<code>\@arrayrule</code> ... 153 , 168
<code>\@acol</code> ... 80 , 100 ,	<code>\@argarraycr</code> .. 205 , 206	<code>\@arstrut</code> . 187 , 201 , 221
102 , 111 , 114 ,	<code>\@argtabularcr</code> ... 247	<code>\@arstrutbox</code> ...
157 , 159 , 319 , 321	<code>\@array</code> ... 177 , 229 , 339	. 138 , 141 , 173 ,
<code>\@acolampacol</code> ...	<code>\@arrayacol</code> ... 245	176 , 180 , 201 ,
... 80 , 110 , 112	<code>\@arrayclassiv</code> ... 243	210 , 348 , 349 ,
<code>\@addamp</code> ...	<code>\@arrayclassz</code> ... 243	351 , 355 , 356 , 360
77 , 82 , 111 , 115 , 216	<code>\@arraycr</code> ... 197 , 202	<code>\@chclass</code> ... 28 , 32 ,

44, 55, 94, 98, 152, 312, 317, 329	\@chnum 28, 33, 40, 51, 120, 168	\@reargdef 267	\col@sep . . . 80, 226, 236
\@classi . . . 94, 167, 312	\@classii . . . 94, 162, 312	\@sharp . . . 73, 84, 104, 193, 220, 301, 323	\copy 351, 360
\@classiii 162	\@classix . . . 96, 148, 327	\@startpbox . . 84, 129, 133, 134, 170, 301	\count@ . . . 70, 70, 71, 72, 76, 88, 118, 162, 165, 289, 291, 292, 298, 299, 306, 332, 335
\@classv 95, 164, 169, 313, 330	\@classvi . . . 95, 152, 156, 167, 313, 329	\@tabacol 245	
\@classvii 96, 154, 160, 314	\@classviii 96, 151, 314, 328	\@tabarray 228, 229, 238, 337	
\@classx 97, 108, 117, 150, 315, 316	\@classz . . . 94, 117, 312	\@tabclassiv 244	
\@empty 197, 218, 335, 341, 342	\@endpbox . . . 84, 129, 133, 134, 176, 301	\@tabclassz 244	
\@expast 242	\@finalstrut 176	\@tabular . . . 230, 233, 234	
\@firstampfalse 78, 114, 216	\@firstamptrue . . 83, 300	\@tabularcr 246	
\@halignto 186, 224, 227, 230, 233	\@iffirstamp 77	\@tempswafalse 305	
\@lastchclass 28, 33, 34, 35, 36, 38, 83, 98, 99, 109, 148, 151, 154, 156, 300, 317, 318, 328	\@mkpream 83, 185, 218, 300	\@tempwattrue . . . 273, 304	
\@namedef 265, 288	\@nextchar . . . 39, 41, 42, 43, 45, 46, 47, 48, 49, 52, 53, 54, 72, 91, 129, 133, 134, 250, 299, 309, 331	\@temptokena 59, 66, 270, 279, 280, 293, 304, 310	
\@preamble . . . 31, 83, 186, 187, 197, 221, 239, 300, 340	\@preamerr 55, 103, 104, 106, 149, 152, 155, 217, 248, 322, 323, 325, 329	\@testpach . . . 32, 93, 311	
		\@tfor 91, 260, 309	
		\@whilesw 305	
		\@xargarraycr . . . 207, 209	
		\@xarraycr 203, 204	
		\@xexnoop 65, 69, 296	
		\@xexpast 57, 87, 296	
		\@xhline 363	
		\@xtabularcr 247	
		\@yargarraycr . . . 208, 209	
		\ 5	
A			
	\align@mccl 86, 130, 137, 303		
	\ar@cellbox 373, 375, 378, 380, 384		
	\array 226		
	\arraybackslash 198		
	\arraycolsep 226		
	\arrayrulewidth 350, 357, 365		
	\arraystretch . . . 181, 182		
	\AtBeginDocument 5		
B			
	\backup@length 345, 348, 349, 350, 352, 355, 356, 357, 358		
	\begin 21, 375, 380		
	\bottomfraction 10		
	\box 143, 146		
C			
	\CheckCommand 363		
	\CodelineIndex 17		
D			
	\dollarbegin . . . 122, 125, 126, 165, 224, 227, 236, 332		
	\dollarend 124, 125, 126, 165, 224, 227, 237, 332		
	\DeleteShortVerb 5		
	\dimen@ 140, 141, 142, 143, 232, 233		
	\DisableCrossrefs . . . 13		
	\do@row@strut 85, 124, 125, 126, 132, 133, 134, 209, 211, 212, 302		
	\DocInput 22		
	\documentclass 3		
	\doublerulesep 158, 364, 369		
E			
	\EnableCrossrefs . . . 12		
	\end 23, 377, 382		
	\endarray 239, 240, 340		
	\endgroup 144, 189, 219, 225, 237		
	\endtabular 240		
	\endtabular* 240		
	\everypar 172, 174		
	\extracolsep 331, 334		
	\extrarowheight 1, 179, 199		
	\extratabsurround 5, 343, 351, 360		
F			
	\firsthline 5, 346		
	\futurelet 270		
G			
	\global 211, 348, 349, 350, 355, 356, 357		
H			
	\hline 352, 354, 363, 368		
	\hss 383		

I		R	
<code>\ialign</code>	186	<code>\NC@list</code>	<code>\protect</code> 193
<code>\if@firstamp</code> . . .	78, 216	<code>\NC@rewrite</code> . . .	<code>\ProvidesPackage</code> . . 27
<code>\if@tempswa</code>	305	<code>\NC@rewrite@*</code>	
<code>\iffalse</code>	202	<code>\NC@show</code>	
<code>\insert@column</code>		<code>\NC@strip</code>	
.. 73, 123, 125,		<code>\NeedsTeXFormat</code> . . .	
126, 129, 133, 134		<code>\newbox</code>	
L		<code>\newcol@</code>	
<code>\lasthline</code>	5, 354	<code>\newcolumn</code>	
<code>\long</code>	214, 288	<code>\newcolumntype</code> . . .	
<code>\loop</code>	290	257, 287, 374, 379	
<code>\lower</code>	143, 360	<code>\newcolumntype_W</code> . .	
M		<code>\newcolumntype_␣_W</code> . .	
<code>\m@th</code>	196	<code>\newcommand</code> . . .	
<code>\makebox</code>	378, 384	<code>\newif</code>	
<code>\mcell@box</code> 128, 136,		<code>\newlength</code> . . .	
138, 140, 143, 146		<code>\newsavebox</code>	
<code>\meaning</code>	284	<code>\newtoks</code>	
<code>\multicolumn</code>		<code>\next</code>	
. 214, 347, 354, 359		<code>\noexpand</code>	
N		<code>\null</code>	
<code>\NC@</code>	265, 269		
<code>\NC@char</code> 258, 259, 260,		O	
262, 264, 265, 266		<code>\OldMakeindex</code>	20
<code>\NC@do</code>	263, 274, 281	<code>\OnlyDescription</code> . .	19
<code>\NC@ecs</code>	331, 334	P	
<code>\NC@find</code>		<code>\PackageError</code>	249
. 268, 277, 280, 295		<code>\PackageWarning</code> 261, 264	
<code>\NC@ifend</code>	270, 271	<code>\par</code>	197
		<code>\prepnext@tok</code>	
		70, 90, 119, 135,	
		163, 166, 308, 333	
S		T	
<code>\save@decl</code> 72, 95, 163,		<code>\tabcolsep</code>	236
164, 298, 313, 330		<code>\tabular</code>	230
<code>\setlength</code> 171, 232, 344		<code>\tabular*</code>	230
<code>\showcols</code>	4, 281	<code>\tabularnewline</code> 197, 198	
<code>\string</code> 39, 258, 276, 278		<code>\the@toks</code>	
		. 57, 74, 76, 83,	
		165, 307, 326, 332	
		<code>\the@toksz</code>	57
U		U	
<code>\unhbox</code>	384	<code>\unhbox</code>	384
<code>\usebox</code>	378	<code>\usebox</code>	378
<code>\usepackage</code>	7	<code>\usepackage</code>	7

Change History

1994/12/08	v1.2a
<code>\@array</code> : add <code>\tabularnewline</code>	General: Completely new implementation. 1
v1.0b	v1.2b
General: ‘@classi (faster), ‘@classvi (new) A in preamble means && in ‘halign.	General: does no longer generate space at start or end of the preamble. Otherwise ‘hline is too long. 1
v1.1a	Enlarged ‘@arstrutbox by 1pt (Test-Impl) with dimen ‘@strutheight. 1
General: New concept: preamblechar: c,l,r,C,L,R,A,p,t,l,@,!	
v1.1b	v1.2c
General: Again p like original L ^A T _E X and z for centered ‘parbox.	General: Enlarged ‘@arstrutbox by ‘extrarowheight. Thus you may

	avoid large characters to overprint a ‘hline.	1	v1.9c	General: 1) ‘def ‘the@toks {‘the ...} remaining only in ‘@mkpream. 2) Removed ‘@classiii and replaced by ‘save@decl.	1
	Introduced ‘m@th in ‘@array to allow non-zero values of ‘mathsurround.	1		3) ‘insert@column contains only ‘@tempcnta and ‘count@ counters. 4) ‘@@startpbox and ‘@@endpbox now totally obsolete.	1
	New dimen parameter ‘extrarowheight (default: 0pt). .	1		Re-introduced ‘@endpbox. ‘multicolumn now works! Version number still 1.9 since the documentation is still not finished.	1
v1.2d	General: Completed the documentation.	1			
v1.2e	General: Bug fixed: A at start of preamble resulted in an error since ‘@mkpream generated ‘@arstrut & ... as a preamble. .	1			
v1.2f	General: ‘@testpach documented. .	1	v1.9d	General: Replaced ‘number by ‘the where the ‘toks registers’ contents are used.	1
v1.3a	General: Again a new implementation, with a new concept (cf. the documentation).	1	v1.9e	General: Re-introduced ‘@xargarraycr and ‘@yargarraycr, since ‘endtemplate seems to be ‘outer.	1
v1.3b	General: ‘@decl expands now into ‘@empty, i.e., it disappears when the preamble is generated, except when the user specifies A{} or B{}.	1	v1.9f	General: Small changes finally carried out: 1) ‘par=‘@empty. 2) {..ifnum0=}... → ‘bgroup and analogously ‘egroup.	1
v1.4a	General: Test implementation of use of token registers in order to do without ‘protect.	1	v1.9g	General: Inserted again {..ifnum0=}..., c.f. Appendix D of the T _E Xbook.	1
v1.4b	General: Changed erroneous class numbers: 5 -i 6 6 -i 7 7 -i 5 Corresponding changes in the macros.	1	v1.9h	General: No longer necessary to read in the file twice.	1
v1.4c	General: Everything except p,z now works with token registers. .	1	v1.9i	General: Corrected typo in german version.	1
v1.9a	General: 2) ‘protect is no longer necessary. But still the macro ‘@expast needs top be modified. ‘multicolumn still does not work.	1	v1.9j	General: In a ‘r’ column an extra ‘kern‘z@ is needed.	1
	Last (so I hope) major change: 1) Options B,A now called i,j. These options now point to the column they modify.	1	v1.9k	Otherwise the ‘hfil on the left side will be removed by the ‘unskip in ‘insert@column if the entry is empty.	1
v1.9b	General: inserted missing ‘fi in ‘@testpach. Corrected L _A T _E Xbug in ‘@tfor.	1		General: ‘beginMacro changed to ‘beginmacro in documentation. Corrected typo in german version.	1

v2.0a		v2.1c	
\@testpach: p option renamed to		\@startpbox: Use ‘everypar to	
m (middle).	9	insert strut	20
t option renamed to p to be		v2.2a	
compatible to the original.	9	\newcolumn: Now made	
General: \@thetoks changed to		‘newcolumn an error	26
\the@toks.	1	Removed ‘newcolumn	26
File renamed from array.sty to		General: Upgrade to L ^A T _E X 2 _ε	1
array.sty.	1	v2.2b	
source changed to reflect new		General: Removed interactive	
doc.sty conventions.	1	prompt	7
t option renamed to p to be		v2.2c	
compatible to the original.	1	General: removed check for \@tfor	
v2.0b		bug	1
General: All lines shortened to 72		v2.2d	
or less.	1	\@endpbox: Use	
Three forgotten end macro		L ^A T _E X 2 _ε \@finalstrut	20
added.	1	v2.2e	
v2.0c		\multicolumn: Added \null	24
\@classv: \relax added to avoid		v2.3a	
problem ‘the’toks0’the’toks1.	20	General: Added code for	
\@sharp: \relax added to avoid		\firsthline and friends	1
problem		v2.3c	
\the\toks0\the\toks1.	13	\@argarraycr: Avoid adding an	
\save@decl: \relax removed and		ord atom in math	23
added elsewhere.	12	Use \expandafter’s in	
v2.0d		conditional	23
\@tabular: ‘d@llar local to		\@arraycr: Avoid adding an ord	
preamble.	25	atom in math	23
\array: ‘d@llar local to preamble.	25	\@xarraycr: Avoid adding an ord	
v2.0e		atom in math	23
\@sharp: Added {} around		General: (DPC) minor doc changes	1
\@sharp for new ftset	13	v2.3d	
v2.0f		\@xhline: fix space between	
\@testpach: Argument removed		double rules pr/1945	32
since implicitly known	9	v2.3f	
Ensure to test a char which is		\@classz: (DPC) Extra \kern	
not active	10	keeps tabcolsep in empty l	
\the@toks: \@testpach now		columns internal/2122	17
without arg	14	v2.3g	
v2.0g		\@endpbox: Add \hfil for	
\d@llarend: ‘d@llarbegin defined		tools/2120	20
on toplevel.	24	v2.3h	
v2.0h		\firsthline: Complete	
\@sharp: Removed {} again in		reimplementation	31
favour of \d@llarbegin	13	\lasthline: Complete	
v2.1a		reimplementation	32
\@array: Hook for delarray added	22	v2.3i	
Wrong spec is now equiv to [t]	22	\@classz: Change both \kern\z@	
General: Newcolumn stuff added	26	to \hskip1sp for latex/2160	17
v2.1b		v2.3j	
\newcolumnntype: Macro renamed		\multicolumn: Command made	
from ‘newcolumn	26	\long to match kernel change	
		for pr/2180	23

v2.3k	(pr/4488)	25
\@startpbox: Use \setlength to set \hsize, so that the calc package can be applied here (pr/2793)	\d@llarend: \@halignto set locally (pr/4488)	24
	\tabular*: \@halignto set locally (pr/4488)	25
v2.3l	v2.4e	
\tabular*: Use \setlength evaluate arg so that the calc package can be applied here (pr/2793)	\@classz: Fixing SX68732	17
	\@mkpream: Fixing SX68732	29
	\@yargarraycr: Fixing SX68732	23
	\the@toks: Fixing SX68732	14
v2.3m	v2.4f	
\@array: Added \noexpand in front of \ialign to guard against interesting :-) changes to \halign done to support text glyphs in math	\@classz: Managing m-cells without \vcenter	17
	\@mkpream: Managing m-cells without \vcenter	29
v2.4a	\align@mccl: Managing m-cells without \vcenter	18
\arraybackslash: (DPC) Macro added (from tabularx)	\ar@cellbox: Macro added	32
v2.4b	\mcell@box: Managing m-cells without \vcenter	17
\NC@rewrite@*: Fix occasional spurious space (PR/3755)	\newcolumntype_lw: Column type added	33
v2.4c	\newcolumntype_lw: Column type added	33
General: (WR) Typo fix in documentation	\the@toks: Managing m-cells without \vcenter	14
v2.4d		
\array: \@halignto set locally		

References

- [1] M. GOOSSENS, F. MITTELBACH and A. SAMARIN. The L^AT_EX Companion. Addison-Wesley, Reading, Massachusetts, 1994.
- [2] D. E. KNUTH. The T_EXbook (Computers & Typesetting Volume A). Addison-Wesley, Reading, Massachusetts, 1986.
- [3] L. LAMPORT. L^AT_EX — A Document Preparation System. Addison-Wesley, Reading, Massachusetts, 1986.