NAME

tlmgr - the native TeX Live Manager

SYNOPSIS

tlmgr [option]... action [option]... [operand]...

DESCRIPTION

tlmgr manages an existing TeX Live installation, both packages and configuration options. For information on initially downloading and installing TeX Live, see http://tug.org/texlive/acquire.html.

The most up-to-date version of this documentation (updated nightly from the development sources) is available at http://tug.org/texlive/tlmgr.html, along with procedures for updating tlmgr itself and information about test versions.

TeX Live is organized into a few top-level *schemes*, each of which is specified as a different set of *collections* and *packages*, where a collection is a set of packages, and a package is what contains actual files. Schemes typically contain a mix of collections and packages, but each package is included in exactly one collection, no more and no less. A TeX Live installation can be customized and managed at any level.

See <http://tug.org/texlive/doc> for all the TeX Live documentation available.

EXAMPLES

After successfully installing TeX Live, here are a few common operations with tlmgr:

```
tlmgr option repository ctan
tlmgr option repository
```

http://mirror.ctan.org/systems/texlive/tlnet

Tell tlmgr to use a nearby CTAN mirror for future updates; useful if you installed TeX Live from the DVD image and want to have continuing updates. The two commands are equivalent; ctan is just an alias for the given url. Caveat: mirror.ctan.org resolves to many different hosts, and they are not perfectly synchronized; we recommend updating only daily (at most), and not more often.

```
tlmgr update --list
```

Report what would be updated without actually updating anything.

```
tlmgr update --all
```

Make your local TeX installation correspond to what is in the package repository (typically useful when updating from CTAN).

```
tlmgr info what
```

Display detailed information about a package *what*, such as the installation status and description, of searches for *what* in all packages.

For all the capabilities and details of tlmgr, please read the following voluminous information.

OPTIONS

The following options to tlmgr are global options, not specific to any action. All options, whether global or action-specific, can be given anywhere on the command line, and in any order. The first non-option argument will be the main action. In all cases, --option and -option are equivalent, and an = is optional between an option name and its value.

--repository url/path

Specifies the package repository from which packages should be installed or updated, overriding the default package repository found in the installation's TeX Live Package Database (a.k.a. the TLPDB, defined entirely in the file tlpkg/texlive.tlpdb). The documentation for install-tl has more details about this (http://tug.org/texlive/tug.org/texlive/doc/install-tl.html).

--repository changes the repository location only for the current run; to make a permanent change, use option repository (see the "option" action).

For backward compatibility and convenience, --location and --repo are accepted as aliases for this option.

--gui [action]

tlmgr has a graphical interface as well as the command line interface. You can give this option, --gui, together with an action to be brought directly into the respective screen of the GUI. For example, running

tlmgr --gui update

starts you directly at the update screen. If no action is given, the GUI will be started at the main screen.

--gui-lang llcode

By default, the GUI tries to deduce your language from the environment (on Windows via the registry, on Unix via LC_MESSAGES). If that fails you can select a different language by giving this option with a language code (based on ISO 639–1). Currently supported (but not necessarily completely translated) are: English (en, default), Czech (cs), German (de), French (fr), Italian (it), Japanese (ja), Dutch (nl), Polish (pl), Brazilian Portuguese (pt_BR), Russian (ru), Slovak (sk), Slovenian (sl), Serbian (sr), Ukrainian (uk), Vietnamese (vi), simplified Chinese (zh_CN), and traditional Chinese (zh_TW).

--debug-translation

In GUI mode, this switch tells tlmgr to report any untranslated (or missing) messages to standard error. This can help translators to see what remains to be done.

--machine-readable

Instead of the normal output intended for human consumption, write (to standard output) a fixed format more suitable for machine parsing. See the "MACHINE-READABLE OUTPUT" section below.

--no-execute-actions

Suppress the execution of the execute actions as defined in the tlpsrc files. Documented only for completeness, as this is only useful in debugging.

--package-logfile file

tlmgr logs all package actions (install, remove, update, failed updates, failed restores) to a separate log file, by default TEXMFSYSVAR/web2c/tlmgr.log. This option allows you to specify a different file for the log.

--pause

This option makes tlmgr wait for user input before exiting. Useful on Windows to avoid disappearing command windows.

--persistent-downloads

--no-persistent-downloads

For network-based installations, this option (on by default) makes tlmgr try to set up a persistent connection (using the LWP Perl module). The idea is to open and reuse only one connection per session between your computer and the server, instead of initiating a new download for each package.

If this is not possible, tlmgr will fall back to using wget. To disable these persistent connections, use --no-persistent-downloads.

--pin-file

Change the pinning file location from TEXMFLOCAL/tlpkg/pinning.txt (see "Pinning" below). Documented only for completeness, as this is only useful in debugging.

--require-verification

--no-require-verification

Instructs tlmgr to only accept signed and verified remotes. In any other case tlmgr will quit operation. See "CRYPTOGRAPHIC VERIFICATION" below for details.

--usermode

Activates user mode for this run of tlmgr; see "USER MODE" below.

--usertree *dir*

Uses *dir* for the tree in user mode; see "USER MODE" below.

--verify-downloads

--no-verify-downloads

Enables or disables cryptographic verification of downloaded database files. A working GnuPG (gpg) binary needs to be present in the path, otherwise this option has no effect. See "CRYPTOGRAPHIC VERIFICATION" below for details.

The standard options for TeX Live programs are also accepted: --help/-h/-?, --version, -q (no informational messages), -v (debugging messages, can be repeated). For the details about these, see the TeXLive::TLUtils documentation.

The --version option shows version information about the TeX Live release and about the tlmgr script itself. If -v is also given, revision number for the loaded TeX Live Perl modules are shown, too.

ACTIONS

help

Display this help information and exit (same as --help, and on the web at <http://tug.org/texlive/doc/tlmgr.html>). Sometimes the perldoc and/or PAGER programs on the system have problems, resulting in control characters being literally output. This can't always be detected, but you can set the NOPERLDOC environment variable and perldoc will not be used.

version

Gives version information (same as --version).

If -v has been given the revisions of the used modules are reported, too.

backup [--clean[=N]] [--backupdir dir] [--all | pkg]...

If the --clean option is not specified, this action makes a backup of the given packages, or all packages given --all. These backups are saved to the value of the --backupdir option, if

that is an existing and writable directory. If --backupdir is not given, the backupdir option setting in the TLPDB is used, if present. If both are missing, no backups are made.

If the -clean option is specified, backups are pruned (removed) instead of saved. The optional integer value N may be specified to set the number of backups that will be retained when cleaning. If N is not given, the value of the autobackup option is used. If both are missing, an error is issued. For more details of backup pruning, see the option action.

Options:

--backupdir directory

Overrides the backupdir option setting in the TLPDB. The *directory* argument is required and must specify an existing, writable directory where backups are to be placed.

--all

If -clean is not specified, make a backup of all packages in the TeX Live installation; this will take quite a lot of space and time. If -clean is specified, all packages are pruned.

--clean[=N]

Instead of making backups, prune the backup directory of old backups, as explained above. The optional integer argument N overrides the autobackup option set in the TLPDB. You must use --all or a list of packages together with this option, as desired.

--dry-run

Nothing is actually backed up or removed; instead, the actions to be performed are written to the terminal.

candidates pkg

candidates pkg

Shows the available candidate repositories for package *pkg*. See "MULTIPLE REPOSITORIES" below.

check [option]... [files|depends|executes|runfiles|all]

Executes one (or all) check(s) on the consistency of the installation.

files

Checks that all files listed in the local TLPDB (texlive.tlpdb) are actually present, and lists those missing.

depends

Lists those packages which occur as dependencies in an installed collection, but are themselves not installed, and those packages which are not contained in any collection.

If you call tlmgr check collections this test will be carried out instead since former versions for tlmgr called it that way.

executes

Check that the files referred to by execute directives in the TeX Live Database are present.

runfiles

List those filenames that are occurring more than one time in the runfiles sections.

Options:

--use-svn

Use the output of svn status instead of listing the files; for checking the TL development repository.

conf [texmf|tlmgr|updmap [--**conffile** *file*] [--**delete**] [*key* [*value*]]] =**head2 conf texmf** [--**conffile** *file*] **auxtrees [show|add|delete**] [*value*]

With only conf, show general configuration information for TeX Live, including active configuration files, path settings, and more. This is like running texconfig conf, but works on all supported platforms.

With one of conf texmf, conf tlmgr, or conf updmap, shows all key/value pairs (i.e., all settings) as saved in ROOT/texmf.cnf, the user-specific tlmgr configuration file (see below), or the first found (via kpsewhich) updmap.cfg file, respectively.

If key is given in addition, shows the value of only that key in the respective file. If option --delete is also given, the value in the given configuration file is entirely removed (not just commented out).

If value is given in addition, key is set to value in the respective file. No error checking is done!

Here is a practical example of changing configuration values. If the execution of (some or all) system commands via \write18 was left enabled during installation, you can disable it afterwards:

tlmgr conf texmf shell_escape 0

For texmf, an additional subcommand auxtrees allows adding and removing arbitrary additional texmf trees, completely under user control. texmf auxtrees show shows the list of additional trees, texmf auxtrees add *tree* adds a tree to the list, and texmf auxtrees remove *tree* removes a tree from the list (if present). The trees should not contain an ls-R file. This works by manipulating the Kpathsea variable TEXMFAUXTREES, in ROOT/texmf. Example:

tlmgr conf texmf auxtrees add /quick/test/tree
tlmgr conf texmf auxtrees remove /quick/test/tree

In all cases the configuration file can be explicitly specified via the option --conffile, if desired.

The PATH value shown by conf is as used by tlmgr. The directory in which the tlmgr executable is found is automatically prepended to the PATH value inherited from the environment.

Warning: The general facility is here, but tinkering with settings in this way is strongly discouraged. Again, no error checking on either keys or values is done, so any sort of breakage is possible.

dump-tlpdb [--local|--remote]

Dump complete local or remote TLPDB to standard output, as-is. The output is analogous to the --machine-readable output; see "MACHINE-READABLE OUTPUT" section.

Options:

--local

Dump the local TLPDB.

--remote

Dump the remote TLPDB.

Exactly one of --local and --remote must be given.

In either case, the first line of the output specifies the repository location, in this format:

"location-url" "\t" location

where location-url is the literal field name, followed by a tab, and *location* is the file or url to the repository.

Line endings may be either LF or CRLF depending on the current platform.

generate [option] ... what

generate language generate language.dat generate language.def generate language.dat.lua

The generate action overwrites any manual changes made in the respective files: it recreates them from scratch based on the information of the installed packages, plus local adaptions. The TeX Live installer and tlmgr routinely call generate for all of these files.

For managing your own fonts, please read the updmap --help information and/or <http://tug.org/fonts/fontinstall.html>.

For managing your own formats, please read the fmtutil --help information.

In more detail: generate remakes any of the configuration files language.dat, language.def, and language.dat.lua from the information present in the local TLPDB, plus locally-maintained files.

The locally-maintained files are language-local.dat, language-local.def, or language-local.dat.lua, searched for in TEXMFLOCAL in the respective directories. If local additions are present, the final file is made by starting with the main file, omitting any entries that the local file specifies to be disabled, and finally appending the local file.

(Historical note: The formerly supported updmap-local.cfg and fmtutil-local.cnf are no longer read, since updmap and fmtutil now reads and supports multiple configuration files. Thus, local additions can and should be put into an updmap.cfg of fmtutil.cnf file in TEXMFLOCAL. The generate updmap and generate fmtutil actions no longer exist.)

Local files specify entries to be disabled with a comment line, namely one of these:

```
%!NAME
--!NAME
```

where language.dat and language.def use %, and language.dat.lua use --. In all cases, the *name* is the respective format name or hyphenation pattern identifier. Examples:

```
%!german
--!usenglishmax
```

(Of course, you're not likely to actually want to disable those particular items. They're just examples.)

After such a disabling line, the local file can include another entry for the same item, if a different

definition is desired. In general, except for the special disabling lines, the local files follow the same syntax as the master files.

The form generate language recreates all three files language.dat, language.def, and language.dat.lua, while the forms with an extension recreates only that given language file.

Options:

--dest output_file

specifies the output file (defaults to the respective location in TEXMFSYSVAR). If --dest is given to generate language, it serves as a basename onto which .dat will be appended for the name of the language.dat output file, .def will be appended to the value for the name of the language.def output file, and .dat.lua to the name of the language.dat.lua file. (This is just to avoid overwriting; if you want a specific name for each output file, we recommend invoking tlmgr twice.)

```
--localcfg local_conf_file
```

specifies the (optional) local additions (defaults to the respective location in TEXMFLOCAL).

```
--rebuild-sys
```

```
tells tlmgr to run necessary programs after config files have been regenerated. These are:
fmtutil-sys --all after generate fmtutil, fmtutil-sys --byhyphen
.../language.dat after generate language.dat, and fmtutil-sys
--byhyphen .../language.def after generate language.def.
```

These subsequent calls cause the newly-generated files to actually take effect. This is not done by default since those calls are lengthy processes and one might want to made several related changes in succession before invoking these programs.

The respective locations are as follows:

```
tex/generic/config/language.dat (and language-local.dat)
tex/generic/config/language.def (and language-local.def)
tex/generic/config/language.dat.lua (and language-local.dat.lua)
```

gui

Start the graphical user interface. See GUI below.

info [option...] [collections|schemes|pkg...]

With no argument, lists all packages available at the package repository, prefixing those already installed with *i*.

With the single word collections or schemes as the argument, lists the request type instead of all packages.

With any other arguments, display information about pkg: the name, category, short and long description, installation status, and TeX Live revision number. If pkg is not locally installed, searches in the remote installation source.

If *pkg* is not found locally or remotely, the search action is used and lists matching packages and files.

It also displays information taken from the TeX Catalogue, namely the package version, date, and license. Consider these, especially the package version, as approximations only, due to timing skew of the updates of the different pieces. By contrast, the revision value comes directly

from TL and is reliable.

The former actions show and list are merged into this action, but are still supported for backward compatibility.

Options:

--list

If the option --list is given with a package, the list of contained files is also shown, including those for platform-specific dependencies. When given with schemes and collections, --list outputs their dependencies in a similar way.

--only-installed

If this option is given, the installation source will not be used; only locally installed packages, collections, or schemes are listed.

init-usertree

Sets up a texmf tree for so-called user mode management, either the default user tree (TEXMFHOME), or one specified on the command line with --usertree. See "USER MODE" below.

install [option] ... pkg...

Install each pkg given on the command line, if it is not already installed. (It does not touch existing packages; see the update action for how to get the latest version of a package.)

By default this also installs all packages on which the given pkgs are dependent. Options:

--dry-run

Nothing is actually installed; instead, the actions to be performed are written to the terminal.

--file

Instead of fetching a package from the installation repository, use the package files given on the command line. These files must be standard TeX Live package files (with contained tlpobj file).

--force

If updates to tlmgr itself (or other parts of the basic infrastructure) are present, tlmgr will bail out and not perform the installation unless this option is given. Not recommended.

--no-depends

Do not install dependencies. (By default, installing a package ensures that all dependencies of this package are fulfilled.)

--no-depends-at-all

Normally, when you install a package which ships binary files the respective binary package will also be installed. That is, for a package foo, the package foo.i386-linux will also be installed on an i386-linux system. This option suppresses this behavior, and also implies --no-depends. Don't use it unless you are sure of what you are doing.

--reinstall

Reinstall a package (including dependencies for collections) even if it already seems to be installed (i.e, is present in the TLPDB). This is useful to recover from accidental removal of files in the hierarchy.

When re-installing, only dependencies on normal packages are followed (i.e., not those of category Scheme or Collection).

--with-doc

--with-src

While not recommended, the install-tl program provides an option to omit installation of all documentation and/or source files. (By default, everything is installed.) After such an installation, you may find that you want the documentation or source files for a given package after all. You can get them by using these options in conjunction with --reinstall, as in (using the fontspec package as the example):

```
tlmgr install --reinstall --with-doc --with-src fontspec
```

key list|add file|remove keyid

The action key allows listing, adding and removing additional GPG keys to the set of trusted keys, that is, those that are used to verify the TeX Live databases.

With the list argument, key lists all keys.

The add argument requires another argument, either a filename or – for stdin, from which the key is added. The key is added to the local keyring GNUPGHOME/repository-keys.gpg, which is normally) tlpkg/gpg/repository-keys.gpg.

The remove argument requires a key id and removes the requested id from the local keyring.

option

option [show] option showall option *key* [*value*]

The first form shows the global TeX Live settings currently saved in the TLPDB with a short description and the key used for changing it in parentheses.

The second form is similar, but also shows options which can be defined but are not currently set to any value.

In the third form, if *value* is not given, the setting for *key* is displayed. If *value* is present, *key* is set to *value*.

Possible values for *key* are (run tlmgr option showall for the definitive list):

```
repository (default package repository),
formats (create formats at installation time),
postcode
           (run postinst code blobs)
docfiles (install documentation files),
srcfiles (install source files),
backupdir (default directory for backups),
autobackup (number of backups to keep).
sys_bin
           (directory to which executables are linked by the path action)
sys_man
           (directory to which man pages are linked by the path action)
sys_info
           (directory to which Info files are linked by the path action)
desktop_integration (Windows-only: create Start menu shortcuts)
fileassocs (Windows-only: change file associations)
multiuser
           (Windows-only: install for all users)
```

One common use of option is to permanently change the installation to get further updates from the Internet, after originally installing from DVD. To do this, you can run

tlmgr option repository http://mirror.ctan.org/systems/texlive/tlnet

The install-tl documentation has more information about the possible values for repository. (For backward compatibility, location can be used as alternative name for repository.)

If formats is set (this is the default), then formats are regenerated when either the engine or the format files have changed. Disable this only when you know what you are doing.

The postcode option controls execution of per-package postinstallation action code. It is set by default, and again disabling is not likely to be of interest except perhaps to developers.

The docfiles and srcfiles options control the installation of their respective files of a package. By default both are enabled (1). Either or both can be disabled (set to 0) if disk space is limited or for minimal testing installations, etc. When disabled, the respective files are not downloaded at all.

The options autobackup and backupdir determine the defaults for the actions update, backup and restore. These three actions need a directory in which to read or write the backups. If --backupdir is not specified on the command line, the backupdir option value is used (if set).

The autobackup option (de)activates automatic generation of backups. Its value is an integer. If the autobackup value is -1, no backups are removed. If autobackup is 0 or more, it specifies the number of backups to keep. Thus, backups are disabled if the value is 0. In the --clean mode of the backup action this option also specifies the number to be kept.

To setup autobackup to -1 on the command line, use:

tlmgr option -- autobackup -1

The -- avoids having the -1 treated as an option. (-- stops parsing for options at the point where it appears; this is a general feature across most Unix programs.)

The sys_bin, sys_man, and sys_info options are used on Unix-like systems to control the generation of links for executables, info files and man pages. See the path action for details.

The last three options control behavior on Windows installations. If desktop_integration is set, then some packages will install items in a sub-folder of the Start menu for tlmgr gui, documentation, etc. If fileassocs is set, Windows file associations are made (see also the postaction action). Finally, if multiuser is set, then adaptions to the registry and the menus are done for all users on the system instead of only the current user. All three options are on by default.

paper

paper [a4|letter]

[xdvi|pdftex|dvips|dvipdfmx|context|psutils] paper [papersize|--list]

With no arguments (tlmgr paper), shows the default paper size setting for all known programs.

With one argument (e.g., tlmgr paper a4), sets the default for all known programs to that paper size.

With a program given as the first argument and no paper size specified (e.g., tlmgr dvips paper), shows the default paper size for that program.

With a program given as the first argument and a paper size as the last argument (e.g., tlmgr

dvips paper a4), set the default for that program to that paper size.

With a program given as the first argument and --list given as the last argument (e.g., tlmgr dvips paper --list), shows all valid paper sizes for that program. The first size shown is the default.

Incidentally, this syntax of having a specific program name before the paper keyword is unusual. It is inherited from the longstanding texconfig script, which supports other configuration settings for some programs, notably dvips. tlmgr does not support those extra settings.

path [--w32mode=user|admin] [add|remove]

On Unix, merely adds or removes symlinks for binaries, man pages, and info pages in the system directories specified by the respective options (see the "option" description above). Does not change any initialization files, either system or personal.

On Windows, the registry part where the binary directory is added or removed is determined in the following way:

If the user has admin rights, and the option -w32mode is not given, the setting $w32_multi_user$ determines the location (i.e., if it is on then the system path, otherwise the user path is changed).

If the user has admin rights, and the option --w32mode is given, this option determines the path to be adjusted.

If the user does not have admin rights, and the option -w32mode is not given, and the setting $w32_multi_user$ is off, the user path is changed, while if the setting $w32_multi_user$ is on, a warning is issued that the caller does not have enough privileges.

If the user does not have admin rights, and the option --w32mode is given, it must be **user** and the user path will be adjusted. If a user without admin rights uses the option --w32mode admin a warning is issued that the caller does not have enough privileges.

pinning

The pinning action manages the pinning file, see "Pinning" below.

```
pinning show
```

Shows the current pinning data.

pinning add repo pkgglob...

Pins the packages matching the *pkgglob*(s) to the repository *repo*.

pinning remove repo pkgglob ...

Any packages recorded in the pinning file matching the <pkgglob>s for the given repository *repo* are removed.

```
pinning remove repo --all
```

Remove all pinning data for repository repo.

platform list|add|remove platform...

platform set platform

platform set auto

platform list lists the TeX Live names of all the platforms (a.k.a. architectures), (i386-linux, ...) available at the package repository.

platform add *platform*... adds the executables for each given platform *platform* to the installation from the repository.

platform remove *platform*... removes the executables for each given platform *platform* from the installation, but keeps the currently running platform in any case.

platform set *platform* switches TeX Live to always use the given platform instead of auto detection.

platform set auto switches TeX Live to auto detection mode for platform.

Platform detection is needed to select the proper xz, xzdec and wget binaries that are shipped with TeX Live.

arch is a synonym for platform.

Options:

--dry-run

Nothing is actually installed; instead, the actions to be performed are written to the terminal.

postaction [--w32mode=user|admin] [--fileassocmode=1|2] [--all] [install|remove] [shortcut|fileassoc|script] [pkg]...

Carry out the postaction shortcut, fileassoc, or script given as the second required argument in install or remove mode (which is the first required argument), for either the packages given on the command line, or for all if --all is given.

If the option --w32mode is given the value user, all actions will only be carried out in the user-accessible parts of the registry/filesystem, while the value admin selects the system-wide parts of the registry for the file associations. If you do not have enough permissions, using --w32mode=admin will not succeed.

--fileassocmode specifies the action for file associations. If it is set to 1 (the default), only new associations are added; if it is set to 2, all associations are set to the TeX Live programs. (See also option fileassocs.)

print-platform

Print the TeX Live identifier for the detected platform (hardware/operating system) combination to standard output, and exit. --print-arch is a synonym.

remove [option]... pkg...

Remove each pkg specified. Removing a collection removes all package dependencies (unless --no-depends is specified), but not any collection dependencies of that collection. However, when removing a package, dependencies are never removed. Options:

--no-depends

Do not remove dependent packages.

```
--no-depends-at-all
```

See above under install (and beware).

--force

By default, removal of a package or collection that is a dependency of another collection or scheme is not allowed. With this option, the package will be removed unconditionally. Use with care.

A package that has been removed using the --force option because it is still listed in an installed collection or scheme will not be updated, and will be mentioned as **forcibly removed** in the output of **tlmgr update** --**list**.

--dry-run

Nothing is actually removed; instead, the actions to be performed are written to the terminal.

repository

repository list repository list *path/tag* repository add *path* [*tag*] repository remove *path/tag* repository set *path*[#*tag*] [*path*[#*tag*] ...]

This action manages the list of repositories. See "MULTIPLE REPOSITORIES" below for detailed explanations.

The first form (list) lists all configured repositories and the respective tags if set. If a path, url, or tag is given after the list keyword, it is interpreted as source from where to initialize a TeX Live Database and lists the contained packages. This can also be an up-to-now not used repository, both locally and remote. If one pass in addition --with-platforms, for each package the available platforms (if any) are listed, too.

The third form (add) adds a repository (optionally attaching a tag) to the list of repositories. The forth form (remove) removes a repository, either by full path/url, or by tag. The last form (set) sets the list of repositories to the items given on the command line, not keeping previous settings

In all cases, one of the repositories must be tagged as main; otherwise, all operations will fail!

restore [--backupdir dir] [--all | pkg [rev]]

Restore a package from a previously-made backup.

If --all is given, try to restore the latest revision of all package backups found in the backup directory.

Otherwise, if neither pkg nor rev are given, list the available backup revisions for all packages. With pkg given but no rev, list all available backup revisions of pkg.

When listing available packages, tlmgr shows the revision, and in parenthesis the creation time if available (in format yyyy-mm-dd hh:mm).

If (and only if) both *pkg* and a valid revision number *rev* are specified, try to restore the package from the specified backup.

Options:

--all

Try to restore the latest revision of all package backups found in the backup directory. Additional non-option arguments (like pkg) are not allowed.

--backupdir directory

Specify the directory where the backups are to be found. If not given it will be taken from the configuration setting in the TLPDB.

--dry-run

Nothing is actually restored; instead, the actions to be performed are written to the terminal.

--force

Don't ask questions.

```
search [option ...] what
```

search [option...] ––file what

search [option...] --all what

By default, search the names, short descriptions, and long descriptions of all locally installed packages for the argument *what*, interpreted as a (Perl) regular expression.

Options:

--file

List all filenames containing what.

--all

Search everything: package names, descriptions and filenames.

--global

Search the TeX Live Database of the installation medium, instead of the local installation.

--word

Restrict the search of package names and descriptions (but not filenames) to match only full words. For example, searching for table with this option will not output packages containing the word tables (unless they also contain the word table on its own).

shell

Starts the TeX Live Manager Shell.

uninstall

Uninstalls the entire TeX Live installation. Options:

--force

Do not ask for confirmation, remove immediately.

update [option]... [pkg]...

Updates the packages given as arguments to the latest version available at the installation source. Either --all or at least one *pkg* name must be specified. Options:

--all

Update all installed packages except for tlmgr itself. Thus, if updates to tlmgr itself are present, this will simply give an error, unless also the option --force or --self is given. (See below.)

In addition to updating the installed packages, during the update of a collection the local installation is (by default) synchronized to the status of the collection on the server, for both additions and removals.

This means that if a package has been removed on the server (and thus has also been removed from the respective collection), tlmgr will remove the package in the local installation. This is called "auto-remove" and is announced as such when using the option --list. This auto-removal can be suppressed using the option --no-auto-remove (not recommended, see option description).

Analogously, if a package has been added to a collection on the server that is also installed locally, it will be added to the local installation. This is called "auto–install" and is

announced as such when using the option --list. This auto-installation can be suppressed using the option --no-auto-install.

An exception to the collection dependency checks (including the auto-installation of packages just mentioned) are those that have been "forcibly removed" by you, that is, you called tlmgr remove --force on them. (See the remove action documentation.) To reinstall any such forcibly removed packages use --reinstall-forcibly-removed.

If you want to exclude some packages from the current update run (e.g., due to a slow link), see the --exclude option below.

--self

Update tlmgr itself (that is, the infrastructure packages) if updates to it are present. On Windows this includes updates to the private Perl interpreter shipped inside TeX Live.

If this option is given together with either --all or a list of packages, then tlmgr will be updated first and, if this update succeeds, the new version will be restarted to complete the rest of the updates.

In short:

--dry-run

Nothing is actually installed; instead, the actions to be performed are written to the terminal. This is a more detailed report than --list.

--list [pkg]

Concisely list the packages which would be updated, newly installed, or removed, without actually changing anything. If --all is also given, all available updates are listed. If --self is given, but not --all, only updates to the critical packages (tlmgr, texlive infrastructure, perl on Windows, etc.) are listed. If neither --all nor --self is given, and in addition no *pkg* is given, then --all is assumed (thus, tlmgr update --list is the same as tlmgr update --list --all). If neither --all nor --self is given, but specific package names are given, those packages are checked for updates.

--exclude *pkg*

Exclude *pkg* from the update process. If this option is given more than once, its arguments accumulate.

An argument *pkg* excludes both the package *pkg* itself and all its related platform-specific packages *pkg.ARCH*. For example,

tlmgr update --all --exclude a2ping

will not update a2ping, a2ping.i386-linux, or any other a2ping.ARCH package.

If this option specifies a package that would otherwise be a candidate for auto-installation, auto-removal, or reinstallation of a forcibly removed package, tlmgr quits with an error message. Excludes are not supported in these circumstances.

--no-auto-remove [*pkg*]...

By default, t lmgr tries to remove packages which have disappeared on the server, as described above under --all. This option prevents such removals, either for all packages (with --all), or for just the given *pkg* names. This can lead to an inconsistent TeX installation, since packages are not infrequently renamed or replaced by their authors. Therefore this is not recommend.

--no-auto-install [pkg]...

Under normal circumstances tlmgr will install packages which are new on the server, as described above under --all. This option prevents any such automatic installation, either for all packages (with --all), or the given *pkg* names.

Furthermore, after the tlmgr run using this has finished, the packages that would have been auto-installed *will be considered as forcibly removed*. So, if foobar is the only new package on the server, then

tlmgr update --all --no-auto-install

is equivalent to

tlmgr update --all
tlmgr remove --force foobar

--reinstall-forcibly-removed

Under normal circumstances tlmgr will not install packages that have been forcibly removed by the user; that is, removed with remove --force, or whose installation was prohibited by --no-auto-install during an earlier update.

This option makes tlmgr ignore the forcible removals and re-install all such packages. This can be used to completely synchronize an installation with the server's idea of what is available:

tlmgr update --reinstall-forcibly-removed --all

--backup and --backupdir directory

These two options control the creation of backups of packages *before* updating; that is, backup of packages as currently installed. If neither of these options are given, no backup package will be saved. If --backupdir is given and specifies a writable directory then a backup will be made in that location. If only --backup is given, then a backup will be made to the directory previously set via the option action (see below). If both are given then a backup will be made to the specified *directory*.

You can set options via the option action to automatically create backups for all packages, and/or keep only a certain number of backups. Please see the option action for details.

tlmgr always makes a temporary backup when updating packages, in case of download or other failure during an update. In contrast, the purpose of this --backup option is to allow you to save a persistent backup in case the actual *content* of the update causes problems, e.g., introduces an incompatibility.

The restore action explains how to restore from a backup.

--no-depends

If you call for updating a package normally all depending packages will also be checked for updates and updated if necessary. This switch suppresses this behavior.

--no-depends-at-all

See above under **install** (and beware).

--force

Force update of normal packages, without updating tlmgr itself (unless the --self option is also given). Not recommended.

Also, update --list is still performed regardless of this option.

If the package on the server is older than the package already installed (e.g., if the selected mirror is out of date), tlmgr does not downgrade. Also, packages for uninstalled platforms are not installed.

tlmgr saves a copy of the texlive.tlpdb file used for an update with a suffix representing the repository url, as in tlpkg/texlive.tlpdb.*long-hash-string*. These can be useful for fallback information, but if you don't like them accumulating (e.g., mirror.ctan.org resolves to many different hosts, each resulting in a possibly different hash), it's harmless to delete them.

CONFIGURATION FILE FOR TLMGR

There are two configuration files for tlmgr: One is system-wide in TEXMFSYSCONFIG/tlmgr/config, and the other is user-specific in TEXMFCONFIG/tlmgr/config. The user-specific one is the default for the conf tlmgr action. (Run kpsewhich -var-value=TEXMFSYSCONFIG or ... TEXMFCONFIG ... to see the actual directory names.)

A few defaults corresponding to command-line options can be set in these configuration files. In addition, the system-wide file can contain a directive to restrict the allowed actions.

In these config files, empty lines and lines starting with # are ignored. All other lines must look like:

key = value

where the spaces are optional but the = is required.

The allowed keys are:

auto-remove, value 0 or 1 (default 1), same as command-line option.
gui-expertmode, value 0 or 1 (default 1). This switches between the full GUI and a
simplified GUI with only the most common settings.
gui-lang *llcode*, with a language code value as with the command-line option.
no-checksums, value 0 or 1 (default 0, see below).

```
persistent-downloads, value 0 or 1 (default 0), same as command-line option.
require-verification, value 0 or 1 (default 0), same as command-line option.
verify-downloads, value 0 or 1 (default 1), same as command-line option.
```

The system-wide config file can contain one additional key:

allowed-actions *action1* [,*action*,...] The value is a comma-separated list of tlmgr actions which are allowed to be executed when tlmgr is invoked in system mode (that is, without --usermode).

This allows distributors to include the tlmgr in their packaging, but allow only a restricted set of actions that do not interfere with their distro package manager. For native TeX Live installations, it doesn't make sense to set this.

The no-checksums key needs more explanation. By default, package checksums computed and stored on the server (in the TLPDB) are compared to checksums computed locally after downloading. That is, for each texlive.tlpdb loaded from a repository, the corresponding checksum file texlive.tlpdb.sha512 is also downloaded, and tlmgr confirms whether the checksum of the downloaded TLPDB file agrees with the download data. no-checksums disables this process.

The checksum algorithm is SHA-512. Your system must have one of (looked for in this order) the Perl Digest::SHA module, the openssl program (http://openssl.org), the sha512sum program (from GNU Coreutils, http://www.gnu.org/software/coreutils), or finally the shasum program (just to support old Macs). If none of these are available, a warning is issued and tlmgr proceeds without checking checksums. (Incidentally, other SHA implementations, such as the pure Perl and pure Lua modules, are much too slow to be usable in our context.) no-checksums avoids the warning.

CRYPTOGRAPHIC VERIFICATION

tlmgr and install-tl perform cryptographic verification if possible. If verification is performed and successful, the programs report (verified) after loading the TLPDB; otherwise, they report (not verified). Either way, by default the installation and/or updates proceed normally.

The attempted verification can be suppressed by specifying --no-verify-downloads on the command line, or the entry verify-downloads = 0 in a tlmgr config file (described in "CONFIGURATION FILE FOR TLMGR"). On the other hand, it is possible to *require* verification by specifying --require-verification on the command line, or require-verification = 1 in a tlmgr config file; in this case, if verification is not possible, the program quits.

Cryptographic verification requires checksum checking (described just above) to succeed, and a working GnuPG (gpg) program (see below for search method). Then, unless cryptographic verification has been disabled, a signature file (texlive.tlpdb.*.asc) of the checksum file is downloaded and the signature verified. The signature is created by the TeX Live Distribution GPG key 0x06BAB6BC, which in turn is signed by Karl Berry's key 0x30D155AD and Norbert Preining's key 0x6CACA448. All of these keys are obtainable from the standard key servers.

Additional trusted keys can be added using the key action.

Configuration of GnuPG invocation

The executable used for GnuPG is searched as follows: If the environment variable TL_GNUPG is set, it is tested and used; otherwise gpg is checked; finally gpg2 is checked.

Further adaptation of the gpg invocation can be made using the two environment variables TL_GNUPGHOME, which is passed to gpg as the value for --homedir, and TL_GNUPGARGS, which replaces the default options --no-secmem-warning --no-permission-warning.

USER MODE

tlmgr provides a restricted way, called "user mode", to manage arbitrary texmf trees in the same way as the main installation. For example, this allows people without write permissions on the installation location to update/install packages into a tree of their own.

tlmgr is switched into user mode with the command line option --usermode. It does not switch automatically, nor is there any configuration file setting for it. Thus, this option has to be explicitly given every time user mode is to be activated.

This mode of tlmgr works on a user tree, by default the value of the TEXMFHOME variable. This can be overridden with the command line option --usertree. In the following when we speak of the user tree we mean either TEXMFHOME or the one given on the command line.

Not all actions are allowed in user mode; tlmgr will warn you and not carry out any problematic actions. Currently not supported (and probably will never be) is the platform action. The gui action is currently not supported, but may be in a future release.

Some tlmgr actions don't need any write permissions and thus work the same in user mode and normal mode. Currently these are: check, help, list, print-platform, search, show, version.

On the other hand, most of the actions dealing with package management do need write permissions, and thus behave differently in user mode, as described below: install, update, remove, option, paper, generate, backup, restore, uninstall, symlinks.

Before using tlmgr in user mode, you have to set up the user tree with the init-usertree action. This creates *usertree*/web2c and *usertree*/tlpkg/tlpobj, and a minimal *usertree*/tlpkg/texlive.tlpdb. At that point, you can tell tlmgr to do the (supported) actions by adding the --usermode command line option.

In user mode the file *usertree*/tlpkg/texlive.tlpdb contains only the packages that have been installed into the user tree using tlmgr, plus additional options from the "virtual" package O0texlive.installation (similar to the main installation's texlive.tlpdb).

All actions on packages in user mode can only be carried out on packages that are known as relocatable. This excludes all packages containing executables and a few other core packages. Of the 2500 or so packages currently in TeX Live the vast majority are relocatable and can be installed into a user tree.

Description of changes of actions in user mode:

User mode install

In user mode, the install action checks that the package and all dependencies are all either relocated or already installed in the system installation. If this is the case, it unpacks all containers to be installed into the user tree (to repeat, that's either TEXMFHOME or the value of --usertree) and add the respective packages to the user tree's texlive.tlpdb (creating it if need be).

Currently installing a collection in user mode installs all dependent packages, but in contrast to normal mode, does *not* install dependent collections. For example, in normal mode tlmgr install collection-context would install collection-basic and other collections, while in user mode, *only* the packages mentioned in collection-context are installed.

If a package shipping map files is installed in user mode, a backup of the user's updmap.cfg in USERTREE/web2c/ is made, and then this file regenerated from the list of installed packages.

User mode backup, restore, remove, update

In user mode, these actions check that all packages to be acted on are installed in the user tree before proceeding; otherwise, they behave just as in normal mode.

User mode generate, option, paper

In user mode, these actions operate only on the user tree's configuration files and/or texlive.tlpdb. creates configuration files in user tree

MULTIPLE REPOSITORIES

The main TeX Live repository contains a vast array of packages. Nevertheless, additional local repositories can be useful to provide locally-installed resources, such as proprietary fonts and house styles. Also, alternative package repositories distribute packages that cannot or should not be included in TeX Live, for whatever reason.

The simplest and most reliable method is to temporarily set the installation source to any repository (with the -repository or option repository command line options), and perform your operations.

When you are using multiple repositories over a sustained length of time, however, explicitly switching between them becomes inconvenient. Thus, it's possible to tell tlmgr about additional repositories you want to use. The basic command is tlmgr repository add. The rest of this section explains further.

When using multiple repositories, one of them has to be set as the main repository, which distributes most of the installed packages. When you switch from a single repository installation to a multiple repository installation, the previous sole repository will be set as the main repository.

By default, even if multiple repositories are configured, packages are *still only* installed from the main repository. Thus, simply adding a second repository does not actually enable installation of anything from there. You also have to specify which packages should be taken from the new repository, by specifying so-called "pinning" rules, described next.

Pinning

When a package $f \circ \circ$ is pinned to a repository, a package $f \circ \circ$ in any other repository, even if it has a higher revision number, will not be considered an installable candidate.

As mentioned above, by default everything is pinned to the main repository. Let's now go through an example of setting up a second repository and enabling updates of a package from it.

First, check that we have support for multiple repositories, and have only one enabled (as is the case by default):

```
$ tlmgr repository list
List of repositories (with tags if set):
    /var/www/norbert/tlnet
```

Ok. Let's add the tlcontrib repository (this is a real repository, hosted at http://tlcontrib.metatex.org, maintained by Taco Hoekwater et al.), with the tag tlcontrib:

\$ tlmgr repository add http://tlcontrib.metatex.org/2012 tlcontrib

Check the repository list again:

```
$ tlmgr repository list
List of repositories (with tags if set):
    http://tlcontrib.metatex.org/2012 (tlcontrib)
    /var/www/norbert/tlnet (main)
```

Now we specify a pinning entry to get the package context from tlcontrib:

\$ tlmgr pinning add tlcontrib context

Check that we can find context:

```
$ tlmgr show context
tlmgr: package repositories:
...
package: context
repository: tlcontrib/26867
...
- install context:
$ tlmgr install context
tlmgr: package repositories:
...
[1/1, ??:??/??:??] install: context @tlcontrib [
```

In the output here you can see that the context package has been installed from the tlcontrib repository (@tlcontrib).

Finally, tlmgr pinning also supports removing certain or all packages from a given repository:

\$ tlmgr	pinning	remove	tlcontrib	context	#	remove just context
\$ tlmgr	pinning	remove	tlcontrib	all	#	take nothing from tlcontrib

A summary of the tlmgr pinning actions is given above.

GUI FOR TLMGR

The graphical user interface for tlmgr requires Perl/Tk

<http://search.cpan.org/search?query=perl%2Ftk>. For Windows the necessary modules are shipped within TeX Live, for all other (i.e., Unix-based) systems Perl/Tk (as well as Perl of course) has to be installed outside of TL. http://tug.org/texlive/distro.html#perltk> has a list of invocations for some distros.

The GUI is started with the invocation tlmgr gui; assuming Tk is loadable, the graphical user interface will be shown. The main window contains a menu bar, the main display, and a status area where messages normally shown on the console are displayed.

Within the main display there are three main parts: the Display configuration area, the list of packages, and the action buttons.

Also, at the top right the currently loaded repository is shown; this also acts as a button and when clicked will try to load the default repository. To load a different repository, see the tlmgr menu item.

Finally, the status area at the bottom of the window gives additional information about what is going on.

Main display

Display configuration area

The first part of the main display allows you to specify (filter) which packages are shown. By default, all are shown. Changes here are reflected right away.

Status

Select whether to show all packages (the default), only those installed, only those *not* installed, or only those with update available.

Category

Select which categories are shown: packages, collections, and/or schemes. These are briefly explained in the "DESCRIPTION" section above.

Match

Select packages matching for a specific pattern. By default, this searches both descriptions and filenames. You can also select a subset for searching.

Selection

Select packages to those selected, those not selected, or all. Here, "selected" means that the checkbox in the beginning of the line of a package is ticked.

Display configuration buttons

To the right there are three buttons: select all packages, select none (a.k.a. deselect all), and reset all these filters to the defaults, i.e., show all available.

Package list area

The second are of the main display lists all installed packages. If a repository is loaded, those that are available but not installed are also listed.

Double clicking on a package line pops up an informational window with further details: the long description, included files, etc.

Each line of the package list consists of the following items:

a checkbox

Used to select particular packages; some of the action buttons (see below) work only on the selected packages.

package name

The name (identifier) of the package as given in the database.

local revision (and version)

If the package is installed the TeX Live revision number for the installed package will be shown. If there is a catalogue version given in the database for this package, it will be shown in parentheses. However, the catalogue version, unlike the TL revision, is not guaranteed to reflect what is actually installed.

remote revision (and version)

If a repository has been loaded the revision of the package in the repository (if present) is shown. As with the local column, if a catalogue version is provided it will be displayed. And also as with the local column, the catalogue version may be stale.

short description

The short description of the package.

Main display action buttons

Below the list of packages are several buttons:

Update all installed

This calls tlmgr update --all, i.e., tries to update all available packages. Below this button is a toggle to allow reinstallation of previously removed packages as part of this action.

The other four buttons only work on the selected packages, i.e., those where the checkbox at the beginning of the package line is ticked.

Update

Update only the selected packages.

Install

Install the selected packages; acts like tlmgr install, i.e., also installs dependencies. Thus, installing a collection installs all its constituent packages.

Remove

Removes the selected packages; acts like tlmgr remove, i.e., it will also remove dependencies of collections (but not dependencies of normal packages).

Backup

Makes a backup of the selected packages; acts like tlmgr backup. This action needs the option backupdir set (see Options – General>).

Menu bar

The following entries can be found in the menu bar:

tlmgr menu

The items here load various repositories: the default as specified in the TeX Live database, the default network repository, the repository specified on the command line (if any), and an arbitrarily manually-entered one. Also has the so-necessary quit operation.

Options menu

Provides access to several groups of options: Paper (configuration of default paper sizes), Platforms (only on Unix, configuration of the supported/installed platforms), GUI Language (select language used in the GUI interface), and General (everything else).

Several toggles are also here. The first is Expert options, which is set by default. If you turn this off, the next time you start the GUI a simplified screen will be shown that display only the most important functionality. This setting is saved in the configuration file of tlmgr; see "CONFIGURATION FILE FOR TLMGR" for details.

The other toggles are all off by default: for debugging output, to disable the automatic installation of new packages, and to disable the automatic removal of packages deleted from the server. Playing with the choices of what is or isn't installed may lead to an inconsistent TeX Live installation; e.g., when a package is renamed.

Actions menu

Provides access to several actions: update the filename database (aka ls-R, mktexlsr, texhash), rebuild all formats (fmtutil-sys --all), update the font map database (updmap-sys), restore from a backup of a package, and use of symbolic links in system directories (not on Windows).

The final action is to remove the entire TeX Live installation (also not on Windows).

Help menu

Provides access to the TeX Live manual (also on the web at <<u>http://tug.org/texlive/doc.html></u>) and the usual "About" box.

GUI options

Some generic Perl/Tk options can be specified with tlmgr gui to control the display:

-background *color* Set background color. -font ``fontname fontsize ''

Set font, e.g., tlmgr gui -font "helvetica 18". The argument to -font must be quoted, i.e., passed as a single string.

-foreground color

Set foreground color.

-geometry geomspec

Set the X geometry, e.g., tlmgr gui -geometry 1024x512-0+0 creates the window of (approximately) the given size in the upper-right corner of the display.

```
-xrm xresource
```

Pass the arbitrary X resource string *xresource*.

A few other obscure options are recognized but not mentioned here. See the Perl/Tk documentation (<http://search.cpan.org/perldoc?Tk>) for the complete list, and any X documentation for general information.

MACHINE-READABLE OUTPUT

With the --machine-readable option, tlmgr writes to stdout in the fixed line-oriented format described here, and the usual informational messages for human consumption are written to stderr (normally they are written to stdout). The idea is that a program can get all the information it needs by reading stdout.

Currently this option only applies to the update, install, and "option" actions.

Machine-readable update and install output

The output format is as follows:

```
fieldname "\t" value
...
"end-of-header"
pkgname status localrev serverrev size runtime esttot
...
"end-of-updates"
other output from post actions, not in machine readable form
```

The header section currently has two fields: location-url (the repository source from which updates are being drawn), and total-bytes (the total number of bytes to be downloaded).

The *localrev* and *serverrev* fields for each package are the revision numbers in the local installation and server repository, respectively. The *size* field is the number of bytes to be downloaded, i.e., the size of the compressed tar file for a network installation, not the unpacked size. The runtime and esttot fields are only present for updated and auto-install packages, and contain the currently passed time since start of installation/updates and the estimated total time.

Line endings may be either LF or CRLF depending on the current platform.

```
location-url location
```

The *location* may be a url (including file:///foo/bar/...), or a directory name (/foo/bar). It is the package repository from which the new package information was drawn.

```
total-bytes count
```

The *count* is simply a decimal number, the sum of the sizes of all the packages that need updating or installing (which are listed subsequently).

Then comes a line with only the literal string end-of-header.

Each following line until a line with literal string end-of-updates reports on one package. The fields on each line are separated by a tab. Here are the fields.

pkgname

The TeX Live package identifier, with a possible platform suffix for executables. For instance, pdftex and pdftex.i386-linux are given as two separate packages, one on each line.

status

The status of the package update. One character, as follows:

- d The package was removed on the server.
- f The package was removed in the local installation, even though a collection depended on it. (E.g., the user ran tlmgr remove --force.)
- u Normal update is needed.
- r Reversed non-update: the locally-installed version is newer than the version on the server.
- a Automatically-determined need for installation, the package is new on the server and is (most probably) part of an installed collection.
- i Package will be installed and isn't present in the local installation (action install).
- I Package is already present but will be reinstalled (action install).

localrev

The revision number of the installed package, or – if it is not present locally.

serverrev

The revision number of the package on the server, or – if it is not present on the server.

size

The size in bytes of the package on the server. The sum of all the package sizes is given in the total-bytes header field mentioned above.

runtime

The run time since start of installations or updates.

esttot

The estimated total time.

Machine-readable option output

The output format is as follows:

key "\t" value

If a value is not saved in the database the string (not set) is shown.

If you are developing a program that uses this output, and find that changes would be helpful, do not hesitate to write the mailing list.

AUTHORS AND COPYRIGHT

This script and its documentation were written for the TeX Live distribution (<http://tug.org/texlive>) and both are licensed under the GNU General Public License Version 2 or later.