

Cheat sheet for **pst-optexp** (v3.3)

labeloffset=<num>
labelstyle=<macros>
labelalign=<refpoint>
labelangle=<num>
labelref=relative, relgrav, global, absolute
label=<offset>[<angle>[<refpoint>[<labelref>]]]
innerlabel=true
position=<num>, start, end
abspos=<num>, start, end
endbox=true, false
angle=<num>
rotateref=<refpoint>
compshift=<num>
OptComp<psstyle>
OptionalStyle<psstyle>
VariableStyle<psstyle>
addtoOptComp=<list>
newOptComp=<list>
optional=true, false

\lens[<opt>](<in>)(<out>){<label>}
lensheight=<num>
lensradiusleft=<num>
lensradiusright=<num>
lensradius=<left>[<right>]
lenswidth=<num>
lens=<radiusleft>[<radiusright>[<height>[
 <width>]]]
thicklens=true, false

\optplate[<opt>](<in>)(<out>){<label>}
plateheight=<num>
platelinewidth=<num> or <dimen>

\optretplate[<opt>](<in>)(<out>){<label>}
platewidth=<num>
platesize=<width> <height>

\pinhole[<opt>](<in>)(<out>){<label>}
outerheight=<num>
innerheight=<num>
phlinewidth=<num> or <dimen>

phwidth=<num>

\optbox[<opt>](<in>)(<out>){<label>}
optboxwidth=<num>
optboxheight=<num>
optboxsize=<width> <height>

\crystal[<opt>](<in>)(<out>){<label>}
crystalwidth=<num>
crystalheight=<num>
crystalsize=<width> <height>
caxislength=<num>
caxisinv=true, false
voltage=true, false
lamp=true, false
ampscale=<num>
CrystalCaxis<psstyle>
CrystalLamp<psstyle>

\optdetector[<opt>](<in>)(<out>){<label>}
detsize=<num> or <width> <height>
dettype=round, diode
DetectorStyle<psstyle>

\optdiode[<opt>](<in>)(<out>){<label>}
optdiodesize=<num>

\doveprism[<opt>](<in>)(<out>){<label>}
doveprismsize=<num> or <width> <height>

\glanthompson[<opt>](<in>)(<out>){<label>}
glothompsonwidth=<num>
glothompsonheight=<num>
glothompsonsize=<width> <height>
glothompsongap=<num>

\polarization[<opt>](<in>)(<out>){<label>}
polsize=<num>
pollinewidth=<num> or <dimen>
poltype=parallel, perp, misc, lcirc, rcirc
Polarization<psstyle>

\mirror[<opt>](<in>)(<center>)(<out>){<label>}
mirrorwidth=<num>
mirrorlinewidth=<num> or <dimen>
mirrорradius=<radius>[0]

mirrortype=plain, piezo, extended, semitrans
variable=true, false
mirrordepth=<num>
ExtendedMirror<psstyle>
PiezoMirror<psstyle>
SemitransMirror<psstyle>

\beam splitter[<opt>](<in>)(<center>)(<out>){<label>}
bssize=<num>
bsstyle=cube, plate

\optgrating[<opt>](<in>)(<center>)(<out>){<label>}
gratingwidth=<num>
gratingheight=<num>
gratingdepth=<num>
gratingcount=<int>
gratingtype=blazed, binary
gratingalign=t, top, c, center
reverse=true, false
gratinglinewidth=<num> or <dimen>

\optprism[<opt>](<in>)(<center>)(<out>){<label>}
prismsize=<num>
prismangle=<num>
prismalign=auto, center

\rightangleprism[<opt>](<in>)(<center>)(<out>){<label>}
raprismsize=<num>

\pentaprism[<opt>](<in>)(<center>)(<out>){<label>}
pentaprismsize=<num>
usefiberstyle=true, false

\optfiber[<opt>](<in>)(<out>){<label>}
fiberloops=<int>
fiberloopradius=<num>
fiberloopsep=<num>

\optamp[<opt>](<in>)(<out>){<label>}
optampsize=<num> or <width> <height>

\optmzm[<opt>](<in>)(<out>){<label>}
optmzmsize=<num> or <width> <height>

\polcontrol[<opt>](<in>)(<out>){<label>}
polcontrolsize=<num>

```

polcontroltype=linear, triangle
\optisolator[\langle opt \rangle](\langle in \rangle)(\langle out \rangle){\langle label \rangle}
  isolatorsize=\langle num \rangle or \langle width \rangle \langle height \rangle
  IsolatorArrow(psstyle)
\optswitch[\langle opt \rangle](\langle in \rangle)(\langle out \rangle){\langle label \rangle}
  switchsize=\langle num \rangle
  switchstyle=opened, closed
\fiberdelayline[\langle opt \rangle](\langle in \rangle)(\langle out \rangle){\langle label \rangle}
  fdlsize=\langle num \rangle or \langle width \rangle \langle height \rangle
  FdlArrow(psstyle)
\optfiberpolarizer[\langle opt \rangle](\langle in \rangle)(\langle out \rangle){\langle label \rangle}
  fiberpolsize=\langle num \rangle or \langle width \rangle \langle height \rangle
\optcirculator(\langle left \rangle)(\langle right \rangle)(\langle bottom \rangle){\langle label \rangle}
  optcircsize=\langle num \rangle
  optcircangleA=\langle num \rangle
  optcircangleB=\langle num \rangle
  optcircangle=\langle num \rangle \langle num \rangle
  OptCircArrow(psstyle)
\optcoupler(\langle tl \rangle)(\langle bl \rangle)(\langle tr \rangle)(\langle br \rangle){\langle label \rangle}
\wdmcoupler(\langle tl \rangle)(\langle bl \rangle)(\langle r \rangle){\langle label \rangle}
\wdmsplitter(\langle l \rangle)(\langle tr \rangle)(\langle br \rangle){\langle label \rangle}
  couplersize=\langle num \rangle or \langle width \rangle \langle height \rangle
  couplersep=\langle num \rangle
  couplertype=none, ellipse, rectangle, cross
  coupleralign=t, top, b, bottom, c, center
  align=top, bottom, center
  VariableCoupler(psstyle)
\fiberbox(\langle in \rangle)(\langle out \rangle){\langle label \rangle}
  fiberboxwidth=\langle num \rangle
  fiberboxheight=\langle num \rangle
  fiberboxsize=\langle width \rangle \langle height \rangle
  fiberboxsepin=\langle num \rangle
  fiberboxsepout=\langle num \rangle
  fiberboxcount=\langle N \rangle x \langle M \rangle
\optfilter[\langle opt \rangle](\langle in \rangle)(\langle out \rangle){\langle label \rangle}
  filtersize=\langle num \rangle
  filtertype=bandpass, bandstop, lowpass,
    highpass
  FilterStyle(psstyle)
\fibercollimator(\langle in \rangle)(\langle A \rangle)(\langle B \rangle)(\langle out \rangle){\langle label \rangle}
  fibercolsize=\langle num \rangle or \langle width \rangle \langle height \rangle
\oenode{\langle node \rangle}{\langle comp \rangle}
  namingscheme=old, new
  showoptdots=true, false
  compname=\langle string \rangle
\oenodeRefA{\langle comp \rangle}
\oenodeRefB{\langle comp \rangle}
\oenodeTrefA{\langle comp \rangle}
\oenodeTrefB{\langle comp \rangle}
\oenodeCenter{\langle comp \rangle}
\oenodeLabel{\langle comp \rangle}
\oenodeExt{\langle comp \rangle}
  extnode=\langle refpoint \rangle
  extnodealign=rel, relative, abs, absolute
\oenodeIfc{\langle num \rangle}{\langle comp \rangle}
\oenodeIn{\langle comp \rangle}
\oenodeOut{\langle comp \rangle}
\oenodeRotref{\langle comp \rangle}
\oenodeBeam{\langle num \rangle}
\oenodeBeamUp{\langle num \rangle}
\oenodeBeamLow{\langle num \rangle}
\oeBeamVec{\langle num \rangle}
\oeBeamVecUp{\langle num \rangle}
\oeBeamVecLow{\langle num \rangle}
\drawbeam[\langle options \rangle]{\langle obj_1 \rangle}{\langle obj_2 \rangle}...
  raytrace=true, false
  useNA=true, false
  n=\langle code \rangle
  refractiveindex=\langle code \rangle
  beampos=[\langle x \rangle ]\langle y \rangle
  beamangle=\langle pscode \rangle
  beamalign=rel, relative, abs, absolute
  beaminside=true, false
  beaminsidefirst=true, false
  beaminsidelast=true, false
  allowbeaminside=true, false
  forcebeaminside=true, false
\optplane(\langle center \rangle)
  beam=true, false
conn=\langle string \rangle
Beam\langle psstyle \rangle
addtoBeam=\langle list \rangle
newBeam=\langle list \rangle
ArrowInsideMinLength=\langle pscode \rangle
ArrowInsideMaxLength=\langle pscode \rangle
\drawwidebeam[\langle options \rangle]{\langle obj_1 \rangle}{\langle obj_2 \rangle}...
  beamwidth=\langle pscode \rangle
  beamdiv=\langle pscode \rangle
  pswarning=true, false
  savebeampoints=true, false, \langle int \rangle
  loadbeampoints=true, false, \langle int \rangle
  savebeam=true, false
  loadbeam=true, false
  startinside=true, false
  stopinside=true, false
\drawfiber[\langle options \rangle]{\langle obj_1 \rangle}{\langle obj_2 \rangle}...
  fiberalign=rel, relative, center, abs,
    absolute
  fiberangleA=\langle num \rangle
  fiberangleB=\langle num \rangle
  startnode=auto, N, 1, 2, ...
  stopnode=auto, N, 1, 2, ...
  Fiber\langle psstyle \rangle
  addtoFiber=\langle list \rangle
  newFiber=\langle list \rangle
  fiberstyle=\langle string \rangle
  fiber=[*+]none, all, i, o, \langle refpoint \rangle
\begin{optexp}...\end{optexp}
\backlayer{\langle code \rangle}
\frontlayer{\langle code \rangle}
\optdipole[\langle opt \rangle](\langle in \rangle)(\langle out \rangle){\langle label \rangle}
\opttripole[\langle opt \rangle](\langle in \rangle)(\langle center \rangle)(\langle out \rangle){\langle label \rangle}
  optdipolesize=\langle width \rangle [ \langle height \rangle ]
\newOptexpDipole[\langle fixopt \rangle]{\langle name \rangle}{\langle dftopt \rangle}
\newOptexpTripole[\langle fixopt \rangle]{\langle name \rangle}{\langle dftopt \rangle}
\newOptexpFiberDipole[\langle fixopt \rangle]{\langle name \rangle}{\langle dftopt \rangle}
  showifcnodes=true, false
  IfcNodeStyle\langle psstyle \rangle

```