

# Cheat sheet for `pst-optexp` (v5.0)

## General component parameters

`labeloffset=<num>`  
`labelstyle=<macros>`  
`labelalign=<refpoint>`  
`labelangle=<num>`  
`labelref=relative, relgrav, global, absolute`  
`label=<offset>[ <angle>[ <refpoint>[ <labelref>]]]`  
`innerlabel=true`  
`position=<num>, start, end`  
`abspos=<num>, start, end`  
`endbox=true, false`  
`angle=<pstype>`  
`rotateref=<refpoint>`  
`compshift=<num>`  
`compoffset=<num>`  
`innercompalign=rel, relative, abs, absolute`  
`OptComp <pstype>`  
`OptionalStyle <pstype>`  
`VariableStyle <pstype>`  
`addtoOptComp=<list>`  
`newOptComp=<list>`  
`optional=true, false`

## Free-ray components

`\lens[<opt>](<in>)(<out>){<label>}`  
  
`lensheight=<num>`  
`lensradiusleft=<num>`  
`lensradiusright=<num>`  
`lensradius=<left>[ <right>]`  
`lenswidth=<num>`  
`lens=<radiusleft>[ <radiusright>[ <height>[ <width>]]]`  
`thicklens=true, false`  
  
`\optplate[<opt>](<in>)(<out>){<label>}`  
`plateheight=<num>`  
`platelinewidth=<num> or <dimen>`  
  
`\optretplate[<opt>](<in>)(<out>){<label>}`

`platewidth=<num>`  
`platesize=<width> <height>`  
  
`\pinhole[<opt>](<in>)(<out>){<label>}`  
`outerheight=<num>`  
`innerheight=<num>`  
`phlinewidth=<num> or <dimen>`  
`phwidth=<num>`  
  
`\optbox[<opt>](<in>)(<out>){<label>}`  
`optboxwidth=<num>`  
`optboxheight=<num>`  
`optboxsize=<width> <height>`  
  
`\optarrowcomp[<opt>](<in>)(<out>){<label>}`  
`arrowcompwidth=<num>`  
`arrowcompheight=<num>`  
`arrowcompsize=<size> or <width> <height>`  
`arrowcompangle=<num>`  
`arrowcompshape=rectangle, circle`  
`ArrowCompStyle <pstype>`  
  
`\optbarcomp[<opt>](<in>)(<out>){<label>}`  
`barcompwidth=<num>`  
`barcompheight=<num>`  
`barcompsize=<size> or <width> <height>`  
`barcompangle=<num>`  
`barcompshape=rectangle, circle`  
`BarCompStyle <pstype>`  
  
`\optsource[<opt>](<in>)(<out>){<label>}`  
`sourcewidth=<num>`  
`sourceheight=<num>`  
`sourcesize=<width> <height>`  
  
`\crystal[<opt>](<in>)(<out>){<label>}`  
`crystalwidth=<num>`  
`crystalheight=<num>`  
`crystalsize=<width> <height>`  
`caxislength=<num>`  
`caxisinv=true, false`  
`voltage=true, false`  
`lamp=true, false`  
`CrystalCaxis <pstype>`  
`CrystalLamp <pstype>`  
  
`\optdiode[<opt>](<in>)(<out>){<label>}`  
`optdiodesize=<num>`  
  
`\doveprism[<opt>](<in>)(<out>){<label>}`  
`doveprismsize=<num> or <width> <height>`  
  
`\glanthonpson[<opt>](<in>)(<out>){<label>}`  
`glanthonpsonwidth=<num>`  
`glanthonpsonheight=<num>`  
`glanthonpsonsize=<width> <height>`  
`glanthonpsongap=<num>`  
  
`\polarization[<opt>](<in>)(<out>){<label>}`  
`polsize=<num>`  
`poltype=parallel, perp, misc, lcirc, rcirc`  
`Polarization <pstype>`  
  
`\mirror[<opt>](<in>)(<center>)(<out>){<label>}`  
`mirrorwidth=<num>`  
`mirrorlinewidth=<num> or <dimen>`  
`mirrorradius=<radius>[ 0]`  
`mirrortype=plain, piezo, extended, semitrans`  
`variable=true, false`  
`mirrordepth=<num>`  
`ExtendedMirror <pstype>`  
`PiezoMirror <pstype>`  
`SemitransMirror <pstype>`  
  
`\parabolicmirror[<opt>](<in>)(<out>){<label>}`  
`parmirrorwidth=<num>`  
`parmirrorheight=<num>`  
  
`\beamsplitter[<opt>](<in>)(<center>)(<out>){<label>}`  
`bssize=<num>`  
`bsstyle=cube, plate`  
  
`\optgrating[<opt>](<in>)(<center>)(<out>){<label>}`  
`gratingwidth=<num>`  
`gratingheight=<num>`  
`gratingdepth=<num>`  
`gratingcount=<int>`  
`gratingtype=blazed, binary`  
`gratingalign=t, top, c, center`  
`reverse=true, false`  
`gratinglinewidth=<num> or <dimen>`

```

\transmissionrating[<opt>](<in>)(<center>)(<out>){<label>} 
\optaom[<options>](<in>)(<trans>)(<diff>){<label>} 
  aomheight=<num>
  aomwidth=<num>
  aomsize=<width> <height>
  aomgratingcount=<int>
  aomalign=symmetric, straight
  aomrefalign=perp, parallel
  aomcomp=default, <macro>
  diffractionorders=<int>
  beamdiffractionorder=<int>

\optprism[<opt>](<in>)(<center>)(<out>){<label>} 
  prismsize=<num>
  prismangle=<num>
  prismtype=transmittive, reflective
  prismalign=auto, center

\rightangleprism[<opt>](<in>)(<center>)(<out>){<label>} OptCircArrow <psstyle>
  raprismsize=<num>
  raprismalign=auto, center

\pentaprism[<opt>](<in>)(<center>)(<out>){<label>} 
  pentaprismsize=<num>

```

## Fiber components

```

usefiberstyle=true, false
usewirestyle=true, false

\optfiber[<opt>](<in>)(<out>){<label>} 
  fiberloops=<int>
  fiberloopradius=<num>
  fiberloopsep=<num>

\optamp[<opt>](<in>)(<out>){<label>} 
  optampsiz=<num> or <width> <height>

\optmzm[<opt>](<in>)(<out>){<label>} 
  optmzmsize=<num> or <width> <height>

\polcontrol[<opt>](<in>)(<out>){<label>} 
  polcontrolsize=<num>
  polcontroltype=linear, triangle

\optisolator[<opt>](<in>)(<out>){<label>} 

```

```

  isolatorsize=<num> or <width> <height>
  IsolatorArrow <psstyle>

\optswitch[<opt>](<in>)(<out>){<label>} 
  switchsize=<num> or <width> <height>
  switchstyle=opened, closed

\fiberdelayline[<opt>](<in>)(<out>){<label>} 
  fdlsiz=<num> or <width> <height>
  FdlArrow <psstyle>

\optfiberpolarizer[<opt>](<in>)(<out>){<label>} 
  fiberpolsize=<num> or <width> <height>

\optcirculator[<left>](<right>)(<bottom>){<label>} 
  optcircsize=<num>
  optcircangleA=<num>
  optcircangleB=<num>
  optcircangle=<num> <num>

\optcoupler(<tl>)(<bl>)(<tr>)(<br>){<label>} 
\wdmcoupler(<tl>)(<bl>)(<r>){<label>} 
\wdmsplitter(<l>)(<tr>)(<br>){<label>} 
  couplersize=<num> or <width> <height>
  couplersep=<num>
  couplertype=none, ellipse, rectangle, cross
  coupleralign=t, top, b, bottom, c, center
  VariableCoupler <psstyle>

\fiberbox(<in>)(<out>){<label>} 
  fiberboxwidth=<num>
  fiberboxheight=<num>
  fiberboxsize=<width> <height>
  fiberboxsepin=<num>
  fiberboxsepout=<num>
  fiberboxcount=<N>x<M>
```

## Electrical components

```

\eleccoupler(<tl>)(<bl>)(<tr>)(<br>){<label>} 
  eleccouplersize=<size> or <width> <height>
  eleccouplersep=<num>
  eleccouplertype=standard, directional
  eleccouplerinput=left, right

```

```

\elecsynthesizer(<in>)(<out>){<label>} 
  synthsize=<size> or <width> <height>
  synthtype=sine, pulse, sawtooth, rectangle,
    triangle, custom
  synthshape=circle, rectangle
  SynthStyle <psstyle>
```

```

\elecmixer(<left>)(<right>)(<bottom>){<label>} 
  elecmixersize=<num>
```

## Hybrid components

```

\optfilter[<opt>](<in>)(<out>){<label>} 
  filtersize=<num>
  filtertype=bandpass, bandstop, lowpass,
    highpass
  filterangle=<num>
  FilterStyle <psstyle>

\fibercollimator(<in>)(<A>)(<B>)(<out>){<label>} 
  fibercolsiz=<num> or <width> <height>

\optdetector[<opt>](<in>)(<out>){<label>} 
  detsize=<num> or <width> <height>
  dettype=round, diode
  DetectorStyle <psstyle>
```

## Special nodes

```

\oenode{<node>}{<comp>} 
  namingscheme=old, new
  showoptdots=true, false
  compname=<string>

\oenodeRefA{<comp>} 
\oenodeRefB{<comp>} 
\oenodeTrefA{<comp>} 
\oenodeTrefB{<comp>} 
\oenodeCenter{<comp>} 
\oenodeLabel{<comp>} 
\oenodeExt{<comp>} 
  extnode=<refpoint>
  extnodealign=rel, relative, abs, absolute
```

```

extnodes=<list>
\oenodeIfc{\langle num \rangle}{\langle comp \rangle}
\oenodeIn{\langle comp \rangle}
\oenodeOut{\langle comp \rangle}
\oenodeRotref{\langle comp \rangle}
\oenodeBeam{\langle num \rangle}
\oenodeBeamUp{\langle num \rangle}
\oenodeBeamLow{\langle num \rangle}
\oeBeamCenter{\langle num \rangle}
\oeBeamVec{\langle num \rangle}
\oeBeamVecUp{\langle num \rangle}
\oeBeamVecLow{\langle num \rangle}
\oeBeamVecMedian{\langle num \rangle}

```

## Connecting components

```

\drawbeam[\langle options \rangle]{\langle obj_1 \rangle}{\langle obj_2 \rangle}...
raytrace=true, false
useNA=true, false
n=\langle code \rangle
beampos=[\langle x \rangle ]\langle y \rangle
beamangle=\langle pscode \rangle
beamalign=rel, relative, abs, absolute,
firstcomp
beampathskip=\langle num \rangle
beampathcount=\langle num \rangle
beaminside=true, false
beaminsidefirst=true, false
beaminsidelast=true, false
allowbeaminside=true, false
forcebeaminside=true, false
startinsidecount=\langle num \rangle
stopinsidecount=\langle num \rangle
beammode=refl, trans, reflective, transmittive,
auto
beamnodealign=vec, conn, vector, connection

\optplane{\langle center \rangle}
beam=true, false
Beam \langle psstyle \rangle
addtoBeam=\langle list \rangle
newBeam=\langle list \rangle

```

```

ArrowInsideMinLength=\langle pscode \rangle
ArrowInsideMaxLength=\langle pscode \rangle
fade \langle linestyle \rangle
fadeto=white, black, transparency
fadepoints=\langle num \rangle
fadefuncname=gauss, linear, squared, exp,
custom
fadefunc=\langle PS code \rangle

\drawwidebeam[\langle options \rangle]{\langle obj_1 \rangle}{\langle obj_2 \rangle}...
beamwidth=\langle pscode \rangle
beamdiv=\langle pscode \rangle
pswarning=true, false
savebeampoints=true, false, \langle int \rangle
loadbeampoints=true, false, \langle int \rangle
savebeam=true, false, \langle int \rangle
loadbeam=true, false, \langle int \rangle
startinside=true, false
stopinside=true, false

\drawfiber[\langle options \rangle]{\langle obj_1 \rangle}{\langle obj_2 \rangle}...
fiberalign=rel, relative, center, abs,
absolute
fiberangleA=\langle num \rangle
fiberangleB=\langle num \rangle
startnode=auto, N, 1, 2, ...
stopnode=auto, N, 1, 2, ...
Fiber \langle psstyle \rangle
addtoFiber=\langle list \rangle
newFiber=\langle list \rangle
fiberstyle=\langle string \rangle

\drawwire[\langle options \rangle]{\langle obj_1 \rangle}{\langle obj_2 \rangle}...
wirealign=rel, relative, center, abs,
absolute
wireangleA=\langle num \rangle
wireangleB=\langle num \rangle
wirestyle=\langle string \rangle
addtoWire=\langle list \rangle
newWire=\langle list \rangle
Wire \langle psstyle \rangle
fiber=[*+]none, all, i, o, \langle refpoint \rangle
wire=[*+]none, all, i, o, \langle refpoint \rangle

```

```

\begin{optexp} ... \end{optexp}
\backlayer{\langle code \rangle}
\frontlayer{\langle code \rangle}

```

## Custom components

```

\optdipole[\langle options \rangle]{\langle in \rangle}{\langle out \rangle}{\langle comp \rangle}{\langle label \rangle}
\opttripole[\langle options \rangle]{\langle in \rangle}{\langle center \rangle}{\langle out \rangle}{\langle comp \rangle}{\langle la
optdipolesize=\langle width \rangle[ \langle height \rangle ]
optdipolecomp=\langle macros \rangle
opttripolecomp=\langle macros \rangle

\newOptexpDipole[\langle fixopt \rangle]{\langle name \rangle}{\langle dftopt \rangle}
\newOptexpTripole[\langle fixopt \rangle]{\langle name \rangle}{\langle dftopt \rangle}
\newOptexpFiberDipole[\langle fixopt \rangle]{\langle name \rangle}{\langle dftopt \rangle}
\newOptexpElecDipole[\langle fixopt \rangle]{\langle name \rangle}{\langle dftopt \rangle}

```

## Additional information

```

showifcnodes=true, false
IfcNodeStyle \langle psstyle \rangle
showinterfaces=true, false
IfcStyle \langle psstyle \rangle

```