# NAME

fmtutil.cnf - configuration file for fmtutil

## DESCRIPTION

The *fmtutil.cnf* file contains the configuration information for **fmtutil**(8). Each line contains the name of the format (e.g., "tex", "latex", "omega"), the name of the engine that is used by that format (e.g., "tex", "etex", "omega"), the pattern file (e.g., *language.dat*, *language.def*), and any arguments (name of an *.ini* file).

Fields are separated by whitespace and complete lines can be commented out with "#". The "pattern file" field cannot be used to define a file that is used while building the format. It tells **fmtutil** which file the format creation procedure reads and it has an effect to the options *--showhyphen* and *--byhyphen*. If the format has no way to customize hyphenation, a "-" can be used to indicate this.

## NOTES

The tex(1) and amstex(1) formats always load *hyphen.tex*. No customization by a pattern file is available for these formats. Therefore, the pattern-file field for the **tex** and **amstex** is usually indicated to be empty ("--").

You can, however, build customized formats on top of plain tex(1) or amstex(1) by using *bplain.tex* instead of *plain.tex* (b for the *Babel* system). See, for example, the *bplain.ini* file for the bplain format).

etex(1) loads *language.def*, not *language.dat*.

Symbolic links to the correct engines (e.g., bplain -> tex) are generated by the **texlinks**(8) script. Remember to run **texlinks**(8) if you run **fmtutil**(8) yourself, rather than using the FORMATS option in **texconfig**(8).

## FILES

fmtutil.cnf

default configuration file

language.dat

hyphenation pattern file

language.def

hyphenation pattern file

#### **SEE ALSO**

amstex(1), etex(1), fmtutil(8), tex(1), texconfig(8), texlinks(8).

Web page: <http://tug.org/teTeX/>

## BUGS

None known, but report any bugs found to <tetex@dbs.uni-hannover.de> (mailing list).

#### AUTHOR

*fmtutil.cnf* was written by Thomas Esser <te@dbs.uni-hannover.de>, and is Copyright 1998, 1999 but released into the public domain.

This manual page was written by C.M. Connelly  $\langle c@eskimo.com \rangle$ , for the Debian GNU/Linux system. It may be used by other distributions without contacting the author. Any mistakes or

omissions in the manual page are my fault; inquiries about or corrections to this manual page should be directed to me (and not to the primary author).