NAME

etex – extended (plain) TeX

SYNOPSIS

etex [options] [&format] [file|\commands]

DESCRIPTION

Run the e-T_EX typesetter on *file*, by default creating *file.dvi*. If the file argument has no extension, ".tex" will be appended to it. Instead of a filename, a set of e-T_EX commands can be given, the first of which must start with a backslash. With a & *format* argument e-T_EX uses a different set of precompiled commands, contained in *format*.fmt; it is usually better to use the -fmt *format* option instead.

e-T_EX is the first concrete result of an international research & development project, the NTS Project, which was established under the aegis of DANTE e.V. during 1992. The aims of the project are to perpetuate and develop the spirit and philosophy of T_EX, whilst respecting Knuth's wish that T_EX should remain frozen.

e-T_EX can be used in two different modes: in *compatibility mode* it is supposed to be completely interchangable with standard T_EX. In *extended mode* several new primitives are added that facilitate (among other things) bidirectional typesetting.

An extended mode format is generated by prefixing the name of the source file for the format with an asterisk (*).

e-T_EX's handling of its command-line arguments is similar to that of the other T_EX programs in the *web2c* implementation.

OPTIONS

This version of e-T_EX understands the following command line options.

-fmt format

Use *format* as the name of the format to be used, instead of the name by which e-T_EX was called or a %& line.

-enc Enable the encT_EX extensions. This option is only effective in combination with -ini. For documentation of the encT_EX extensions see http://www.olsak.net/enctex.html.

-etex Enable the e-T_EX extensions. This option is only effective in combination with **-ini**.

-file-line-error

Print error messages in the form *file:line:error* which is similar to the way many compilers format them.

-no-file-line-error

Disable printing error messages in the file:line:error style.

-file-line-error-style

This is the old name of the **-file-line-error** option.

-halt-on-error

Exit with an error code when an error is encountered during processing.

-help Print help message and exit.

-ini Start in *INI* mode, which is used to dump formats. The *INI* mode can be used for type-setting, but no format is preloaded, and basic initializations like setting catcodes may be required.

-interaction mode

Sets the interaction mode. The mode can be either *batchmode*, *nonstopmode*, *scrollmode*, and *errorstopmode*. The meaning of these modes is the same as that of the corresponding \commands.

-ipc Send DVI output to a socket as well as the usual output file. Whether this option is available is the choice of the installer.

-ipc-start

As **-ipc**, and starts the server at the other end as well. Whether this option is available is the choice of the installer.

-jobname name

Use *name* for the job name, instead of deriving it from the name of the input file.

-kpathsea-debug bitmask

Sets path searching debugging flags according to the bitmask. See the *Kpathsea* manual for details.

-mktex fmt

Enable mktex fmt, where fmt must be either tex or tfm.

-mltex Enable MLT_EX extensions. Only effective in combination with -ini.

-no-mktex fmt

Disable mktex fmt, where fmt must be either tex or tfm.

-output-comment string

Use *string* for the *DVI* file comment instead of the date.

-output-directory *directory*

Write output files in *directory* instead of the current directory. Look up input files in *directory* first, the along the normal search path.

-parse-first-line

If the first line of the main input file begins with %& parse it to look for a dump name or a **-translate-file** option.

-no-parse-first-line

Disable parsing of the first line of the main input file.

-progname name

Pretend to be program *name*. This affects both the format used and the search paths.

-recorder

Enable the filename recorder. This leaves a trace of the files opened for input and output in a file with extension .fls.

-shell-escape

Enable the \write18{command} construct. The *command* can be any shell command. This construct is normally disallowed for security reasons.

-no-shell-escape

Disable the \write18{command} construct, even if it is enabled in the texmf.cnf file.

-src-specials

Insert source specials into the DVI file.

-src-specials where

Insert source specials in certain placed of the *DVI* file. *where* is a comma-separated value list: *cr*, *display*, *hbox*, *math*, *par*, *parent*, or *vbox*.

-translate-file texname

Use the *tcxname* translation table to set the mapping of input characters and re-mapping of output characters.

-default-translate-file texname

Like **-translate-file** except that a %& line can overrule this setting.

-version

Print version information and exit.

ENVIRONMENT

See the Kpathsearch library documentation (the 'Path specifications' node) for precise details of how the environment variables are used. The **kpsewhich** utility can be used to query the values of the variables.

One caveat: In most e-TeX formats, you cannot use ~ in a filename you give directly to e-TeX, because ~ is an active character, and hence is expanded, not taken as part of the filename. Other programs, such as METAFONT, do not have this problem.

TEXMFOUTPUT

Normally, e-T_EX puts its output files in the current directory. If any output file cannot be opened there, it tries to open it in the directory specified in the environment variable TEXMFOUTPUT. There is no default value for that variable. For example, if you say *etex paper* and the current directory is not writable, if TEXMFOUTPUT has the value /tmp, e-T_EX attempts to create /tmp/paper.log (and /tmp/paper.dvi, if any output is produced.) TEXMFOUTPUT is also checked for input files, as T_EX often generates files that need to be subsequently read; for input, no suffixes (such as ".tex") are added by default, the input name is simply checked as given.

TEXINPUTS

Search path for \input and \openin files. This should start with ".", so that user files are found before system files. An empty path component will be replaced with the paths defined in the *texmf.cnf* file. For example, set TEXINPUTS to ".:/home/user/tex:" to prepend the current direcory and "/home/user/tex" to the standard search path.

TEXFORMATS

Search path for format files.

TEXPOOL

search path for etex internal strings.

TEXEDIT

Command template for switching to editor. The default, usually **vi**, is set when e-T_EX is compiled.

TFMFONTS

Search path for font metric (.tfm) files.

FILES

The location of the files mentioned below varies from system to system. Use the **kpsewhich** utility to find their locations.

etex.pool

Text file containing e-T_FX's internal strings.

texfonts.map

Filename mapping definitions.

*.tfm Metric files for e-T_EX's fonts.

*.fmt Predigested e-TEX format (. fmt) files.

NOTES

Starting with version 1.40, pdfT_EX incorporates the e-T_EX extensions, so in this installation eT_EX may be just a symbolic link to pdfT_EX. See **pdftex**(1). This manual page is not meant to be exhaustive. The complete documentation for this version of e-T_EX can be found in the info manual *Web2C*: A TeX implementation.

BUGS

This version of e-T_EX implements a number of optional extensions. In fact, many of these extensions conflict to a greater or lesser extent with the definition of e-T_EX. When such extensions are enabled, the banner printed when e-T_EX starts is changed to print **e-TeXk** instead of **e-TeX**.

This version of e-T_EX fails to trap arithmetic overflow when dimensions are added or subtracted. Cases where this occurs are rare, but when it does the generated *DVI* file will be invalid.

SEE ALSO

```
pdftex(1), tex(1), mf(1).
```

AUTHORS

e-T_EX was developed by Peter Breitenlohner and the NTS team; Peter later continued its development outside of the team.

TEX was designed by Donald E. Knuth, who implemented it using his WEB system for Pascal programs. It was ported to Unix at Stanford by Howard Trickey, and at Cornell by Pavel Curtis. The version now offered with the Unix TeX distribution is that generated by the WEB to C system (web2c), originally written by Tomas Rokicki and Tim Morgan.

The encTeX extensions were written by Petr Olsak.